Veritas Storage Foundation™ and High Availability Solutions 6.0

Solutions Guide

Linux



Veritas Storage Foundation and High Availability Solutions Guide

The software described in this book is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

Product version: 6.0

Document version: 6.0.4

Legal Notice

Copyright © 2012 Symantec Corporation. All rights reserved.

Symantec, the Symantec logo, Veritas, Veritas Storage Foundation, CommandCentral, NetBackup, Enterprise Vault, and LiveUpdate are trademarks or registered trademarks of Symantec corporation or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Symantec Corporation and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. SYMANTEC CORPORATION SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, "Rights in Commercial Computer Software or Commercial Computer Software Documentation", as applicable, and any successor regulations. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Symantec Corporation 350 Ellis Street Mountain View, CA 94043

http://www.symantec.com

Technical Support

Symantec Technical Support maintains support centers globally. Technical Support's primary role is to respond to specific queries about product features and functionality. The Technical Support group also creates content for our online Knowledge Base. The Technical Support group works collaboratively with the other functional areas within Symantec to answer your questions in a timely fashion. For example, the Technical Support group works with Product Engineering and Symantec Security Response to provide alerting services and virus definition updates.

Symantec's support offerings include the following:

- A range of support options that give you the flexibility to select the right amount of service for any size organization
- Telephone and/or Web-based support that provides rapid response and up-to-the-minute information
- Upgrade assurance that delivers software upgrades
- Global support purchased on a regional business hours or 24 hours a day, 7 days a week basis
- Premium service offerings that include Account Management Services

For information about Symantec's support offerings, you can visit our Web site at the following URL:

www.symantec.com/business/support/index.jsp

All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policy.

Contacting Technical Support

Customers with a current support agreement may access Technical Support information at the following URL:

www.symantec.com/business/support/contact techsupp static.jsp

Before contacting Technical Support, make sure you have satisfied the system requirements that are listed in your product documentation. Also, you should be at the computer on which the problem occurred, in case it is necessary to replicate the problem.

When you contact Technical Support, please have the following information available:

Product release level

- Hardware information
- Available memory, disk space, and NIC information
- Operating system
- Version and patch level
- Network topology
- Router, gateway, and IP address information
- Problem description:
 - Error messages and log files
 - Troubleshooting that was performed before contacting Symantec
 - Recent software configuration changes and network changes

Licensing and registration

If your Symantec product requires registration or a license key, access our technical support Web page at the following URL:

www.symantec.com/business/support/

Customer service

Customer service information is available at the following URL:

www.symantec.com/business/support/

Customer Service is available to assist with non-technical questions, such as the following types of issues:

- Questions regarding product licensing or serialization
- Product registration updates, such as address or name changes
- General product information (features, language availability, local dealers)
- Latest information about product updates and upgrades
- Information about upgrade assurance and support contracts
- Information about the Symantec Buying Programs
- Advice about Symantec's technical support options
- Nontechnical presales questions
- Issues that are related to CD-ROMs or manuals

Support agreement resources

If you want to contact Symantec regarding an existing support agreement, please contact the support agreement administration team for your region as follows:

Asia-Pacific and Japan customercare_apac@symantec.com

Europe, Middle-East, and Africa semea@symantec.com

North America and Latin America supportsolutions@symantec.com

Documentation

Your feedback on product documentation is important to us. Send suggestions for improvements and reports on errors or omissions. Include the title and document version (located on the second page), and chapter and section titles of the text on which you are reporting. Send feedback to:

doc_feedback@symantec.com

About Symantec Connect

Symantec Connect is the peer-to-peer technical community site for Symantec's enterprise customers. Participants can connect and share information with other product users, including creating forum posts, articles, videos, downloads, blogs and suggesting ideas, as well as interact with Symantec product teams and Technical Support. Content is rated by the community, and members receive reward points for their contributions.

http://www.symantec.com/connect/storage-management

Contents

Technical Sup	pport	4
Section 1	Solutions for Veritas Storage Foundation and High Availability products	13
Chapter 1	Solutions for Veritas Storage Foundation and High Availability products	15
	About Storage Foundation and High Availability Solutions	17 19
Section 2	Improving database performance	21
Chapter 2	Overview of database accelerators	23
	About Storage Foundation and High Availability Solutions products database accelerators	23
Chapter 3	Improving database performance with Veritas Concurrent I/O	25
	About Concurrent I/O	
	How Concurrent I/O works	
	Tasks for enabling and disabling Concurrent I/O	
	Enabling Concurrent I/O for DB2	
	Disabling Concurrent I/O for DB2 Enabling Concurrent I/O for Sybase	
	Disabling Concurrent I/O for Sybase	

Section 3	Using point-in-time copies	31
Chapter 4	Understanding point-in-time copy methods	33
	About point-in-time copies Implementing point-in time copy solutions on a primary	
	host	
	Implementing off-host point-in-time copy solutions	
	About Storage Foundation point-in-time copy technologies	
	Volume-level snapshots	
	Storage Checkpoints	
	About FileSnaps	
Chapter 5	Backing up and recovering	47
	About Storage Foundation and High Availability Solutions backup and recovery use cases	47
	Creating and maintaining a full image snapshot and incremental	
	point-in-time copies	
	copies	
	Refreshing point-in-time copies	
	Recovering from logical corruption	
	Online database backups	
	Making a backup of an online database on the same host	
	Making an off-host backup of an online database	
	Backing up on an off-host cluster file system	
	Mounting a file system for shared access	
	Preparing a snapshot of a mounted file system with shared	
	accessBacking up a snapshot of a mounted file system with shared	/8
	access	80
	Resynchronizing a volume from its snapshot volume	83
	Reattaching snapshot plexes	84
	Database recovery using Storage Checkpoints	85
	Creating Storage Checkpoints	86
	Rolling back a database	87

Chapter 6	Backing up and recovering in a NetBackup environment	89
	About Veritas NetBackup	89
	About using Veritas NetBackup for backup and restore for DB2	
	About using NetBackup for backup and restore for Sybase	91
	Using NetBackup in an SFHA Solutions product environment	
	Clustering a NetBackup Master Server	92
	Backing up and recovering a VxVM volume using NetBackup	വാ
	Recovering a VxVM volume using NetBackup	
	Recovering a VAVWI volume using Netbackup	93
Chapter 7	Off-host processing	97
	Storage Foundation off-host processing methods	97
	Using a replica database for decision support	98
	Creating a replica database on the same host	
	Creating an off-host replica database	
	What is off-host processing?	
	About using VVR for off-host processing	120
Chapter 8	Creating and refreshing test environments	121
	About test environments	121
	Creating a test environment	
	Refreshing a test environment	122
Chapter 9	Creating point-in-time copies of files	125
	Using FileSnaps to create point-in-time copies of files	125
	Using FileSnaps to provision virtual desktops	
	Using FileSnaps to optimize write intensive applications for	
	virtual machines	126
	Using FileSnaps to create multiple copies of data instantly	126
Section 4	Maximizing storage utilization	129
Chapter 10	Optimizing storage tiering with SmartTier	131
•	About SmartTier	
	SmartTier building blocks	
	About VxFS multi-volume file systems	
	About VxVM volume sets	
	About volume tags	

	SmartTier use cases for DB2 or Sybase	134
	Setting up a filesystem for storage tiering with SmartTier	134
	Relocating old archive logs to tier two storage using SmartTier	
	Relocating inactive tablespaces or segments to tier two storage	
	Relocating active indexes to premium storage	
	Relocating all indexes to premium storage	144
Section 5	Migrating data	149
Chapter 11	Understanding data migration	151
	Types of data migration	151
Chapter 12	Offline migration from LVM to VxVM	153
	About migration from LVM	152
	Converting unused LVM physical volumes to VxVM disks	
	LVM volume group to VxVM disk group conversion	
	Volume group conversion limitations	
	Converting LVM volume groups to VxVM disk groups	
	Examples of second stage failure analysis	
	LVM volume group restoration	
	Restoring an LVM volume group	
Chapter 13	Migrating storage arrays	173
	Array migration for storage using Linux	173
	Overview of storage mirroring for migration	
	Allocating new storage	175
	Initializing the new disk	177
	Checking the current VxVM information	
	Adding a new disk to the disk group	
	Mirroring	
	Monitoring	
	Mirror completion	
	Removing old storage	
	Post-mirroring steps	183
Chapter 14	Migrating data between platforms	185
	Overview of the Cross-Platform Data Sharing (CDS) feature	
	Shared data across platforms	
	Disk drive sector size	
	Block size issues	187

	Operating system data	187
	CDS disk format and disk groups	187
	CDS disk access and format	188
	Non-CDS disk groups	191
	Disk group alignment	191
	Setting up your system to use Cross-platform Data Sharing	
	(CDS)	193
	Creating CDS disks from uninitialized disks	194
	Creating CDS disks from initialized VxVM disks	195
	Creating CDS disk groups	196
	Converting non-CDS disks to CDS disks	197
	Converting a non-CDS disk group to a CDS disk group	198
	Verifying licensing	200
	Defaults files	200
	Maintaining your system	202
	Disk tasks	203
	Disk group tasks	205
	Displaying information	211
	Default activation mode of shared disk groups	214
	Additional considerations when importing CDS disk groups	214
	File system considerations	215
	Considerations about data in the file system	216
	File system migration	216
	Specifying the migration target	217
	Using the fscdsadm command	218
	Migrating a file system one time	221
	Migrating a file system on an ongoing basis	221
	When to convert a file system	223
	Converting the byte order of a file system	223
	Alignment value and block size	
	Migrating a snapshot volume	228
ndev		221

Section

Solutions for Veritas Storage Foundation and High Availability products

■ Chapter 1. Solutions for Veritas Storage Foundation and High Availability products

Chapter 1

Solutions for Veritas Storage Foundation and High Availability products

This chapter includes the following topics:

- About Storage Foundation and High Availability Solutions
- Feature support across Veritas Storage Foundation and High Availability Solutions 6.0 products
- Using SmartMove and Thin Provisioning with DB2 and Sybase
- Finding Veritas Storage Foundation and High Availability Solutions management feature information

About Storage Foundation and High Availability Solutions

Veritas Storage Foundation and High Availability (SFHA) Solutions product components and features can be used individually and in concert to improve performance, resilience, and ease of management for your storage and applications. This guide documents key use cases for the management features of SFHA Solutions products:

Key use cases for SFHA Solutions products Table 1-1

Use case	SFHA Solutions feature
Improve DB2 and Sybase database performance using SFHA Solutions database accelerators to enable your database to achieve the speed of raw disk while retaining the management features and convenience of a file system.	Concurrent I/O
Protect your data using SFHA Solutions Flashsnap, Storage Checkpoints, and NetBackup point-in-time copy methods to back up and recover your data.	FlashSnap Storage Checkpoints NetBackup with SFHA Solutions
Process your data off-host to avoid performance loss to your production hosts by using SFHA Solutions volume snapshots.	FlashSnap
Optimize copies of your production database for test, decision modeling, and development purposes by using SFHA Solutions point-in-time copy methods.	FlashSnap
Make file level point-in-time snapshots using SFHA Solutions space-optimized FileSnap when you need finer granualarity for your point-in-time copies than file systems or volumes. You can use FileSnap for cloning virtual machines.	FileSnap
Maximize your storage utilization using SFHA Solutions SmartTier to move data to storage tiers based on age, priority, and access rate criteria.	SmartTier
Convert your data from native OS to VxFS using SFHA Solutions Portable Data Containers.	Offline conversion utility
Convert your data from raw disk to VxFS: use SFHA Solutions Portable Data Containers.	Offline conversion utility
Migrate your data from one platform to another (server migration) using SFHA Solutions Portable Data Containers.	Portable Data Containers

Table 1-1 Key use cases for SFHA Solutions products (continued)

Use case	SFHA Solutions feature
Migrate your data across arraysusing SFHA Solutions Portable Data Containers.	Volume mirroring

Feature support across Veritas Storage Foundation and High Availability Solutions 6.0 products

Storage solutions and use cases are based on the shared management features of Veritas Storage Foundation and High Availability (SFHA) Solutions products. Clustering features are available separately through Veritas Cluster Server (VCS) as well as through the SFHA Solutions products.

Table 1-2 lists the features supported across SFHA Solutions products. Table 1-3 lists the high availability and disaster recovery features available in VCS.

Storage management features in SFHA Solutions products Table 1-2

Storage management feature	SF Basic	SF Std.	SF Ent.	SF Std. HA	SF Ent. HA	SFCFS HA	SFRAC	SVS	SF Syb CE
Veritas Extension for Oracle Disk Manager	Y	Y	Y	Y	Y	Y	Y	Y	N
Veritas Extension for Cached Oracle Disk Manager	Y	Y	Y	Y	Y	Y	N	Y	Y
Concurrent I/O	Y	Y	Y	Y	Y	Y	Y	Y	Y
Compression	N	Y	Y	Y	Y	Y	Y	Y	Y
SmartMove	Y	Y	Y	Y	Y	Y	Y	Y	Y
SmartTier	N	Y	Y	Y	Y	Y	Y	Y	Y
SmartTier for Oracle	N	N	Y	Y	Y	Y	Y	N	N
Thin Reclamation	N	N	Y	Y	Y	Y	Y	Y	Y
Portable Data Containers	N	N	Y	Y	Y	Y	Y	Y	Y
FlashSnap	N	N	Y	Y	Y	Y	Y	Y	Y
Database FlashSnap	N	N	Y	Y	Y	Y	Y	N	N
Storage Checkpoints	N	N	Y	Y	Y	Y	Y	Y	Y

Storage management features in SFHA Solutions products Table 1-2 (continued)

Storage management feature	SF Basic	SF Std.	SF Ent.	SF Std. HA	SF Ent. HA	SFCFS HA	SFRAC	SVS	SF Syb CE
Database Storage Checkpoints	N	N	Y	Y	Y	Y	Y	N	N
FileSnap	N	N	N	Y	Y	Y	Y	Y	Y
Volume replication	О	О	0	О	О	О	О	0	О
File replication	О	О	0	О	О	О	О	Y	О
Advanced support for virtual storage	Y	Y	Y	Y	Y	Y	N	N	N
Symantec Storage Plug-in for VMWare vCenter	Y	Y	Y	Y	Y	Y	Y	Y	Y
Clustering features for high availability (HA)	N	N	N	Y	Y	Y	Y	Y	Y
Disaster recovery features (HA/DR)	N	N	N	0	О	0	О	N	0

Availability management features in SFHA Solutions products Table 1-3

Availability management feature	vcs	VCS HA/DR
Clustering for high availability (HA)	Y	Y
Database and application/ISV agents	Y	Y
Advanced failover logic	Y	Y
Data integrity protection with I/O fencing	Y	Y
Advanced virtual machines support	Y	Y
Virtual Business Services	Y	Y
Replication agents	N	Y
Replicated Data Cluster	N	Y
Stretch cluster	N	Y
Campus cluster	N	Y
Global clustering (GCO)	N	Y
Fire Drill	N	Y

Legend:

- Y=Feature is included in the product license.
- O=Feature is not included in the product license but may be licensed separately.
- N=Feature is not supported with the product license.

Notes:

- The Veritas File Replicator license includes file replication.
- The Veritas Replicator license includes both file replication and volume replication (also known as Veritas Volume Replicator, VVR).
- SmartTier is an expanded and renamed version of Dynamic Storage Tiering (DST).
- All features listed in Table 1-2 and Table 1-3 are supported on Linux. Consult specific product documentation for information on supported operating systems.

Using SmartMove and Thin Provisioning with DB2 and **Sybase**

You can use SmartMove and Thin Provisioning with Veritas Storage Foundation and High Availability products and your DB2 or Sybase database.

When data files are deleted, you can reclaim the storage space used by these files if the underlying devices are thin reclaimable LUNs.

For information about the Storage Foundation Thin Reclamation feature, see the Veritas Storage Foundation Administrator's Guide.

Finding Veritas Storage Foundation and High **Availability Solutions management feature** information

The following Veritas Storage Foundation and High Availability Solutions management features are illustrated with use case examples in this guide:

- Improving database performance for DB2 and Sybase
- Backing up and recovering your data
- Processing data off-host
- Optimizing test and development environments

Finding Veritas Storage Foundation and High Availability Solutions management feature information

- Maximizing storage utilization
- Converting your data from native OS to VxFS
- Converting your data from raw disk to VxFS
- Migrating your data from one platform to another (server migration)
- Migrating your data across arrays

For Veritas Storage Foundations and High Availibitlity Solutions management features concept and administrative information, see the following guides:

- Veritas Storage Foundation[™] Administrator's Guide
- Veritas Storage Foundation[™] for Cluster File System High Availability Administrator's Guide.
- Veritas Storage Foundation™ for Oracle RAC Administrator's Guide.
- Veritas Storage Foundation™ for Sybase ASE CE Administrator's Guide.

For Information on using Veritas Storage Foundations and High Availibitlity Solutions management features with Oracle databases, see: Veritas Storage Foundation™: Storage and Availability Management for Oracle Databases.

For Information on using Veritas Storage Foundations and High Availibitlity Solutions replication features, see: Veritas Storage Foundation and High Availability Solutions Replication Guide

Section

Improving database performance

- Chapter 2. Overview of database accelerators
- Chapter 3. Improving database performance with Veritas Concurrent I/O

Chapter 2

Overview of database accelerators

This chapter includes the following topics:

 About Storage Foundation and High Availability Solutions products database accelerators

About Storage Foundation and High Availability Solutions products database accelerators

The major concern in any environment is maintaining respectable performance or meeting performance service level agreements (SLAs). Veritas Storage Foundation products improve the overall performance of database environments in a variety of ways.

- Concurrent I/O (CIO) optimized for DB2 and Sybase environments
- Oracle Disk Manager (ODM) and Cached Oracle Disk Manager (CODM) optimized specifically for Oracle environments

These database accelerator technologies enable database performance equal to raw disk partitions, but with the manageability benefits of a file system. With the Dynamic Multi-pathing (DMP) feature of Storage Foundation, performance is maximized by load-balancing I/O activity across all available paths from server to array. DMP supports all major hardware RAID vendors, hence there is no need for third-party multi-pathing software, reducing the total cost of ownership.

Storage Foundation database accelerators enable you to manage performance for your database with more precision.

About Storage Foundation and High Availability Solutions products database accelerators

- To achieve improved performance for DB2 or Sybase databases run on VxFS file systems, without restrictions on increasing file size, use Veritas Concurrent I/O.
- To improve Oracle performance and manage system bandwidth through an improved Application Programming Interface (API) that contains advanced kernel support for file I/O, use Veritas Oracle Disk Manager (ODM).
- To enable selected I/O to use caching to improve ODM I/O performance, use Veritas Extension for Cached Oracle Disk Manager (Cached ODM).

Chapter 3

Improving database performance with Veritas Concurrent I/O

This chapter includes the following topics:

- About Concurrent I/O
- Tasks for enabling and disabling Concurrent I/O

About Concurrent I/O

Veritas Concurrent I/O improves the performance of regular files on a VxFS file system. This simplifies administrative tasks and allows databases, which do not have a sequential read/write requirement, to access files concurrently. This chapter describes how to use the Concurrent I/O feature.

How Concurrent I/O works

Traditionally, Linux semantics require that read and write operations on a file occur in a serialized order. Because of this, a file system must enforce strict ordering of overlapping read and write operations. However, databases do not usually require this level of control and implement concurrency control internally, without using a file system for order enforcement.

The Veritas Concurrent I/O feature removes these semantics from the read and write operations for databases and other applications that do not require serialization.

The benefits of using Concurrent I/O are:

- Concurrency between a single writer and multiple readers
- Concurrency among multiple writers
- Minimalization of serialization for extending writes
- All I/Os are direct and do not use file system caching
- I/O requests are sent directly to file systems
- Inode locking is avoided

Tasks for enabling and disabling Concurrent I/O

Concurrent I/O is not turned on by default and must be enabled manually. You will also have to manually disable Concurrent I/O if you choose not to use it in the future.

You can perform the following tasks:

- Enable Concurrent I/O
- Disable Concurrent I/O

Enabling Concurrent I/O for DB2

Because you do not need to extend name spaces and present the files as devices, you can enable Concurrent I/O on regular files.

For DB2, you can enable an entire file system to use Concurrent I/O or you can enable specific SMS containers to use Concurrent I/O. If you enable a specific SMS container, the rest of the file system will use the regular buffer I/O.

Before enabling Concurrent I/O, review the following:

Prerequisites

- To use the Concurrent I/O feature, the file system must be a VxFS
- Make sure the mount point on which you plan to mount the file system exists.
- Make sure the DBA can access the mount point.

For DB2, */mount point* is the directory in which you can put data containers of the SMS tablespaces using the Concurrent I/O feature.

Note: This applies to both creating a new tablespace to use Concurrent I/O or enabling an existing tablespace to use Concurrent I/O.

For example for DB2 to mount a file system named /datavol on a mount point named /db2data:

/usr/sbin/mount -t vxfs -o cio /dev/vx/dsk/db2dg/datavol \ /db2data

To enable Concurrent I/O on a new SMS container using the namefs -o cio option

- Using the mount command, mount the directory in which you want to put data containers of the SMS tablespaces using the Concurrent I/O feature.
 - # /usr/sbin/mount -Vt namefs -o cio /path name /new mount point where:
 - /path name is the directory in which the files that will be using Concurrent I/O reside
 - /new mount point is the new target directory that will use the Concurrent I/O feature

The following is an example of mounting a directory (where the new SMS containers are located) to use Concurrent I/O.

To mount an SMS container named /container1 on a mount point named /mysms:

/usr/sbin/mount -Vt namefs -o cio /datavol/mysms/container1 /mysms

To enable Concurrent I/O on an existing SMS container using the namefs -o cio option

- Stop the DB2 instance using the db2stop command.
- 2 Make the directory that will have Concurrent I/O turned on available using the my command.
 - # mv /mydb/mysmsdir /mydb/mysmsdir2
- Remount /mydb/mysmsdir2 on /mydb/mysmsdir using the mount command with the -o cio option.
 - # mount -Vt namefs -o cio /mydb/mysmsdir2 /mydb/mysmsdir
- Start the DB2 instance using the db2start command.
 - # db2stop
 - # mv /mydb/mysmsdir /mydb/mysmsdir2
 - # mount -Vt namefs -o cio /mydb/mysmsdir2 /mydb/mysmsdir
 - # db2start

This example shows how to mount a directory for an existing SMS container to use Concurrent I/O.

To enable Concurrent I/O on a DB2 tablespace when creating the tablespace

- Use the db2 -v "create regular tablespace..." command with the no file system caching option.
- Set all other parameters according to your system requirements.

To enable Concurrent I/O on an existing DB2 tablespace

- Use the DB2 no file system caching option as follows:
 - # db2 -v "alter tablespace tablespace name no file system caching"

where tablespace name is the name of the tablespace for which you are enabling Concurrent I/O.

To verify that Concurrent I/O has been set for a particular DB2 tablespace

- Use the DB2 get snapshot option to check for Concurrent I/O.
 - # db2 -v "get snapshot for tablespaces on dbname"

where *dbname* is the database name.

Find the tablespace you want to check and look for the File system caching attribute. If you see File system caching = No, then Concurrent I/O is enabled.

Disabling Concurrent I/O for DB2

If you need to disable Concurrent I/O, use the DB2 file system caching option.

Note: If you used the namefs -o cio option with the mount command to mount a directory to enable Concurrent I/O, make sure you remount without that option as well. Also, if you follow the directions for enabling Concurrent I/O on an existing SMS container, rename the directory back to the original name.

To disable Concurrent I/O on a DB2 tablespace

Use the DB2 file system caching option as follows:

db2 -v "alter tablespace tablespace_name file system caching"

where tablespace name is the name of the tablespace for which you are disabling Concurrent I/O.

Enabling Concurrent I/O for Sybase

Because you do not need to extend name spaces and present the files as devices, you can enable Concurrent I/O on regular files.

Before enabling Concurrent I/O, review the following:

Prerequisites

- To use the Concurrent I/O feature, the file system must be a VxFS file system.
- Make sure the mount point on which you plan to mount the file system exists.
- Make sure the DBA can access the mount point.

To enable Concurrent I/O on a file system using mount with the -o cio option

- Mount the file system using the mount command as follows:
 - # /usr/sbin/mount -t vxfs -o cio special /mount point

where:

- *special* is a block special device.
- */mount point* is the directory where the file system will be mounted.

For example for Sybase, to mount a file system named /datavolon a mount point named /sybasedata:

```
# /usr/sbin/mount -t vxfs -o cio /dev/vx/dsk/sybasedg/datavol \
/sybasedata
```

The following is an example of mounting a directory (where the new SMS containers are located) to use Concurrent I/O.

To mount an SMS container named /container1 on a mount point named /mysms:

/usr/sbin/mount -Vt namefs -o cio /datavol/mysms/container1 /mysms

Disabling Concurrent I/O for Sybase

If you need to disable Concurrent I/O, unmount the VxFS file system and mount it again without the mount option.

To disable Concurrent I/O on a file system using the mount command

- 1 Shutdown the DB instance.
- 2 Unmount the file sytem using the umount command.
- 3 Mount the file system again using the \mathtt{mount} command without using the $-\circ$ ${\tt cio}$ option.

Section 3

Using point-in-time copies

- Chapter 4. Understanding point-in-time copy methods
- Chapter 5. Backing up and recovering
- Chapter 6. Backing up and recovering in a NetBackup environment
- Chapter 7. Off-host processing
- Chapter 8. Creating and refreshing test environments
- Chapter 9. Creating point-in-time copies of files

Chapter 4

Understanding point-in-time copy methods

This chapter includes the following topics:

- About point-in-time copies
- When to use point-in-time copies
- About Storage Foundation point-in-time copy technologies

About point-in-time copies

Veritas Storage Foundation offers a flexible and efficient means of managing business-critical data. Storage Foundation lets you capture an online image of an actively changing database at a given instant, called a point-in-time copy.


More and more, the expectation is that the data must be continuously available (24x7) for transaction processing, decision making, intellectual property creation, and so forth. Protecting the data from loss or destruction is also increasingly important. Formerly, data was taken out of service so that the data did not change while data backups occured; however, this option does not meet the need for minimal down time.

A point-in-time copy enables you to maximize the online availability of the data. You can perform system backup, upgrade, or perform other maintenance tasks on the point-in-time copies. The point-in-time copies can be processed on the same host as the active data, or a different host. If required, you can offload processing of the point-in-time copies onto another host to avoid contention for system resources on your production server. This method is called off-host processing. If implemented correctly, off-host processing solutions have almost no impact on the performance of the primary production system.

Implementing point-in time copy solutions on a primary host

Figure 4-1 illustrates the steps that are needed to set up the processing solution on the primary host.

Figure 4-1 Using snapshots and FastResync to implement point-in-time copy solutions on a primary host



Note: The Disk Group Split/Join functionality is not used. As all processing takes place in the same disk group, synchronization of the contents of the snapshots from the original volumes is not usually required unless you want to prevent disk contention. Snapshot creation and updating are practically instantaneous.

Figure 4-2 shows the suggested arrangement for implementing solutions where the primary host is used and disk contention is to be avoided.




Figure 4-2 Example point-in-time copy solution on a primary host

In this setup, it is recommended that separate paths (shown as 1 and 2) from separate controllers be configured to the disks containing the primary volumes and the snapshot volumes. This avoids contention for disk access, but the primary host's CPU, memory and I/O resources are more heavily utilized when the processing application is run.

Note: For space-optimized or unsynchronized full-sized instant snapshots, it is not possible to isolate the I/O pathways in this way. This is because such snapshots only contain the contents of changed regions from the original volume. If applications access data that remains in unchanged regions, this is read from the original volume.

Implementing off-host point-in-time copy solutions

Figure 4-3 illustrates that, by accessing snapshot volumes from a lightly loaded host (shown here as the OHP host), CPU- and I/O-intensive operations for online backup and decision support are prevented from degrading the performance of the primary host that is performing the main production activity (such as running a database).

Primary Host OHP host Network 2 SCSI or Fibre Channel connectivity Disks containing primary Disks containing snapshot volumes used to hold volumes production databases or file systems

Figure 4-3 Example implementation of an off-host point-in-time copy solution

Also, if you place the snapshot volumes on disks that are attached to host controllers other than those for the disks in the primary volumes, it is possible to avoid contending with the primary host for I/O resources. To implement this, paths 1 and 2 shown in the Figure 4-3 should be connected to different controllers.

Figure 4-4 shows an example of how you might achieve such connectivity using Fibre Channel technology with 4 Fibre Channel controllers in the primary host.




Figure 4-4 Example connectivity for off-host solution using redundant-loop access

This layout uses redundant-loop access to deal with the potential failure of any single component in the path between a system and a disk array.

Disk arrays

Note: On some operating systems, controller names may differ from what is shown here.

Figure 4-5 shows how off-host processing might be implemented in a cluster by configuring one of the cluster nodes as the OHP node.

Figure 4-5 Example implementation of an off-host point-in-time copy solution using a cluster node





Figure 4-6 shows an alternative arrangement, where the OHP node could be a separate system that has a network connection to the cluster, but which is not a cluster node and is not connected to the cluster's private network.

Figure 4-6 Example implementation of an off-host point-in-time copy solution using a separate OHP host




Note: For off-host processing, the example scenarios in this document assume that a separate OHP host is dedicated to the backup or decision support role. For clusters, it may be simpler, and more efficient, to configure an OHP host that is not a member of the cluster.

Figure 4-7 illustrates the steps that are needed to set up the processing solution on the primary host.

disk group.

Implementing off-host processing solutions Figure 4-7



through 9 as required

Disk Group Split/Join is used to split off snapshot volumes into a separate disk group that is imported on the OHP host.

Note: As the snapshot volumes are to be moved into another disk group and then imported on another host, their contents must first be synchronized with the parent volumes. On reimporting the snapshot volumes, refreshing their contents from the original volume is speeded by using FastResync.

When to use point-in-time copies

The following typical activities are suitable for point-in-time copy solutions implemented using Veritas FlashSnap:

- Data backup —Many enterprises require 24 x 7 data availability. They cannot afford the downtime involved in backing up critical data offline. By taking snapshots of your data, and backing up from these snapshots, your business-critical applications can continue to run without extended downtime or impacted performance.
- Providing data continuity —To provide continuity of service in the event of primary storage failure, you can use point-in-time copy solutions to recover application data. In the event of server failure, you can use point-in-time copy solutions in conjunction with the high availability cluster functionality of Veritas Storage Foundation™ for Cluster File System HA or Veritas Storage Foundation HA.
- Decision support analysis and reporting—Operations such as decision support analysis and business reporting may not require access to real-time information. You can direct such operations to use a replica database that you have created from snapshots, rather than allow them to compete for access to the primary database. When required, you can quickly resynchronize the database copy with the data in the primary database.
- Testing and training—Development or service groups can use snapshots as test data for new applications. Snapshot data provides developers, system testers and QA groups with a realistic basis for testing the robustness, integrity and performance of new applications.
- Database error recovery—Logic errors caused by an administrator or an application program can compromise the integrity of a database. You can recover a database more quickly by restoring the database files by using Storage Checkpoints or a snapshot copy than by full restoration from tape or other backup media.

Use Storage Checkpoints to quickly roll back a database instance to an earlier point in time.

■ Cloning data—You can clone your file system or application data. This functionality enable you to quickly and efficiently provision virtual desktops.

All of the snapshot solutions mentioned above are also available on the disaster recovery site, in conjunction with Veritas Volume Replicator.

For more information about snapshots with replication, see the Veritas Storage Foundation and High Availability Solutions Replication Administrator's Guide.

Veritas Storage Foundation provides several point-in-time copy solutions that support your needs, including the following use cases:

- Creating a replica database for decision support. See "Using a replica database for decision support" on page 98.
- Backing up and recovering a database with snapshots. See "Online database backups" on page 53.
- Backing up and recovering an off-host cluster file system See "Backing up on an off-host cluster file system" on page 76.
- Backing up and recovering an online database. See "Database recovery using Storage Checkpoints" on page 85.

About Storage Foundation point-in-time copy technologies

This topic introduces the point-in-time copy solutions that you can implement using the Veritas FlashSnap™ technology. Veritas FlashSnap technology requires an enterprise product license.

Veritas FlashSnap offers a flexible and efficient means of managing business critical data. It allows you to capture an online image of actively changing data at a given instant: a point-in-time copy. You can perform system backup, upgrade and other maintenance tasks on point-in-time copies while providing continuous availability of your critical data. If required, you can offload processing of the point-in-time copies onto another host to avoid contention for system resources on your production server.

The following kinds of point-in-time copy solution are supported with an enterprise license:

■ Volume-level solutions. There are several types of volume-level snapshots. These features are suitable for solutions where separate storage is desirable to create the snapshot. For example, lower-tier storage. Some of these techniques provided exceptional offhost processing capabilities. See "Volume-level snapshots" on page 43.

- File system-level solutions use the Storage Checkpoint feature of Veritas File System. Storage Checkpoints are suitable for implementing solutions where storage space is critical for:
 - File systems that contain a small number of mostly large files.
 - Application workloads that change a relatively small proportion of file system data blocks (for example, web server content and some databases).
 - Applications where multiple writable copies of a file system are required for testing or versioning.

See "Storage Checkpoints" on page 44.

■ File level snapshots. The FileSnap feature provides snapshots at the level of individual files. See "About FileSnaps" on page 45.

Volume-level snapshots

A volume snapshot is an image of a Veritas Volume Manager (VxVM) volume at a given point in time. You can also take a snapshot of a volume set.

Volume snapshots allow you to make backup copies of your volumes online with minimal interruption to users. You can then use the backup copies to restore data that has been lost due to disk failure, software errors or human mistakes, or to create replica volumes for the purposes of report generation, application development, or testing.

Volume snapshots can also be used to implement off-host online backup.

Physically, a snapshot may be a full (complete bit-for-bit) copy of the data set, or it may contain only those elements of the data set that have been updated since snapshot creation. The latter are sometimes referred to as allocate-on-first-write snapshots, because space for data elements is added to the snapshot image only when the elements are updated (overwritten) for the first time in the original data set. Storage Foundation allocate-on-first-write snapshots are called space-optimized snapshots.

Persistent FastResync of volume snapshots

If persistent FastResync is enabled on a volume, VxVM uses a FastResync map to keep track of which blocks are updated in the volume and in the snapshot.

When snapshot volumes are reattached to their original volumes, persistent FastResync allows the snapshot data to be quickly refreshed and re-used. Persistent FastResync uses disk storage to ensure that FastResync maps survive both system and cluster crashes. If persistent FastResync is enabled on a volume in a private disk group, incremental resynchronization can take place even if the host is rebooted.

Persistent FastResync can track the association between volumes and their snapshot volumes after they are moved into different disk groups. After the disk groups are rejoined, persistent FastResync allows the snapshot plexes to be quickly resynchronized.

Data integrity in volume snapshots

A volume snapshot captures the data that exists in a volume at a given point in time. As such, VxVM does not have any knowledge of data that is cached in memory by the overlying file system, or by applications such as databases that have files open in the file system. Snapshots are always crash consistent, that is, the snapshot can be put to use by letting the application perform its recovery. This is similar to how the application recovery occurs after a server crash. If the fsqen volume usage type is set on a volume that contains a mounted Veritas File System (VxFS). VxVM coordinates with VxFS to flush data that is in the cache to the volume. Therefore, these snapshots are always VxFS consistent and require no VxFS recovery while mounting.

For databases, a suitable mechanism must additionally be used to ensure the integrity of tablespace data when the volume snapshot is taken. The facility to temporarily suspend file system I/O is provided by most modern database software. The examples provided in this document illustrate how to perform this operation. For ordinary files in a file system, which may be open to a wide variety of different applications, there may be no way to ensure the complete integrity of the file data other than by shutting down the applications and temporarily unmounting the file system. In many cases, it may only be important to ensure the integrity of file data that is not in active use at the time that you take the snapshot. However, in all scenarios where application coordinate, snapshots are crash-recoverable.

Storage Checkpoints

A Storage Checkpoint is a persistent image of a file system at a given instance in time. Storage Checkpoints use a copy-on-write technique to reduce I/O overhead by identifying and maintaining only those file system blocks that have changed since a previous Storage Checkpoint was taken. Storage Checkpoints have the following important features:

■ Storage Checkpoints persist across system reboots and crashes.

- A Storage Checkpoint can preserve not only file system metadata and the directory hierarchy of the file system, but also user data as it existed when the Storage Checkpoint was taken.
- After creating a Storage Checkpoint of a mounted file system, you can continue to create, remove, and update files on the file system without affecting the image of the Storage Checkpoint.
- Unlike file system snapshots, Storage Checkpoints are writable.
- To minimize disk space usage, Storage Checkpoints use free space in the file system.

Storage Checkpoints and the Storage Rollback feature of Veritas Storage Foundation for Databases enable rapid recovery of databases from logical errors such as database corruption, missing files and dropped table spaces. You can mount successive Storage Checkpoints of a database to locate the error, and then roll back the database to a Storage Checkpoint before the problem occurred.

See "Database recovery using Storage Checkpoints" on page 85.

Symantec NetBackup for Oracle Advanced BLI Agent uses Storage Checkpoints to enhance the speed of backing up Oracle databases.

See the Symantec NetBackup for Oracle Advanced BLI Agent System Administrator's Guide.

About FileSnaps

A FileSnap is an atomic space-optimized copy of a file in the same name space, stored in the same file system. Veritas File System (VxFS) supports snapshots on file system disk layout Version 8 and later.

FileSnaps provide an ability to snapshot objects that are smaller in granularity than a file system or a volume. The ability to snapshot parts of a file system name space is required for application-based or user-based management of data stored in a file system. This is useful when a file system is shared by a set of users or applications or the data is classified into different levels of importance in the same file system.

All regular file operations are supported on the FileSnap, and VxFS does not distinguish the FileSnap in any way.

46 Understanding point-in-time copy methods
About Storage Foundation point-in-time copy technologies

Chapter 5

Backing up and recovering

This chapter includes the following topics:

- About Storage Foundation and High Availability Solutions backup and recovery use cases
- Creating and maintaining a full image snapshot and incremental point-in-time copies
- Online database backups
- Backing up on an off-host cluster file system
- Database recovery using Storage Checkpoints

About Storage Foundation and High Availability Solutions backup and recovery use cases

Storage Foundation and High Availability Solutions (SFHA Solutions) provide point-in-time copy methods which can be applied to multiple database backup use cases.

Example procedures are provided for the following use cases:

- Creating and maintaining a full image snapshot and incremental point-in-time copies
 - See "Creating and maintaining a full image snapshot and incremental point-in-time copies" on page 48.
- Backing up and recovering a database with snapshots.See "Online database backups" on page 53.
- Backing up and recovering an off-host cluster file system
 See "Backing up on an off-host cluster file system" on page 76.

- Backing up and recovering an online database. See "Database recovery using Storage Checkpoints" on page 85.
- Recovering a database with Storage Checkpoints See "Database recovery using Storage Checkpoints" on page 85.
- Backing up and recovering a database in a NetBackup environment.

For basic backup and recovery configuration information, see the Veritas Storage Foundation Administrator's Guide.

Creating and maintaining a full image snapshot and incremental point-in-time copies

On-disk snapshots are efficient when it comes to recovering a logically corrupted data. Storage Foundation and High Availability Solutions (SFHA Solutions) provide a cost effective and very efficient mechanism to manage multiple copies of production data at different points in time. With Flashsnap, you can create a solution to preserve and manage the whole lifecycle of snapshots for recovery from logical data corruption. You can also use the preserved snapshot image itself for business continuity in case of primary storage failure or for off-host processing.

The following example procedures illustrate how to create a full image snapshot and periodic point-in-time copies for recovery. With mulitple point-in-time copies to choose from, you can select the point-in-time to which you want to recover with relative precision.

Setting up a full image snapshot and incremental point-in-time copies

To set up the initial configuration for a full image snapshot and incremental point-in-time copies, set up storage for the point-in-time copies that will be configured over time.

In the example procedures, disk1, disk2, ..., diskN are the LUNs configured on tier 1 storage for application data. A subset of these LUNs logdisk1, logdisk2, ..., logdiskN, will be used to configure DCO. Disks sdisk1, sdisk2, ..., sdiskN are disks from tier 2 storage.

Note: If you have an enclosure or disk array with storage that is backed by write cache, Symantec recommends that you use the same set of LUNS for DCO and for data volume.

If no logdisks are specified by default, Veritas Volume Manager tries to allocate the DCO from the same LUNs used for the data volumes.

See Figure 4-4 on page 37.

You will need to make sure your cache is big enough for the multiple copies with multiple changes. The following guidelines may be useful for estimating your requirements.

To determine your storage requirements, use the following:

Table 5-1 Storage requirements

Represents the storage requirement for the primary volume S_{n}

Represents the storage requirement for the primary break-off snapshot. S_b

 N_c Represents the number of point-in-time copies to be maintained.

Represents the average size of the changes that occur in an interval before the S_c snapshot is taken.

 S_t Represents the total storage requirement.

The total storage requirement for management of multiple point-in-time copies can be roughly calculated as:

$$S_b = S_p$$

$$S_t = S_b + N_c * S_c$$

To determine the size of the cache volume, use the following:

Table 5-2 Cache volume requirements

Represents the number of point-in-time copies to be maintained. N_c

 S_c Represents the average size of the changes that occur in an interval.

Represents the region-size for cache-object. R

Represents the total storage requirement. S_{t}

The size of cache-volume to be configured can be calculated as:

This equation assumes that the application IO size granularity is smaller than cache-object region-size by factor of at most R_c

To configure the initial setup for a full image snapshot and incremental point-in-time copies

1 If the primary application storage is already configured for snapshots, that is, the DCO is already attached for the primary volume, go to step 2.

If not, configure the primary volumes and prepare them for snapshots.

For example:

```
# vxassist -g appdg make appvol 10T <disk1 disk2 ... diskN >
# vxsnap -g appdg prepare appvol
```

- 2 Configure your storage for a full image snapshot and the point-in-time copies to be created periodically, in a similar manner to the way you configured your primary volumes. Veritas Storage Foundation does not need allocation from the same (tier 1) storage to configure point-in-time copies. For instance, the allocation could come from tier 2 storage.
- 3 Configure a snapshot volume from tier 2 storage to use as primary snapshot of the primary volume.

```
# vxassist -g appdg make snap-appvol 10T <sdisk1 sdisk2 ... sdiskN >
# vxsnap -g appdg prepare snap-appvol \
<alloc=slogdisk1, slogdisk2, ...slogdiskN>
```

4 Establish the relationship between primary and snapshot volumes and wait for synchronization of the snapshot to complete.

```
# vxsnap -q appdq make source=appvol/snapvol=snap-appvol/sync=yes
# vxsnap -g appdg syncwait snap-appvol
```

5 Create a volume to use for the cache volume.

```
# vxassist -q appdq make cachevol 1G layout=mirror \
init=active disk16 disk17
```

6 Configure a shared cache object in the disk group from tier 2 storage to use for point-in-time copies created at regular intervals.

```
# vxmake -g appdg cache snapcache cachevolname=cachevol
```

Start the cache object.

```
# vxcache -g appdg start snapcache
```

You now have an initial setup in place to create regular point-in-time copies.

Refreshing point-in-time copies

After configuring your volumes for snapshots, you can periodically invoke a script with steps similar to following to create point-in-time copies at regular intervals.

To identify snapshot age

- To find the oldest and the most recent snapshots, use the creation time of the snapshots. You can use either of the following commands:
 - Use the following command and find the SNAPDATE of snapshot volume.

```
# vxsnap -g appdg list appvol
```

■ Use the following command:

```
# vxprint -g appdg -m snapobject name| grep creation time
```

Where the *snapobject-name* is *appvol-snp*, *appvol-snp1* *appvol-snpN*.

To refresh the primary snapshot

Refresh the primary snapshot from the primary volume.

```
# vxsnap -g appdg refresh snap-appvol source=appvol
```

To create cascaded snapshot of the refreshed snapshot volume

Create a cascaded snapshot of the refreshed snapshot volume.

```
# vxsnap -g appdg make source=snap-appvol/new=sosnap-\
appvol${NEW SNAP IDX}/cache=snapcache/infrontof=snap-appvol
```

To remove the oldest point-in-time copy

If the limit on number of point-in-time copies is reached, remove the oldest point-in-time copy.

```
# vxedit -g appdg -rf rm sosnap-appvol${ OLDEST SNAP IDX }
```

Recovering from logical corruption

You can use the preserved snapshot image in case of primary storage corruption. You must identify the most recent snapshot which is not affected by the logical corruption.

To identify the most recent valid snapshot

For each snapshot, starting from the most recent to the oldest, verify the snapshot image. Create a space-optimized snapshot of the point-in-time copy to generate a synthetic replica of the point-in-time image.

```
# vxsnap -q appdq make source=sosnapappvol${
CURIDX}/new=syn-appvol/cache=snapcache/sync=no
```

2 Mount the synthetic replica and verify the data.

If a synthetic replica is corrupted, proceed to 3.

When you identify a synthetic replica that is not corrupted, you can proceed to the recovery steps.

See "To recover from logical corruption" on page 52.

Unmount the synthetic replica, remove it and go back to verify the next most recent point-in-time copy. Use the following command to dissociate the synthetic replica and remove it:

```
# vxsnap -g appdg dis syn-appvol
# vxedit -q appdq -rf rm syn-appvol
```

When you find the most recent uncorrupted snapshot, use it to restore the primary volume.

To recover from logical corruption

- If the application is running on the primary volume, stop the application.
- 2 Unmount the application volume.
- 3 Restore the primary volume from the synthetic replica.

```
# vxsnap -q appdg restore appvol source=syn-appvol
```

- Resume the application:
 - Mount the primary volume.
 - Verify the content of the primary volume.
 - Restart the application.

Off-host processing using refreshed snapshot images

Preserved point-in-time images can also be used to perform off-host processing. Using preserved point-in-time images for this purpose requires that the storage used for creating the snapshots must be:

- Accessible from the application host
- Accessible from the off-host processing host
- Split into a separate diskgroup

To split the snapshot storage into a separate disk group

Split the snapshot storage into a separate disk group.

```
# vxdg split appdg snapdg snap-appvol
```

The *snapdg* disk group can optionally be deported from the application host using the vxdq deport command and imported on another host using the vxdq import command to continue to perform off-host processing.

To refresh snapshot images for off-host processing

Deport the *snapdg* disk group from the off-host processing host.

```
# vxdq deport snapdq
```

Import the *snapdg* disk group on the application host.

```
# vxdq import snapdq
```

On the application host, join the *snapdg* disk group to *appdg*.

```
# vxdq join snapdq appdq
```

After this step, you can proceed with the steps for managing point-in-time copies.

See "Refreshing point-in-time copies" on page 51.

Online database backups

Online backup of a database can be implemented by configuring either the primary host or a dedicated separate host to perform the backup operation on snapshot mirrors of the primary host's database.

Two backup methods are described in the following sections:

■ See "Making a backup of an online database on the same host" on page 54.

■ See "Making an off-host backup of an online database" on page 65.

Note: All commands require superuser (root) or equivalent privileges, except where it is explicitly stated that a command must be run by the database administrator.

For more information about using snapshots to back up Oracle databases, see the Veritas Storage Foundation™: Storage and Availability Management for Oracle Databases.

Note: The sample database scripts in the following procedures are not supported by Symantec, and are provided for informational use only. You can purchase customization of the environment through Veritas Vpro Consulting Services.

Making a backup of an online database on the same host

Figure 5-1 shows an example with two primary database volumes to be backed up, database vol and dbase logs, which are configured on disks attached to controllers *c1* and *c2*, and the snapshots to be created on disks attached to controllers c3 and c4.

Figure 5-1 Example system configuration for database backup on the primary

Primary host for database Controllers c1 c2 с3 c4 Database volumes Snapshot volumes are are created on these created on these disks disks Disk arrays Backup to disk, tape or other media by primary host

Note: It is assumed that you have already prepared the volumes containing the file systems for the datafiles to be backed up as described in the example.

To make an online database backup

■ Prepare the snapshot, either full-sized or space-optimized. Depending on the application, space-optimized snapshots typically require 10% of the disk space that is required for full-sized instant snapshots. See "Preparing a full-sized instant snapshot for a backup" on page 56. See "Preparing a space-optimized snapshot for a database backup" on page 58.

- Create snapshot mirrors for volumes containing VxFS file systems for database files to be backed up.
- Make the online database backup. See "Backing up a DB2 database on the same host" on page 60. See "Backing up a Sybase database on the same host" on page 62.
- Resynchronize a volume if required. See "Resynchronizing a volume" on page 64.

Some scenarios where full-instant snapshot works better are:

- Off host processing is planned for a databases backup.
- If a space-optimized snapshot is taken for longer duration and modified frequently then it is not much different than the full-snapshot. So, for performance reason full-snapshot will be preferred,

Preparing a full-sized instant snapshot for a backup

You can use a full-sized instant snapshot for your online or off-host database backup.

Warning: To avoid data inconsistencies, do not use the same snapshot with different point-in-time copy applications. If you require snapshot mirrors for more than one application, configure at least one snapshot mirror that is dedicated to each application.

To make a full-sized instant snapshot for a backup of an online database on the same host

Use the following commands to add one or more snapshot plexes to the volume, and to make a full-sized break-off snapshot, snapvol, of the tablespace volume by breaking off these plexes:

```
# vxsnap -g database_dg addmir database vol [nmirror=N] \
 [alloc=storage_attributes]
# vxsnap -q database dg make \
 source=database vol/newvol=snapvol[/nmirror=N] \
  [alloc=storage attributes]
```

By default, one snapshot plex is added unless you specify a number using the nmirror attribute. For a backup, you should usually only require one plex. You can specify storage attributes (such as a list of disks) to determine where the plexes are created.

You can specify at least N number of disks if the specified number of mirrors is N.

If the volume layout does not support plex break-off, prepare an empty volume for the snapshot. Create a full-sized instant snapshot for an original volume that does not contain any spare plexes, you can use an empty volume with the required degree of redundancy, and with the same size and same region size as the original volume.

Use the vxprint command on the original volume to find the required size for the snapshot volume.

```
# LEN='vxprint [-g diskgroup] -F%len database vol'
```

Note: The command shown in this and subsequent steps assumes that you are using a Bourne-type shell such as sh, ksh or bash. You may need to modify the command for other shells such as csh or tcsh. These steps are valid only for instant snap DCOs.

- Use the vxprint command on the original volume to discover the name of its DCO:
 - # DCONAME='vxprint [-g diskgroup] -F%dco name database vol'
- Use the vxprint command on the DCO to discover its region size (in blocks):
 - # RSZ='vxprint [-g diskgroup] -F%regionsz \$DCONAME'
- Use the vxassist command to create a volume, *snapvol*, of the required size and redundancy, together with a instant snap DCO volume with the correct region size:

```
# vxassist [-q diskgroup] make snapvol $LEN \
  [layout=mirror nmirror=number] logtype=dco drl=no \
 dcoversion=20 [ndcomirror=number] regionsz=$RSZ \
 init=active [storage attributes]
```

It is recommended that you specify the same number of DCO mirrors (ndcomirror) as the number of mirrors in the volume (nmirror). The init=active attribute is used to make the volume available immediately. You can use storage attributes to specify which disks should be used for the volume.

As an alternative to creating the snapshot volume and its DCO volume in a single step, you can first create the volume, and then prepare it for instant snapshot operations as shown here:

```
# vxassist [-g diskgroup] make snapvol $LEN \
  [layout=mirror nmirror=number] init=active \
  [storage attributes]
# vxsnap [-g diskgroup] prepare snapvol [ndcomirs=number] \
 regionsz=$RSZ [storage attributes]
```

Use the following command to create the snapshot:

```
# vxsnap -g database_dg make source=database_vol/snapvol=snapvol
```

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database dg make source=database vol1/snapvol=snapvol1 \
source=database vol2/newvol=snapvol2 \
source=database vol3/snapvol=snapvol3
```

When you are ready to make a backup, proceed to make a backup of an online database on the same host.

Preparing a space-optimized snapshot for a database backup

If a snapshot volume is to be used on the same host, and will not be moved to another host, you can use space-optimized instant snapshots rather than full-sized instant snapshots. Depending on the application, space-optimized snapshots typically require 10% of the disk space that is required for full-sized instant snapshots.

To prepare a space-optimized snapshot for a backup of an online database

To save disk space, use the following command to create a space-optimized snapshot:

```
# vxsnap -g database dg make \
 source=database vol/newvol=snapvol/cache=snapcache
```

The argument snapcache is the name of a pre-existing cache that you have created in the disk group for use with space-optimized snapshots.

2 Decide on the following characteristics that you want to allocate to the cache volume that underlies the cache object:

- The size of the cache volume should be sufficient to record changes to the parent volumes during the interval between snapshot refreshes. A suggested value is 10% of the total size of the parent volumes for a refresh interval of 24 hours.
- If redundancy is a desired characteristic of the cache volume, it should be mirrored. This increases the space that is required for the cache volume in proportion to the number of mirrors that it has.
- If the cache volume is mirrored, space is required on at least as many disks as it has mirrors. These disks should not be shared with the disks used for the parent volumes. The disks should also be chosen to avoid impacting I/O performance for critical volumes, or hindering disk group split and join operations.
- Having decided on its characteristics, use the vxassist command to create the volume that is to be used for the cache volume. The following example creates a mirrored cache volume, *cachevol*, with size 1GB in the disk group, database dg, on the disks disk16 and disk17:

```
# vxassist -g database dg make cachevol 1g layout=mirror \
 init=active disk16 disk17
```

The attribute init=active is specified to make the cache volume immediately available for use.

4 Use the vxmake cache command to create a cache object on top of the cache volume that you created in the previous step:

```
# vxmake [-g diskgroup] cache cache_object \
 cachevolname=cachevol [regionsize=size] [autogrow=on] \
  [highwatermark=hwmk] [autogrowby=agbvalue] \
  [maxautogrow=maxagbvalue]]
```

If you specify the region size, it must be a power of 2, and be greater than or equal to 16KB (16k). If not specified, the region size of the cache is set to 64KB.

Note: All space-optimized snapshots that share the cache must have a region size that is equal to or an integer multiple of the region size set on the cache. Snapshot creation also fails if the original volume's region size is smaller than the cache's region size.

If the cache is not allowed to grow in size as required, specify autogrow=off. By default, the ability to automatically grow the cache is turned on.

In the following example, the cache object, cache object, is created over the cache volume, cachevol, the region size of the cache is set to 32KB, and the autogrow feature is enabled:

- # vxmake -g database dg cache cache object cachevolname=cachevol \ regionsize=32k autogrow=on
- Having created the cache object, use the following command to enable it:

```
vxcache [-g diskgroup] start cache object
```

For example, start the cache object cache object:

- # vxcache -g database_dg start cache_object
- 6 Create a space-optimized snapshot with your cache object.

```
# vxsnap -g database dg make \
source=database vol1/newvol=snapvol1/cache=cache object
```

- If several space-optimized snapshots are to be created at the same time, these can all specify the same cache object as shown in this example:
 - # vxsnap -g database dg make \ source=database vol1/newvol=snapvol1/cache=cache object \ source=database_vol2/newvol=snapvol2/cache=cache_object \ source=database vol3/newvol=snapvol3/cache=cache object

Note: This step sets up the snapshot volumes, prepares for the backup cycle, and starts tracking changes to the original volumes.

When you are ready to make a backup, proceed to make a backup of an online database on the same host

Backing up a DB2 database on the same host

You can make an online backup of your DB2 database.

To make a backup of an online DB2 database on the same host

If the volumes to be backed up contain database tables in file systems, suspend updates to the volumes. DB2 provides the write suspend command to temporarily suspend I/O activity for a database. As the DB2 database administrator, use a script such as that shown in the example to suspend I/O for a DB2 database.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to suspend I/O for a DB2 database.
# Note: To recover a database using backups of snapshots, the database
# must be in LOGRETAIN mode.
db2 <<!
connect to database
set write suspend for database
quit
```

Note that to allow recovery from any backups taken from snapshots, the database must be in LOGRETAIN RECOVERY mode.

Refresh the contents of the snapshot volumes from the original volume using the following command:

```
# vxsnap -g database_dg refresh snapvol1 source=database_vol1 \
  [snapvol2 source=database vol2]...
```

For example, to refresh the snapshots *snapvol1*, *snapvol2* and *snapvol3*:

```
# vxsnap -g database_dg refresh snapvol1 source=database_vol1 \
 snapvol2 source=database vol2 snapvol3 source=database vol3
```

If you have temporarily suspended updates to volumes, release all the tablespaces or databases from suspend mode. As the DB2 database administrator, use a script such as that shown in the example to resume I/O for a DB2 database.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to resume I/O for a DB2 database.
db2 <<!
connect to database
set write resume for database
```

```
quit
!
```

Back up the snapshot volume. If you need to remount the file system in the volume to back it up, first run fsck on the volume. The following are sample commands for checking and mounting a file system:

```
# fsck -t vxfs /dev/vx/rdsk/database dg/snapvol
# mount -t vxfs /dev/vx/dsk/database dg/snapvol
    mount point
```

Back up the file system at this point using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.

```
# umount mount point
```

5 Repeat steps in this procedure each time that you need to back up the volume.

Backing up a Sybase database on the same host

You can make an online backup of your Sybase database.

To make a backup of an online Sybase database on the same host

If the volumes to be backed up contain database tables in file systems, suspend updates to the volumes. Sybase ASE from version 12.0 onward provides the Quiesce feature to allow temporary suspension of writes to a database. As the Sybase database administrator, put the database in quiesce mode by using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to quiesce example Sybase ASE database.
# Note: The "for external dump" clause was introduced in Sybase
# ASE 12.5 to allow a snapshot database to be rolled forward.
# See the Sybase ASE 12.5 documentation for more information.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag hold database1[, database2]... [for external dump]
αo
quit
```

Refresh the contents of the snapshot volumes from the original volume using the following command:

```
# vxsnap -g database dg refresh snapvol source=database vol \
  [snapvol2 source=database vol2]...
```

For example, to refresh the snapshots snapvol1, snapvol2 and snapvol3:

```
# vxsnap -g database dg refresh snapvol1 source=database vol1 \
 snapvol2 source=database vol2 snapvol3 source=database vol3
```

If you have temporarily suspended updates to volumes, release all the tablespaces or databases from quiesce mode.

As the Sybase database administrator, release the database from quiesce mode using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to release example Sybase ASE database from
# quiesce mode.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag release
αo
quit
!
```

Back up the snapshot volume. If you need to remount the file system in the volume to back it up, first run fsck on the volume. The following are sample commands for checking and mounting a file system:

```
# fsck -t vxfs /dev/vx/rdsk/database dg/snapvol
# mount -t vxfs /dev/vx/dsk/database dg/snapvol
    mount point
```

Back up the file system at this point using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.

```
# umount mount_point
```

5 Repeat steps in this procedure each time that you need to back up the volume.

Resynchronizing a volume

In some instances, such as recovering the contents of a corrupted volume, it may be useful to resynchronize a volume from its snapshot volume (which is used as a hot standby).

To resynchronize a volume from its snapshot volume

Enter:

```
# vxsnap -g diskgroup restore database vol source=snapvol \
   destroy=ves|no
```

The destroy attribute specifies whether the plexes of the snapshot volume are to be reattached to the original volume. For example, to resynchronize the volume database vol from its snapshot volume snapvol without removing the snapshot volume:

```
# vxsnap -g database dg restore database vol \
  source=snapvol destroy=no
```

Note: You must shut down the database and unmount the file system that is configured on the original volume before attempting to resynchronize its contents from a snapshot.

Making an off-host backup of an online database

Figure 5-2 shows an example of two primary database volumes to be backed up, database_vol and dbase_logs, which are configured on disks attached to controllers c1 and c2, and the snapshots to be created on disks attached to controllers c3 and c4.

There is no requirement for the off-host processing host to have access to the disks that contain the primary database volumes.

Network Primary host for database OHP host disks disks Controllers Controllers c2 c1 с3 c4 с3 c4 Volumes created on these Snapshot volumes created on these disks are accessed by both hosts disks are accessed by the Disk primary host arrays Backup to disk, tape or other media by OHP host

Figure 5-2 Example system configuration for off-host database backup

If the database is configured on volumes in a cluster-shareable disk group, it is assumed that the primary host for the database is the master node for the cluster. However, if the primary host is not also the master node, most VxVM operations on shared disk groups are best performed on the master node.

The procedure in this section is designed to minimize copy-on-write operations that can impact system performance. You can also implement this procedure on a single host by omitting steps 5 through To make an off-host backup of an online Sybase database and 10 through 13 that split, deport, reimport and rejoin the snapshot disk group.

To make an off-host database backup of an online database:

- Prepare the full-sized snapshot for backing up.
- Make the off-host database backup using the steps for DB2 or Sybase. See "Making an off-host backup of an online DB2 database" on page 68. See "Making an off-host backup of an online Sybase database" on page 73.
- Resynchronize a volume if required. See "Resynchronizing a volume" on page 71.

Making an off-host backup of an online DB2 database

To start an off-host backup of an online DB2 database

On the primary host, add one or more snapshot plexes to the volume using this command:

```
# vxsnap -g database dg addmir database vol [nmirror=N] \
[alloc=storage attributes]
```

By default, one snapshot plex is added unless you specify a number using the nmirror attribute. For a backup, you should usually only require one plex. You can specify storage attributes (such as a list of disks) to determine where the plexes are created.

Suspend updates to the volumes. DB2 provides the write suspend command to temporarily suspend I/O activity for a database. As the DB2 database administrator, use a script such as that shown in the example to suspend I/O for a DB2 database.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to suspend I/O for a DB2 database.
# Note: To recover a database using backups of snapshots,
# the database must be in LOGRETAIN mode.
db2 <<!
connect to database
set write suspend for database
quit
!
```

Note that to allow recovery from any backups taken from snapshots, the database must be in LOGRETAIN RECOVERY mode.

Make a full-sized snapshot, *snapvol*, of the tablespace volume by breaking off the plexes that you added in step 1 from the original volume:

```
# vxsnap -q database dq make \
   source=database_vol/newvol=snapvol/nmirror=N \
   [alloc=storage attributes]
```

The nmirror attribute specifies the number of mirrors, N, in the snapshot volume.

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database_dg \
   make source=database vol1/snapvol=snapvol1 \
   source=database vol/snapvol=snapvol2 \
   source=database vol/snapvol=snapvol3 alloc=ctlr:c3,ctlr:c4
```

- This step sets up the snapshot volumes ready for the backup cycle, and starts tracking changes to the original volumes.
- Release all the tablespaces or databases from suspend mode. As the DB2 database administrator, use a script such as that shown in the example. to resume I/O for a DB2 database.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to resume I/O for a DB2 database.
db2 <<!
connect to database
set write resume for database
quit
!
```

6 On the primary host, split the disks containing the snapshot volumes into a separate disk group, snapvoldg, from the original disk group, database_dg using the following command:

```
# vxdg split database dg snapvoldg snapvol ...
```

- On the primary host, deport the snapshot volume's disk group using the following command:
 - # vxdq deport snapvoldq
- On the OHP host where the backup is to be performed, use the following command to import the snapshot volume's disk group:
 - # vxdg import snapvoldg
- VxVM recovers the volumes automatically after the disk group import unless it is set to not recover automatically. Check if the snapshot volume is initially disabled and not recovered following the split.

If a volume is in the DISABLED state, use the following command on the off-host processing host to recover and restart the snapshot volume:

- # vxrecover -g snapvoldg -m snapvol ...
- 10 On the off-host processing host, back up the snapshot volumes. If you need to remount the file system in the volume to back it up, first run fsck on the volumes. The following are sample commands for checking and mounting a file system:
 - # fsck -t vxfs /dev/vx/rdsk/snapvoldg/snapvol # mount -t vxfs /dev/vx/dsk/snapvoldg/snapvol mount point

Back up the file system using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.

- # umount mount point
- 11 On the OHP host, use the following command to deport the snapshot volume's disk group:
 - # vxdq deport snapvoldq
- **12** On the primary host, re-import the snapshot volume's disk group using the following command:
 - # vxdq [-s] import snapvoldq

Note: Specify the -s option if you are reimporting the disk group to be rejoined with a shared disk group in a cluster.

13 On the primary host, use the following command to rejoin the snapshot volume's disk group with the original volume's disk group:

```
# vxdg join snapvoldg database dg
```

14 VxVM will recover the volumes automatically after the join unless it is set not to recover automatically. Check if the snapshot volumes are initially disabled and not recovered following the join.

If a volume is in the DISABLED state, use the following command on the primary host to recover and restart the snapshot volume:

```
# vxrecover -g database_dg -m snapvol
```

15 On the primary host, reattach the snapshot volumes to their original volume. Reattach of multiple volumes in a single command is not supported. Split it into multiple invocations:

```
# vxsnap -g database dg reattach snapvol1 source=database vol1
# vxsnap -g database dg reattach snapvol2 source=database vol2
# vxsnap -g database dg reattach snapvol3 source=database vol3
```

Use the following commands to wait for synchronization to complete:

```
# vxsnap -g database dg snapwait database vol1
# vxsnap -g database dg snapwait database vol2
# vxsnap -g database dg snapwait database vol3
```

For example, to reattach the snapshot volumes snapvol1, snapvol2 and snapvol3:

```
# vxsnap -g database dg reattach snapvol1 source=database vol1 \
  snapvol2 source=database vol2 snapvol3 source=database vol3
```

While the reattached plexes are being resynchronized from the data in the parent volume, they remain in the SNAPTMP state. After resynchronization is complete, the plexes are placed in the SNAPDONE state. You can use the vxsnap print command to check on the progress of synchronization.

Repeat steps 2 through 15 each time that you need to back up the volume.

Resynchronizing a volume

In some instances, such as recovering the contents of a corrupted volume, it may be useful to resynchronize a volume from its snapshot volume (which is used as a hot standby).

To resynchronize a volume

Use the following command syntax:

```
vxsnap -g database dg restore database vol source=snapvol \
   destroy=yes|no
```

The destroy attribute specifies whether the plexes of the snapshot volume are to be reattached to the original volume.

For example, to resynchronize the volume *database vol* from its snapshot volume snapvol without removing the snapshot volume:

```
# vxsnap -g database dg restore database vol \
  source=snapvol destroy=no
```

Note: You must shut down the database and unmount the file system that is configured on the original volume before attempting to resynchronize its contents from a snapshot.

Making an off-host backup of an online Sybase database

To make an off-host backup of an online Sybase database

On the primary host, add one or more snapshot plexes to the volume using this command:

```
# vxsnap -g database dg addmir database vol [nmirror=N] \
 [alloc=storage attributes]
```

By default, one snapshot plex is added unless you specify a number using the nmirror attribute. For a backup, you should usually only require one plex. You can specify storage attributes (such as a list of disks) to determine where the plexes are created.

Suspend updates to the volumes. As the Sybase database administrator, put the database in quiesce mode by using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to quiesce example Sybase ASE database.
# Note: The "for external dump" clause was introduced in Sybase
# ASE 12.5 to allow a snapshot database to be rolled forward.
# See the Sybase ASE 12.5 documentation for more information.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag hold database1[, database2]... [for
external dump]
go
quit
!
```

Use the following command to make a full-sized snapshot, *snapvol*, of the tablespace volume by breaking off the plexes that you added in step 1 from the original volume:

```
# vxsnap -g database dg make \
  source=database vol/newvol=snapvol/nmirror=N \
   [alloc=storage attributes]
```

The nmirror attribute specifies the number of mirrors, *N*, in the snapshot volume.

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database dg make source=database vol1/snapvol=snapvol1 \
  source=database vol/snapvol=snapvol2 \
  source=database vol3/snapvol=snapvol3 alloc=ctlr:c3,ctlr:c4
```

This step sets up the snapshot volumes ready for the backup cycle, and starts tracking changes to the original volumes.

Release all the tablespaces or databases from quiesce mode. As the Sybase database administrator, release the database from quiesce mode using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to release example Sybase ASE database from quiesce
# mode.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag release
go
quit
!
```

On the primary host, split the disks containing the snapshot volumes into a separate disk group, snapvoldg, from the original disk group, database dg using the following command:

```
# vxdg split database dg snapvoldg snapvol ...
```

- 6 On the primary host, deport the snapshot volume's disk group using the following command:
 - # vxdq deport snapvoldq
- On the OHP host where the backup is to be performed, use the following command to import the snapshot volume's disk group:
 - # vxdg import snapvoldg
- VxVM will recover the volumes automatically after the disk group import unless it is set to not recover automatically. Check if the snapshot volume is initially disabled and not recovered following the split.
 - If a volume is in the DISABLED state, use the following command on the OHP host to recover and restart the snapshot volume:
 - # vxrecover -g snapvoldg -m snapvol ...
- On the OHP host, back up the snapshot volumes. If you need to remount the file system in the volume to back it up, first run fsck on the volumes. The following are sample commands for checking and mounting a file system:
 - # fsck -t vxfs /dev/vx/rdsk/snapvoldg/snapvol
 - # mount -t vxfs /dev/vx/dsk/snapvoldg/snapvol mount point

Back up the file system using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.

- # umount mount point
- 10 On the OHP host, use the following command to deport the snapshot volume's disk group:
 - # vxdq deport snapvoldq
- 11 On the primary host, re-import the snapshot volume's disk group using the following command:
 - # vxdg [-s] import snapvoldg

Note: Specify the -s option if you are reimporting the disk group to be rejoined with a shared disk group in a cluster.

- 12 On the primary host, use the following command to rejoin the snapshot volume's disk group with the original volume's disk group:
 - # vxdq join snapvoldq database dq
- 13 VxVM will recover the volumes automatically after the join unless it is set not to recover automatically. Check if the snapshot volumes are initially disabled and not recovered following the join.

If a volume is in the DISABLED state, use the following command on the primary host to recover and restart the snapshot volume:

- # vxrecover -g database dg -m snapvol
- 14 On the primary host, reattach the snapshot volumes to their original volume using the following command:
 - # vxsnap -g database dg reattach snapvol source=database vol \ [snapvol2 source=database vol2]...

For example, to reattach the snapshot volumes *snapvol1*, *snapvol2* and snapvol3:

```
# vxsnap -g database dg reattach snapvol1 source=database vol1 \
  snapvol2 source=database vol2 snapvol3 source=database vol3
```

While the reattached plexes are being resynchronized from the data in the parent volume, they remain in the SNAPTMP state. After resynchronization is complete, the plexes are placed in the SNAPDONE state. You can use the vxsnap print command to check on the progress of synchronization.

Repeat steps 2 through 14 each time that you need to back up the volume.

Backing up on an off-host cluster file system

Storage Foundation Cluster File System High Availability (SFCFSHA) allows cluster nodes to share access to the same file system. SFCFSHA is especially useful for sharing read-intensive data between cluster nodes.

Off-host backup of cluster file systems may be implemented by taking a snapshot of the volume containing the file system and performing the backup operation on a separate host.

Figure 5-3 shows an example where the primary volume that contains the file system to be backed up is configured on disks attached to controllers c1 and c2, and the snapshots are to be created on disks attached to controllers *c*3 and *c*4.




Figure 5-3 System configuration for off-host file system backup scenarios

To set up an off-host cluster file system backup:

- Mount a VxFS file system for shared access by the nodes of a cluster. See "Mounting a file system for shared access" on page 78.
- Prepare a snapshot of the mounted file system with shared access.
- Back up a snapshot of a mounted file system with shared access See "Backing up a snapshot of a mounted file system with shared access" on page 80.
- All commands require superuser (root) or equivalent privileges.

Mounting a file system for shared access

To mount a VxFS file system for shared access, use the following command on each cluster node where required:

```
# mount -t vxfs -o cluster /dev/vx/dsk/database dg/database vol
  mount point
```

For example, to mount the volume *database_vol* in the disk group *database_dg* for shared access on the mount point, /mnt pnt:

```
# mount -t vxfs -o cluster /dev/vx/dsk/database dg/database vol /mnt pnt
```

Preparing a snapshot of a mounted file system with shared access

You must use a full-sized snapshot for your off-host backup.

Warning: To avoid data inconsistencies, do not use the same snapshot with different point-in-time copy applications. If you require snapshot mirrors for more than one application, configure at least one snapshot mirror that is dedicated to each application.

To prepare to back up a snapshot of a mounted file system which has shared access

On the master node, use the following command to make a full-sized snapshot, snapvol, of the volume containing the file system by breaking off plexes from the original volume:

```
# vxsnap -g database dg make \
 source=database vol/newvol=snapvol/nmirror=N
```

The nmirror attribute specifies the number of mirrors, N, in the snapshot volume.

For example, to take a snapshot of the volume *database vol* in the shared disk group exampledg:

```
# vxsnap -q database dq make source=database vol/newvol=snapvol
/nmirror=1
```

If the volume does not have any available plexes, or its layout does not support plex break-off, prepare an empty volume for the snapshot.

Use the vxprint command on the original volume to find the required size for the snapshot volume.

```
# LEN='vxprint [-g database dg] -F%len database vol'
```

Note: The command shown in this and subsequent steps assumes that you are using a Bourne-type shell such as sh, ksh or bash. You may need to modify the command for other shells such as csh or tcsh. These steps are valid only for instant snap DCOs.

- Use the vxprint command on the original volume to discover the name of its DCO:
 - # DCONAME='vxprint [-g database dg] -F%dco name database vol'
- Use the vxprint command on the DCO to discover its region size (in blocks):
 - # RSZ='vxprint [-g database dg] -F%regionsz \$DCONAME'
- Use the vxassist command to create a volume, snapvol, of the required size and redundancy, together with an instant snap DCO volume with the correct region size:
 - # vxassist [-g database_dg] make snapvol \$LEN \ [layout=mirror nmirror=number] logtype=dco drl=no \ dcoversion=20 [ndcomirror=number] regionsz=\$RSZ \ init=active [storage attributes]

It is recommended that you specify the same number of DCO mirrors (ndcomirror) as the number of mirrors in the volume (nmirror). The init=active attribute is used to make the volume available immediately. You can use storage attributes to specify which disks should be used for the volume.

As an alternative to creating the snapshot volume and its DCO volume in a single step, you can first create the volume, and then prepare it for instant snapshot operations as shown here:

```
# vxassist [-g database_dg] make snapvol $LEN \
  [layout=mirror nmirror=number] init=active \
  [storage attributes]
# vxsnap [-g database dg] prepare snapvol [ndcomirs=number] \
 regionsz=$RSZ [storage attributes]
```

- Then use the following command to create the snapshot:
 - # vxsnap -g database_dg make source=database_dg/snapvol=snapvol

Note: This step actually takes the snapshot and sets up the snapshot volumes ready for the backup cycle, and starts tracking changes to the original volumes.

When you are ready to make a backup, proceed to step 1.

Backing up a snapshot of a mounted file system with shared access

While you can run the commands in the following steps from any node, Symantec recommends running them from the master node.

To back up a snapshot of a mounted file system which has shared access

- On any node, refresh the contents of the snapshot volumes from the original volume using the following command:
 - # vxsnap -g database dg refresh snapvol source=database vol \ [snapvol2 source=database vol2]... syncing=yes

The syncing=yes attribute starts a synchronization of the snapshot in the background.

For example, to refresh the snapshot *snapvol*:

vxsnap -g database dg refresh snapvol source=database vol \ syncing=yes

This command can be run every time you want to back up the data. The vxsnap refresh command will resync only those regions which have been modified since the last refresh.

- On any node of the cluster, use the following command to wait for the contents of the snapshot to be fully synchronous with the contents of the original volume:
 - # vxsnap -g database dg syncwait snapvol

For example, to wait for synchronization to finish for the snapshots *snapvol*:

vxsnap -g database_dg syncwait snapvol

Note: You cannot move a snapshot volume into a different disk group until synchronization of its contents is complete. You can use the vxsnap print command to check on the progress of synchronization.

- On the master node, use the following command to split the snapshot volume into a separate disk group, snapvoldg, from the original disk group, database dg:
 - # vxdg split volumedg snapvoldg snapvol

For example, to place the snapshot of the volume *database vol* into the shared disk group splitdg:

- # vxdg split database dg splitdg snapvol
- On the master node, deport the snapshot volume's disk group using the following command:
 - # vxdg deport snapvoldg

For example, to deport the disk group splitdg:

- # vxdg deport splitdg
- 5 On the OHP host where the backup is to be performed, use the following command to import the snapshot volume's disk group:
 - # vxdg import snapvoldg

For example, to import the disk group splitdg:

- # vxdg import splitdg
- VxVM will recover the volumes automatically after the disk group import unless it is set not to recover automatically. Check if the snapshot volume is initially disabled and not recovered following the split.

If a volume is in the DISABLED state, use the following command on the OHP host to recover and restart the snapshot volume:

```
# vxrecover -g snapvoldg -m snapvol
```

For example, to start the volume *snapvol*:

```
# vxrecover -g splitdg -m snapvol
```

- On the OHP host, use the following commands to check and locally mount the snapshot volume:
 - # fsck -t vxfs /dev/vx/rdsk/database dg/database vol
 - # mount -t vxfs /dev/vx/dsk/database dg/database vol mount point

For example, to check and mount the volume *snapvol* in the disk group *snapvoldg* for shared access on the mount point, /bak/mnt pnt:

- # fsck -t vxfs /dev/vx/rdsk/snapvoldg/snapvol
- # mount -t vxfs /dev/vx/dsk/snapvoldq/snapvol /bak/mnt pnt
- Back up the file system at this point using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.
 - # umount mount point
- On the off-host processing host, use the following command to deport the snapshot volume's disk group:
 - # vxdq deport snapvoldq

For example, to deport *snapvoldg*:

- # vxdq deport snapvoldq
- 10 On the master node, re-import the snapshot volume's disk group as a shared disk group using the following command:
 - # vxdg -s import snapvoldg

For example, to import *snapvoldg*:

- # vxdq -s import snapvoldq
- 11 On the master node, use the following command to rejoin the snapshot volume's disk group with the original volume's disk group:
 - # vxdg join snapvoldg database dg

For example, to join disk group *snapvoldg* with *database dg*:

vxdg join snapvoldg database dg

12 VxVM will recover the volumes automatically after the join unless it is set not to recover automatically. Check if the snapshot volumes are initially disabled and not recovered following the join.

If a volume is in the DISABLED state, use the following command on the primary host to recover and restart the snapshot volume:

- # vxrecover -g database dg -m snapvol
- 13 When the backup is complete, use the following command to unmount the snapshot volume, and make it ready for its contents to be refreshed from the primary volume:
 - # umount mount point

When synchronization is complete, the snapshot is ready to be re-used for backup.

Warning: Before attempting to unmount the snapshot, shut down all applications that access a file system in the snapshot volume, and also unmount any such file system.

Repeat the entire procedure each time that you need to back up the volume.

Resynchronizing a volume from its snapshot volume

In some instances, such as recovering the contents of a corrupted volume, it may be useful to resynchronize a volume from its snapshot volume (which is used as a hot standby).

To resynchronize a volume from its snapshot volume

Enter:

```
vxsnap -q database dg restore database vol source=snapvol \
   destroy=yes|no
```

The destroy attribute specifies whether the plexes of the snapshot volume are to be reattached to the original volume. For example, to resynchronize the volume database vol from its snapshot volume snapvol without removing the snapshot volume:

vxsnap -g database dg restore database vol source=snapvol destroy=no

Note: You must unmount the file system that is configured on the original volume before attempting to resynchronize its contents from a snapshot.

Reattaching snapshot plexes

Some or all plexes of an instant snapshot may be reattached to the specified original volume, or to a source volume in the snapshot hierarchy above the snapshot volume.

Note: This operation is not supported for space-optimized instant snapshots.

By default, all the plexes are reattached, which results in the removal of the snapshot. If required, the number of plexes to be reattached may be specified as the value assigned to the nmirror attribute.

Note: The snapshot being reattached must not be open to any application. For example, any file system configured on the snapshot volume must first be unmounted.

To reattach a snapshot

Use the following command to reattach an instant snapshot to the specified original volume, or to a source volume in the snapshot hierarchy above the snapshot volume:

```
vxsnap [-q database dq] reattach snapvol source=database vol \
  [nmirror=number]
```

For example the following command reattaches 1 plex from the snapshot volume, snapvol, to the volume, database vol:

```
# vxsnap -g database dg reattach snapvol source=database vol nmirror=1
```

While the reattached plexes are being resynchronized from the data in the parent volume, they remain in the SNAPTMP state. After resynchronization is complete, the plexes are placed in the SNAPDONE state.

The vxsnap refresh and vxsnap reattach commands have slightly different behaviors.

The vxsnap reattach command reattaches a snapshot volume to its source volume and begins copying the volume data to the snapshot volume.

The vxsnap refresh commands updates the snapshot volumes contents view. The updated snapshot is available immediately with the new contents while synchronization occurs in the background.

Database recovery using Storage Checkpoints

You can use Storage Checkpoints to implement efficient backup and recovery of databases that have been laid out on VxFS file systems. A Storage Checkpoint allows you to roll back an entire database, a tablespace, or a single database file to the time that the Storage Checkpoint was taken. Rolling back to or restoring from any Storage Checkpoint is generally very fast because only the changed data blocks need to be restored.

Storage Checkpoints can also be mounted, allowing regular file system operations to be performed or secondary databases to be started.

For information on how to administer Storage Checkpoints, see Veritas Storage Foundation™ Administrator's Guide.

For information on how to administer Database Storage Checkpoints for an Oracle database, see *Veritas Storage Foundation™*: Storage and High Availability Mangement for Oracle Databases.

Note: Storage Checkpoints can only be used to restore from logical errors such as human mistakes or software faults. You cannot use them to restore files after a disk failure because all the data blocks are on the same physical device. Disk failure requires restoration of a database from a backup copy of the database files kept on a separate medium. Combining data redundancy (for example, disk mirroring) with Storage Checkpoints is recommended for highly critical data to protect against both physical media failure and logical errors.

Storage Checkpoints require space in the file systems where they are created, and the space required grows over time as copies of changed file system blocks are made. If a file system runs out of space, and there is no disk space into which the file system and any underlying volume can expand, VxFS automatically removes the oldest Storage Checkpoints if they were created with the removable attribute.

Creating Storage Checkpoints

To create Storage Checkpoints, select 3 Storage Checkpoint Administration > Create New Storage Checkpoints in the VxDBA utility. This can be done with a database either online or offline.

Note: To create a Storage Checkpoint while the database is online, ARCHIVELOG mode must be enabled in Oracle. During the creation of the Storage Checkpoint, the tablespaces are placed in backup mode. Because it only takes a few seconds to take a Storage Checkpoint, the extra redo logs generated while the tablespaces are in online backup mode are very small. To optimize recovery, it is recommended that you keep ARCHIVELOG mode enabled.

Warning: Changes to the structure of a database, such as the addition or removal of datafiles, make Storage Rollback impossible if they are made after a Storage Checkpoint was taken. A backup copy of the control file for the database is saved under the /etc/vx/vxdba/ORACLE SID/checkpoint dir directory immediately after a Storage Checkpoint is created. If necessary, you can use this file to assist with database recovery. If possible, both an ASCII and binary copy of the control file are made, with the binary version being compressed to conserve space. Use extreme caution if you attempt to recover your database using these control files. It is recommended that you remove old Storage Checkpoints and create new ones whenever you restructure a database.

Rolling back a database

The procedure in this section describes how to roll back a database using a Storage Checkpoint, for example, after a logical error has occurred.

To roll back a database

- Ensure that the database is offline. You can use the VxDBA utility to display the status of the database and its tablespaces, and to shut down the database:
 - Select 2 Display Database/VxDBA Information to access the menus that display status information.
 - Select 1 Database Administration > Shutdown Database Instance to shut down a database.
- Select 4 Storage Rollback Administration > Roll Back the Database to a Storage Checkpoint in the VxDBA utility, and choose the appropriate Storage Checkpoint. This restores all data files used by the database, except redo logs and control files, to their state at the time that the Storage Checkpoint was made.
- Start up, but do not open, the database instance by selecting 1 Database Administration > Startup Database Instance in the VxDBA utility.
- Use one of the following commands to perform an incomplete media recovery of the database:
 - Recover the database until you stop the recovery:

```
recover database until cancel;
alter database [database] recover cancel;
```

■ Recover the database to the point just before a specified system change number, scn:

```
recover database until change scn;
```

■ Recover the database to the specified time:

```
recover database until time 'yyyy-mm-dd:hh:mm:ss';
```

■ Recover the database to the specified time using a backup control file:

```
recover database until time 'yyyy-mm-dd:hh:mm:ss' \
using backup controlfile;
```

Note: To find out when an error occurred, check the ../bdump/alert*.log file.

See the Oracle documentation for complete and detailed information on database recovery.

To open the database after an incomplete media recovery, use the following command:

alter database open resetlogs;

Note: The resetlogs option is required after an incomplete media recovery to reset the log sequence. Remember to perform a full database backup and create another Storage Checkpoint after log reset.

Perform a full database backup, and use the VxDBA utility to remove any existing Storage Checkpoints that were taken before the one to which you just rolled back the database. These Storage Checkpoints can no longer be used for Storage Rollback. If required, use the VxDBA utility to delete the old Storage Checkpoints and to create new ones.

Chapter 6

Backing up and recovering in a NetBackup environment

This chapter includes the following topics:

- About Veritas NetBackup
- About using Veritas NetBackup for backup and restore for DB2
- About using NetBackup for backup and restore for Sybase
- Using NetBackup in an SFHA Solutions product environment

About Veritas NetBackup

Veritas NetBackup provides backup, archive, and restore capabilities for database files and directories contained on client systems in a client-server network. NetBackup server software resides on platforms that manage physical backup storage devices. The NetBackup server provides robotic control, media management, error handling, scheduling, and a repository of all client backup images.

Administrators can set up schedules for automatic, unattended full and incremental backups. These backups are managed entirely by the NetBackup server. The administrator can also manually back up clients. Client users can perform backups, archives, and restores from their client system, and once started, these operations also run under the control of the NetBackup server.

Veritas NetBackup can be configured for DB2 in an Extended Edition (EE) or Extended-Enterprise Edition (EEE) environment. For detailed information and

instructions on configuring DB2 for EEE, see "Configuring for a DB2 EEE (DPF) Environment" in the Veritas NetBackup for DB2 System Administrator's Guide for UNIX.

Veritas NetBackup, while not a shipped component of Veritas Storage Foundation Enterprise products, can be purchased separately.

About using Veritas NetBackup for backup and restore for DB2

With Veritas NetBackup, you can perform high performance, online (hot) backups of databases that must be available on a 24x7 basis. NetBackup supports the Extended Edition (EE) and the Enterprise Extended Edition (EEE) environments. NetBackup also supports Database Partitioning Feature (DPF) for DB2 8.1 and higher.

Veritas NetBackup enables you to back up and restore database files and directories. You can set up schedules for automatic, unattended database backup, as well as full or incremental backup. These backups are managed entirely by the NetBackup server. You can also manually back up database files from any of the NetBackup clients. Client users can perform database backups and restores from their client systems on demand.

Veritas NetBackup can be configured for DB2 in an Extended Edition (EE), Extended-Enterprise Edition (EEE), or Database Partitioning Feature (DPF) environment. Two types of DB2 backup policies are required. One is used to backup the catalog nodes and the other is used to backup all the nodes, including the catalog node. Detailed information and instructions on configuring DB2 for EEE is available in the system administrator's guide.

See the Veritas NetBackup for DB2 System Administrator's Guide for UNIX.

Veritas NetBackup for DB2 has the following features:

- Media and device management
- Scheduling facilities
- Multiplexed backups and restores
- Transparent execution of both DB2 and regular file system backup and restore operations
- Shared devices and tapes used during other file backups
- Centralized and networked backup operations
- Parallel backup and restore operations

■ Incremental backups of DB2 databases

Table 6-1 Options for backing up DB2 with NetBackup

	Automatically	Manually	DB2 BACKUP DATABASE command
DB2 database log backups	Supported	Supported	Supported
DB2 archive log backups	Supported	Supported	Supported
DB2 policy backups	Supported	Supported	

Setting up schedules for automatic backups is the most convenient way to back up your database.

See 'Performing a Backup' in the Veritas NetBackup for DB2 System Administrator's Guide for UNIX.

The procedure for restoring a DB2 database depends on the database involved and the problems that you have on your system. You can browse the backups using the db2 list history command or using the NetBackup bplist command before restoring.

See the DB2 UDB Administration Guide Data Recovery and High Availability Guide.

About using NetBackup for backup and restore for **Sybase**

Veritas NetBackup for Sybase is not included in the standard Veritas Database Edition. The information included here is for reference only.

Veritas NetBackup for Sybase integrates the database backup and recovery capabilities of Sybase Backup Server with the backup and recovery management capabilities of NetBackup.

Veritas NetBackup works with Sybase APIs to provide high-performance backup and restore for Sybase dataservers. With Veritas NetBackup, you can set up schedules for automatic, unattended backups for Sybase ASE dataservers (NetBackup clients) across the network. These backups can be full database dumps or incremental backups (transaction logs) and are managed by the NetBackup server. You can also manually backup dataservers. The Sybase dump and load commands are used to perform backups and restores.

Veritas NetBackup has both graphical and menu driven user interfaces to suit your needs.

For details, refer to Veritas NetBackup System Administrator's Guide for UNIX.

Using NetBackup in an SFHA Solutions product environment

You can enhance the ease of use and efficiency of your SFHA Solutions product and NetBackup by integrating them as follows:

- Clustering a NetBackup Master Server
- Backing up and recovering a VxVM volume using NetBackup

Clustering a NetBackup Master Server

To enable your NetBackup Master Server to be highly available in a cluster environment, use the following procedure.

To make a NetBackup Master Server, media, and processes highly available

- Verify that your versions of NetBackup and Veritas Cluster Server are compatible. Detailed combination information is included in the NetBackup cluster compatibility list:
 - For NetBackup 7.x cluster compatibility: http://www.symantec.com/business/support/index?page=content&id=TECH126902
 - For NetBackup 6.x cluster compatibility: See http://www.symantec.com/business/support/index?page=content&id=TECH43619
 - For NetBackup 5.x cluster compatibility: http://www.symantec.com/business/support/index?page=content&id=TECH29272
 - For more on NetBackup compatibility, see http://www.symantec.com/business/support/index?page=landing&kev=15145
- The steps to cluster a Master Server are different for different versions of NetBackup. See the applicable NetBackup guide for directions.
 - For NetBackup 7.x: See Symantec NetBackup Clustered Master Server Administrator's Guide See http://www.symantec.com/docs/DOC3679
 - For NetBackup 7.0.1:

See Symantec NetBackup Clustered Master Server Administrator's Guide 7.0.1

See http://www.symantec.com/docs/DOC135520

- For NetBackup 7.0: See NetBackup High Availability Guide 7.0 See http://www.symantec.com/docs/DOC127045
- For NetBackup 6.5: See NetBackup High Availability Guide 6.5 See http://www.symantec.com/docs/DOC52835
- For more on NetBackup documentation, see http://www.symantec.com/business/support/index?page=landing&key=15145

To verify the robustness of the VCS resources and NetBackup processes

- Verify that you can online the Netbackup master.
- 2 Verify that you can offline the Netbackup master.
- 3 Verify that you can monitor all the NetBackup resources.

Backing up and recovering a VxVM volume using NetBackup

To enable NetBackup to backup objects on a VxVM volume, use the following procedure. This procedure enables an Instant Recovery (IR) using a VxVM volume.

To back up objects in a VxVM volume using NetBackup

Create a VxVM disk group with six disks. The number of disks may vary depending on the volume size, disk size, volume layout, and snapshot method.

If the system this test is running on is a clustered system, create a shared disk group using the -s option.

```
# vxdg -s init database dg disk1 disk2 disk3 \
disk4 disk5 disk6
```

2 Create a "mirror-striped" VxVM volume with a size of 10 Gbytes or the maximum size of the disk, whichever is larger.

```
# vxassist -g database dg make vol name 10G \
layout=mirror-stripe init=active
# vxvol -g database dg set fastresync=on vol name
# vxassist -g database dg snapstart nmirror=1 vol name
```

Note: There are three types of snapshot: mirror, full-size instant, and space-optimized instant shanpshots. The example uses an Instant Recovery (IR) snapshot. For snapshot creation details:

See pages 104-107 of the NetBackup Snapshot Client Administrator's Guide for 7.1.

See http://www.symantec.com/docs/DOC3661

- 3 Make the file system on the volume.
- Mount a VxFS file system on the volume.

If the VxVM volume is a clustered volume, mount the VxFS file system with the "-o cluster" option.

- Fill up the VxFS file system up to the desired level. For example, you can fill to 95% full, or to whatever level is appropriate for your file system.
- Store the cksum(1) for these files.
- 7 Un-mount the VxFS file system.
- 8 Enable the following Advanced Client option:
 - Perform Snapshot Backup.
 - Set Advanced Snapshot Options to vxvm.

- **■** Enable **Retain snapshots for instant recovery**.
- Back up the VxVM volume with the NetBackup policy.

See pages 98-101 of the NetBackup Snapshot Client Administrator's Guide for 7.1.

See http://www.symantec.com/docs/DOC3661

Recovering a VxVM volume using NetBackup

To enable NetBackup to recover objects on a VxVM volume, use the following procedure. This procedure performs an Instant Recovery (IR) using a VxVM volume.

To recover objects in a VxVM volume using NetBackup

- Initialize the VxVM volume to zeros.
- 2 Recover the VxVM volume to the newly initialized VxVM volume.
- 3 Mount the VxFS file system on the empty VxVM volume.
- Verify the cksum(1) values against the files recovered.

Chapter

Off-host processing

This chapter includes the following topics:

- Storage Foundation off-host processing methods
- Using a replica database for decision support
- What is off-host processing?
- About using VVR for off-host processing

Storage Foundation off-host processing methods

While backup and recovery is an important use case for Storage Foundation point-in-time copy methods, they can also be used for:

- Periodic analysis (mining) of production data
- Predictive what-if analysis
- Software testing against real data
- Application or database problem diagnosis and resolution

Off-host processing use cases are similar to the backup use case in that they generally require consistent images of production data sets. They differ from backup in the three important respects:

- Access mode Whereas backup is a read-only activity, most off-host processing activities update the data they process. Thus, Snapshot File Systems are of limited utility for off-host processing uses.
- Multiple uses

 Backup uses each source data image once, after which the snapshot can be discarded. With other use cases, it is often useful to perform several experiments on the same data set. It is possible to take snapshots of both

Storage Checkpoints and Space-Optimized Instant Snapshots of production data. This facility provides multiple identical data images for exploratory applications at almost no incremental overhead. Rather than testing destructively against a snapshot containing the data set state of interest, tests can be run against snapshots of that snapshot. After each test, the snapshot used can be deleted, leaving the original snapshot containing the starting state intact. Any number of tests or analyses can start with the same data, providing comparable alternatives for evaluation. All such tests can be run while production applications simultaneously process live data.

■ Scheduling

Whereas backup is typically a regularly scheduled activity, allowing storage and I/O capacity needs to be planned, other applications of snapshots must run with little or no notice. Full-sized and space-optimized instant snapshots and Storage Checkpoints provide instantly accessible snapshots, and are therefore more suitable for these applications.

Storage Foundation examples for data analysis and off-host processing use cases:

- Decision support
- Active secondary use-case with VVR

Using a replica database for decision support

You can use snapshots of a primary database to create a replica of the database at a given moment in time. You can then implement decision support analysis and report generation operations that take their data from the database copy rather than from the primary database. The FastResync functionality of Veritas Volume Manager (VxVM) allows you to quickly refresh the database copy with up-to-date information from the primary database. Reducing the time taken to update decision support data also lets you generate analysis reports more frequently.

Two methods are described for setting up a replica database for decision support:

- See "Creating a replica database on the same host" on page 99.
- See "Creating an off-host replica database" on page 109.


Note: All commands require superuser (root) or equivalent privileges, except where it is explicitly stated that a command must be run by the database administrator.

Creating a replica database on the same host

Figure 7-1 shows an example where the primary database volumes to be backed up, dbase vol and dbase logs, are configured on disks attached to controllers c1 and c2, and the snapshots are to be created on disks attached to controllers c3 and c4.

Figure 7-1 Example system configuration for decision support on the primary host

Primary host for database



To set up a replica database to be used for decision support on the primary host

- Prepare the snapshot, either full-sized or space-optimized. See "Preparing a full-sized instant snapshot for a backup" on page 56.
- Create snapshot mirrors for volumes containing VxFS file systems for database files to be backed up.
- Make the database replica.
- All commands require superuser (root) or equivalent privileges.

Preparing for the replica database

To prepare a snapshot for a replica database on the primary host

- If you have not already done so, prepare the host to use the snapshot volume that contains the copy of the database tables. Set up any new database logs and configuration files that are required to initialize the database.
- Use the following command to make a full-sized snapshot, *snapvol*, of the tablespace volume by breaking off plexes from the original volume:

```
# vxsnap -g database dg make \
 source=volume/newvol=snapvol/nmirror=N
```

The nmirror attribute specifies the number of mirrors, N, in the snapshot volume.

If the volume does not have any available plexes, or its layout does not support plex break-off, prepare an empty volume for the snapshot.

Use the vxprint command on the original volume to find the required size for the snapshot volume.

```
# LEN='vxprint [-q diskgroup] -F%len volume'
```

Note: The command shown in this and subsequent steps assumes that you are using a Bourne-type shell such as sh, ksh or bash. You may need to modify the command for other shells such as csh or tcsh. These steps are valid only for an instant snap DCO.

Use the vxprint command on the original volume to discover the name of its DCO:

```
DCONAME='vxprint [-g diskgroup] -F%dco name volume'
```

Use the vxprint command on the DCO to discover its region size (in blocks):

```
# RSZ='vxprint [-g diskgroup] -F%regionsz $DCONAME'
```

Use the vxassist command to create a volume, snapvol, of the required size and redundancy, together with an instant snap DCO volume with the correct region size:

```
# vxassist [-g diskgroup] make snapvol $LEN \
  [layout=mirror nmirror=number] logtype=dco drl=no \
 dcoversion=20 [ndcomirror=number] regionsz=$RSZ \
 init=active [storage attributes]
```

It is recommended that you specify the same number of DCO mirrors (ndcomirror) as the number of mirrors in the volume (nmirror). The init=active attribute is used to make the volume available immediately. You can use storage attributes to specify which disks should be used for the volume.

As an alternative to creating the snapshot volume and its DCO volume in a single step, you can first create the volume, and then prepare it for instant snapshot operations as shown here:

```
# vxassist [-q diskgroup] make snapvol $LEN \
  [layout=mirror nmirror=number] init=active \
  [storage attributes]
# vxsnap [-g diskgroup] prepare snapvol [ndcomirs=number] \
 regionsz=$RSZ [storage attributes]
```

To create the snapshot, use the following command:

```
# vxsnap -g database dg make source=volume/snapvol=snapvol
```

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database dg make \
source=vol1/snapvol=svol1/nmirror=2 \
source=vol2/snapvol=svol2/nmirror=2 \
source=vol3/snapvol=svol3/nmirror=2
```

If you want to save disk space, you can use the following command to create a space-optimized snapshot instead:

```
# vxsnap -g database dg make \
 source=volume/newvol=snapvol/cache=cacheobject
```

The argument cacheobject is the name of a pre-existing cache that you have created in the disk group for use with space-optimized snapshots.

If several space-optimized snapshots are to be created at the same time, these can all specify the same cache object as shown in this example:

```
# vxsnap -g database dg make \
 source=vol1/newvol=svol1/cache=dbaseco \
 source=vol2/newvol=svol2/cache=dbaseco \
 source=vol3/newvol=svol3/cache=dbaseco
```

- Decide on the following characteristics that you want to allocate to the cache volume that underlies the cache object:
 - The size of the cache volume should be sufficient to record changes to the parent volumes during the interval between snapshot refreshes. A suggested value is 10% of the total size of the parent volumes for a refresh interval of 24 hours.
 - If redundancy is a desired characteristic of the cache volume, it should be mirrored. This increases the space that is required for the cache volume in proportion to the number of mirrors that it has.
 - If the cache volume is mirrored, space is required on at least as many disks as it has mirrors. These disks should not be shared with the disks used for the parent volumes. The disks should also be chosen to avoid impacting I/O performance for critical volumes, or hindering disk group split and join operations.

- ${f 9}$ Having decided on its characteristics, use the <code>vxassist</code> command to create the volume that is to be used for the cache volume. The following example creates a mirrored cache volume, cachevol, with size 1GB in the disk group, mydg, on the disks disk16 and disk17:
 - # vxassist -g mydg make cachevol 1g layout=mirror \ init=active disk16 disk17

The attribute init-active is specified to make the cache volume immediately available for use.

10 Use the vxmake cache command to create a cache object on top of the cache volume that you created in the previous step:

```
# vxmake [-g diskgroup] cache cache object \
 cachevolname=volume [regionsize=size] [autogrow=on] \
  [highwatermark=hwmk] [autogrowby=agbvalue] \
  [maxautogrow=maxagbvalue]]
```

If you specify the region size, it must be a power of 2, and be greater than or equal to 16KB (16k). If not specified, the region size of the cache is set to 64KB.

Note: All space-optimized snapshots that share the cache must have a region size that is equal to or an integer multiple of the region size set on the cache. Snapshot creation also fails if the original volume's region size is smaller than the cache's region size.

If the cache is not allowed to grow in size as required, specify autogrow=off. By default, the ability to automatically grow the cache is turned on.

In the following example, the cache object, cobjmydg, is created over the cache volume, cachevol, the region size of the cache is set to 32KB, and the autogrow feature is enabled:

```
# vxmake -g mydg cache cobjmydg cachevolname=cachevol \
 regionsize=32k autogrow=on
```

11 Having created the cache object, use the following command to enable it:

```
# vxcache [-g diskgroup] start cache_object
```

For example to start the cache object, cobjmydg:

```
# vxcache -g mydg start cobjmydg
```

Note: This step sets up the snapshot volumes, and starts tracking changes to the original volumes.

Creating a replica database

After you prepare the snapshot, you are ready to create a replica of the database.

To create the replica database

- If the volumes to be backed up contain database tables in file systems, suspend updates to the volumes:
 - DB2 provides the write suspend command to temporarily suspend I/O activity for a database. As the DB2 database administrator, use a script such as that shown in the example. Note that to allow recovery from any backups taken from snapshots, the database must be in LOGRETAIN RECOVERY mode.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to suspend I/O for a DB2 database.
# Note: To recover a database using backups of snapshots,
# the database must be in LOGRETAIN mode.
db2 <<!
connect to database
set write suspend for database
quit
!
```

■ Sybase ASE from version 12.0 onward provides the Quiesce feature to allow temporary suspension of writes to a database. As the Sybase database administrator, put the database in quiesce mode by using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to quiesce example Sybase ASE database.
# Note: The "for external dump" clause was introduced in Sybase
# ASE 12.5 to allow a snapshot database to be rolled forward.
# See the Sybase ASE 12.5 documentation for more information.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag hold database1[, database2]... [for
external dump]
go
```

```
quit
```

following steps.

If you are using Sybase ASE 12.5, you can specify the for external dump clause to the guiesce command. This warm standby method allows you to update a replica database using transaction logs dumped from the primary database.

See "Updating a warm standby Sybase ASE 12.5 database" on page 119.

Refresh the contents of the snapshot volumes from the original volume using the following command:

```
# vxsnap -g database_dg refresh snapvol source=vol \
  [snapvol2 source=vol2]...
For example, to refresh the snapshots svol1, svol2 and svol3:
# vxsnap -g database dg refresh svol1 source=vol1 \
```

If you temporarily suspended updates to volumes in step 1, perform the

svol2 source=vol2 svol3 source=vol3

Release all the tablespaces or databases from suspend, hot backup or quiesce mode:

■ As the DB2 database administrator, use a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to resume I/O for a DB2 database.
db2 <<!
connect to database
set write resume for database
quit
!
```

■ As the Sybase database administrator, release the database from quiesce mode using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to release example Sybase ASE database from
# quiesce mode.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag release
αo
quit
```

If you are using Sybase ASE 12.5, you can specify the for external dump clause to the guiesce command. This warm standby method allows you to update a replica database using transaction logs dumped from the primary database.

See "Updating a warm standby Sybase ASE 12.5 database" on page 119.

For each snapshot volume containing tablespaces, check the file system that it contains, and mount the volume using the following commands:

```
# fsck -t vxfs /dev/vx/rdsk/diskgroup/snapvol
# mount -t vxfs /dev/vx/dsk/diskgroup/snapvol
  mount point
```

For example, to check the file system in the snapshot volume snap1 dbase vol, and mount it on /rep dbase vol:

```
# fsck -t vxfs /dev/vx/rdsk/database dg/snap1 dbase vol
# mount -t vxfs /dev/vx/dsk/database dg/snap1 dbase vol \
 /rep dbase vol
```

Copy any required log files from the primary database to the replica database.

For a Sybase ASE database, if you specified the for external dump clause when you quiesced the database, use the following isql command as the database administrator to dump the transaction log for the database:

```
dump transaction to dump device with standby access
```

Then copy the dumped transaction log to the appropriate replica database directory.

- As the database administrator, start the new database:
 - For a Sybase ASE database, use a script such as that shown in the example.

```
#!/bin/ksh
# script: startdb.sh <list of database volumes>
# Sample script to recover and start replica Sybase ASE
# database.
# Import the snapshot volume disk group.
vxdg import $snapvoldg
# Mount the snapshot volumes (the mount points must already
# exist).
for i in $*
do
  fsck -t vxfs /dev/vx/rdsk/$snapvoldg/snap $i
  mount -t vxfs /dev/vx/dsk/$snapvoldg/snap $i \
${rep mnt point}/$i
done
# Start the replica database.
\# Specify the -q option if you specified the "for external \setminus
# dump" clause when you quiesced the primary database.
# See the Sybase ASE 12.5 documentation for more information.
/sybase/ASE-12 5/bin/dataserver \
[-q] \
-sdatabase name \
-d /sybevm/master \
-e /sybase/ASE-12 5/install/dbasename.log \
-M /sybase
# Online the database. Load the transaction log dump and
# specify "for standby access" if you used the -q option
# with the dataserver command.
isql -Usa -Ppassword -SFMR <<!
[load transaction from dump device with standby access
online database database name [for standby access]
```

```
quit
```

If you are using the warm standby method, specify the -q option to the dataserver command. Use the following isgl commands to load the dump of the transaction log and put the database online:

load transaction from dump device with standby access online database database_name for standby_access

If you are not using the warm standby method, use the following isql command to recover the database, roll back any uncommitted transactions to the time that the quiesce command was issued, and put the database online:

online database database name

When you want to resynchronize a snapshot with the primary database, shut down the replica database, unmount the snapshot volume, and go back to step 1 to refresh the contents of the snapshot from the original volume.

Creating an off-host replica database

Figure 7-2 shows an example where the primary database volumes to be backed up, dbase vol and dbase logs, are configured on disks attached to controllers c1 and c2, and the snapshots are to be created on disks attached to controllers c3 and c4.

There is no requirement for the off-host processing host to have access to the disks that contain the primary database volumes.

Note: If the database is configured on volumes in a cluster-shareable disk group, it is assumed that the primary host for the database is the master node for the cluster. If the primary host is not also the master node, all VxVM operations on shared disk groups must be performed on the master node.

Network Primary host for database OHP host Volumes created on local disks of OHP host are used for the replica database's logs and ≥ Local : configuration files disks disks Controllers Controllers c2 с3 c2 с3 с4 c1 c4 c1 Volumes created on these Snapshot volumes created on disks are accessed by the Disk these disks are accessed by both hosts primary host arrays

Figure 7-2 Example system configuration for off-host decision support

To set up a replica database to be used for decision support on another host

- Prepare the full-sized snapshot. See "Preparing a space-optimized snapshot for a database backup" on page 58.
- Create snapshot mirrors for volumes containing VxFS file systems for database files to be backed up.
- Make the database replica.
- All commands require superuser (root) or equivalent privileges.

Setting up a replica database for off-host decision support

To set up a replica database for off-host decision support

- If you have not already done so, prepare the off-host processing host to use the snapshot volume that contains the copy of the database tables. Set up any new database logs and configuration files that are required to initialize the database.
- On the primary host, use the following command to make a full-sized snapshot, snapvol, of the tablespace volume by breaking off plexes from the original volume:

```
# vxsnap -g database dg make \
 source=volume/newvol=snapvol/nmirror=N
```

The nmirror attribute specifies the number of mirrors, N, in the snapshot volume.

If the volume does not have any available plexes, or its layout does not support plex break-off, prepare an empty volume for the snapshot.

Then use the following command to create the snapshot:

```
# vxsnap -q database dq make source=volume/snapvol=snapvol
```

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database dg make source=vol1/snapvol=svol1 \
source=vol2/snapvol=svol2 source=vol3/snapvol=svol3
```

Note: This step sets up the snapshot volumes, and starts tracking changes to the original volumes.

When you are ready to create the replica database, proceed to step 3.

- If the volumes to be backed up contain database tables in file systems, suspend updates to the volumes:
 - DB2 provides the write suspend command to temporarily suspend I/O activity for a database. As the DB2 database administrator, use a script such as that shown in the example. Note that if the replica database must be able to be rolled forward (for example, if it is to be used as a standby database), the primary database must be in LOGRETAIN RECOVERY mode.

```
#!/bin/ksh
```

```
# script: backup start.sh
# Sample script to suspend I/O for a DB2 database.
# Note: To recover a database using backups of snapshots, the database
# must be in LOGRETAIN mode.
db2 <<!
connect to database
set write suspend for database
quit
```

■ Sybase ASE from version 12.0 onward provides the Quiesce feature to allow temporary suspension of writes to a database. As the Sybase database administrator, put the database in quiesce mode by using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to quiesce example Sybase ASE database.
# Note: The "for external dump" clause was introduced in Sybase
# ASE 12.5 to allow a snapshot database to be rolled forward.
# See the Sybase ASE 12.5 documentation for more information.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag hold database1[, database2]... [for external dump]
go
quit
!
```

If you are using Sybase ASE 12.5, you can specify the for external dump clause to the quiesce command. This warm standby method allows you to update a replica database using transaction logs dumped from the primary database.

See "Updating a warm standby Sybase ASE 12.5 database" on page 119.

4 On the primary host, refresh the contents of the snapshot volumes from the original volume using the following command:

```
# vxsnap -q database dq refresh snapvol source=vol \
  [snapvol2 source=vol2]... syncing=yes
```

The syncing=yes attribute starts a synchronization of the snapshot in the background.

For example, to refresh the snapshots svol1, svol2 and svol3:

```
# vxsnap -g database dg refresh svol1 source=vol1 \
   svol2 source=vol2 svol3 source=vol3
```

- If you temporarily suspended updates to volumes in step 3, release all the tablespaces or databases from suspend, hot backup or quiesce mode:
 - As the DB2 database administrator, use a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to resume I/O for a DB2 database.
db2 <<!
connect to database
set write resume for database
quit
!
```

■ As the Sybase database administrator, release the database from quiesce mode using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to release example Sybase ASE database from
  quiesce mode.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag release
```

```
go
quit
!
```

Use the following command to wait for the contents of the snapshot to be fully synchronous with the contents of the original volume:

```
# vxsnap -g database dg syncwait snapvol
```

For example, to wait for synchronization to finish for all the snapshots svol1, svol2 and svol3, you would issue three separate commands:

```
# vxsnap -g database dg syncwait svol1
# vxsnap -g database dg syncwait svol2
# vxsnap -g database dg syncwait svol3
```

Note: You cannot move a snapshot volume into a different disk group until synchronization of its contents is complete. You can use the vxsnap print command to check on the progress of synchronization.

On the primary host, use the following command to split the disks containing the snapshot volumes into a separate disk group, snapvoldg, from the original disk group, database dg:

```
# vxdg split database dg snapvoldgsnapvol ...
```

For example to split the snap volumes from *database dg*:

```
# vxdg split database dg snapvoldg svol1 svol2 svol3
```

8 On the primary host, deport the snapshot volume's disk group using the following command:

```
# vxdq deport snapvoldq
```

On the off-host processing host where the replica database is to be set up, use the following command to import the snapshot volume's disk group:

```
# vxdg import snapvoldg
```

10 VxVM will recover the volumes automatically after the disk group import unless it is set to not recover automatically. Check if the snapshot volume is initially disabled and not recovered following the split.

If a volume is in the DISABLED state, use the following command on the off-host processing host to recover and restart the snapshot volume:

```
# vxrecover -q snapvoldg -m snapvol ...
```

11 On the off-host processing host, for each snapshot volume containing tablespaces, check the file system that it contains, and mount the volume using the following commands:

```
# fsck -t vxfs /dev/vx/rdsk/diskgroup/snapvol
# mount -t vxfs /dev/vx/dsk/diskgroup/snapvol
   mount point
```

For example, to check the file system in the snapshot volume snap1 dbase vol, and mount it on /rep/dbase vol:

```
# fsck -t vxfs /dev/vx/rdsk/snapvoldg/snap1 dbase vol
# mount -t vxfs /dev/vx/dsk/snapvoldg/snap1 dbase vol \
 /rep/dbase vol
```

Note: For a replica DB2 database, the database volume must be mounted in the same location as on the primary host.

12 Copy any required log files from the primary host to the off-host processing host.

For a Sybase ASE database on the primary host, if you specified the for external dump clause when you quiesced the database, use the following isql command as the database administrator to dump the transaction log for the database:

```
dump transaction to dump device with standby access
```

Then copy the dumped transaction log to the appropriate database directory on the off-host processing host.

- **13** As the database administrator, start the new database:
 - If the replica DB2 database is not to be rolled forward, use the following commands to start and recover it:

db2start

db2inidb database as snapshot

If the replica DB2 database is to be rolled forward (the primary must have been placed in LOGRETAIN RECOVERY mode before the snapshot was taken), use the following commands to start it, and put it in roll-forward pending state:

db2start

```
db2inidb database as standby
```

Obtain the latest log files from the primary database, and use the following command to roll the replica database forward to the end of the logs:

db2 rollforward db database to end of logs

■ For a Sybase ASE database, use a script such as that shown in the example.

```
#!/bin/ksh
# script: startdb.sh <list of database volumes>
# Sample script to recover and start replica Sybase ASE
# database.
# Import the snapshot volume disk group.
vxdq import $snapvoldq
# Mount the snapshot volumes (the mount points must already
# exist).
for i in $*
   fsck -t vxfs /dev/vx/rdsk/$snapvoldg/snap $i
   mount -t vxfs /dev/vx/dsk/$snapvoldg/snap $i \
${rep mnt point}/$i
done
# Start the replica database.
# Specify the -q option if you specified the "for external
# dump" clause when you quiesced the primary database.
# See the Sybase ASE 12.5 documentation for more information.
```

```
/sybase/ASE-12 5/bin/dataserver \
[-q] \
-sdatabase name \
-d /sybevm/master \
-e /sybase/ASE-12 5/install/dbasename.log \
-M /sybase
# Online the database. Load the transaction log dump and
\# specify "for standby access" if you used the -q option
# with the dataserver command.
isql -Usa -Ppassword -SFMR <<!
[load transaction from dump device with standby access
online database database name [for standby access]
quit
!
```

If you are using the warm standby method, specify the -g option to the dataserver command. Use the following isgl commands to load the dump of the transaction log and put the database online:

```
load transaction from dump device with standby access
online database database name for standby access
```

If you are not using the warm standby method, use the following isql command to recover the database, roll back any uncommitted transactions to the time that the quiesce command was issued, and put the database online:

```
online database database name
```

Resynchronizing the data with the primary host

This procedure describes how to resynchronize the data in a snapshot with the primary host.

To resynchronize a snapshot with the primary database

- On the off-host processing host, shut down the replica database, and use the following command to unmount each of the snapshot volumes:
 - # umount mount point
- On the off-host processing host, use the following command to deport the snapshot volume's disk group:
 - # vxdg deport snapvoldg
- On the primary host, re-import the snapshot volume's disk group using the following command:
 - # vxdg [-s] import snapvoldg

Note: Specify the -s option if you are reimporting the disk group to be rejoined with a shared disk group in a cluster.

- On the primary host, use the following command to rejoin the snapshot volume's disk group with the original volume's disk group:
 - # vxdg join snapvoldg database dg
- VxVM will recover the volumes automatically after the join unless it is set to not recover automatically. Check if the snapshot volumes are initially disabled and not recovered following the join.

If a volume is in the DISABLED state, use the following command on the primary host to recover and restart the snapshot volume:

- # vxrecover -g database dg -m snapvol
- Use the steps in Creating an off-host replica database to to resynchronize the snapshot and make the snapshot available at off-host processing host again.
 - The snapshots are now ready to be re-used for backup or for other decision support applications.

Updating a warm standby Sybase ASE 12.5 database

If you specified the for external dump clause when you quiesced the primary database, and you started the replica database by specifying the -q option to the dataserver command, you can use transaction logs to update the replica database.

To update the replica database

On the primary host, use the following isql command to dump the transaction log for the database:

```
dump transaction to dump device with standby access
```

- Copy the transaction log dump to the appropriate database directory on the off-host processing host.
- On the off-host processing host, use the following isql command to load the new transaction log:

```
load transaction from dump device with standby access
```

On the off-host processing host, use the following isql command to put the database online:

```
online database database name for standby access
```

Reattaching snapshot plexes

Some or all plexes of an instant snapshot may be reattached to the specified original volume, or to a source volume in the snapshot hierarchy above the snapshot volume.

Note: This operation is not supported for space-optimized instant snapshots.

By default, all the plexes are reattached, which results in the removal of the snapshot. If required, the number of plexes to be reattached may be specified as the value assigned to the nmirror attribute.

Note: The snapshot being reattached must not be open to any application. For example, any file system configured on the snapshot volume must first be unmounted.

To reattach a snapshot

- Use the following command, to reattach some or all plexes of an instant snapshot to the specified original volume, or to a source volume in the snapshot hierarchy above the snapshot volume:
 - # vxsnap [-q diskgroup] reattach snapvol source=vol \ [nmirror=number]

For example the following command reattaches 1 plex from the snapshot volume, snapmyvol, to the volume, myvol:

vxsnap -q mydq reattach snapmyvol source=myvol nmirror=1

While the reattached plexes are being resynchronized from the data in the parent volume, they remain in the SNAPTMP state. After resynchronization is complete, the plexes are placed in the SNAPDONE state.

What is off-host processing?

Off-host processing consists of performing operations on application data on a host other than the one where the application is running. Typical operations include Decision Support Systems (DSS) and backup. In a VVR environment, off-host processing operations can be performed on the Secondary of the Replicated Data Set. This reduces the load on the application server, the Primary.

The model for data access on the Secondary is that you break off a mirror from each data volume in the RVG, perform the operation on the mirror, and then reattach the mirror while replication is in progress.

About using VVR for off-host processing

This chapter explains how to use Veritas Volume Replicator (VVR) for off-host processing on the Secondary host. You can use the In-Band Control (IBC) Messaging feature with the FastResync (FMR) feature of Veritas Volume Manager (VxVM) and its integration with VVR to take application-consistent snapshots at the replicated volume group (RVG) level. This lets you perform off-host processing on the Secondary host.

This chapter explains how to perform off-host processing operations using the vradmin ibc command. You can also use the vxibc commands to perform off-host processing operations.

Chapter 8

Creating and refreshing test environments

This chapter includes the following topics:

- About test environments
- Creating a test environment
- Refreshing a test environment

About test environments

Sometimes, there is a need to do some testing or development on a copy of production data. In such scenarios, it is essential to provide isolation of these environments from the production environment. This is required so that there is no interference of testing or development environments with production environment. Veritas Storage Foundation can provide a very efficient and cost effective mechanism to create multiple test setups at the same time from a copy of production data. This is done without affecting performance of the production application, at the same time providing complete isolation.

Creating a test environment

Before you set up a test or development environment, you must have a production application volume already created in the application disk group.

To prepare for a test environment

◆ Prepare the application data volume(s) for snapshot operation

vxsnap -g appdg prepare appvol

To create a test environment

- Identify disks to create break-off snapshots. These disks need not be from the same array as the application volume. These disks must be visible to the host that will run test/dev environment.
- Use these disks to create a mirror breakoff snapshot:
 - Add the mirror to create a breakoff snapshot. This step copies application volume data into the new mirror added to create the snapshot.
 - # vxsnap -g appdg addmir appvol alloc=<sdisk1,sdisk2,...>
 - Create a snapshot.
 - # vxsnap -g appdg make src=appvol/nmirror=1/new=snapvol
- Split the diskgroup containing the mirror breakoff snapshot.
 - # vxdg split appdg testdevdg snapvol
- Deport the diskgroup from the production application host
 - # vxdq deport testdevdq
- Import the *testdev* disk group on the host that will run the test environment.
 - # vxdq import testdevdq

Once this step is done, the *snapvol* present in the *testdevdg* disk group is ready to be used for testing or development purposes. If required, it is also possible to create multiple copies of *snapvol* using Veritas Storage Foundation's Flashsnap feature by creating a snapshot of snapvol using method described above.

Refreshing a test environment

Periodically, it may be required to resynchronize the test or development environment with current production data. This can be efficiently achieved using the Flashsnap feature of Storage Foundation and High Availability Solutions products.

To refresh a test environment

- Deport the *testdevdg* disk group from the test environment. This step requires stopping the usage of *snapvol* in the test environment.
 - # vxdq deport testdevdq
- 2 Import *testdevdg* into the production environment.
 - # vxdg import testdevdg
- Reattach the *snapvol* to *appvol* in order to synchronize current production data. Note that this synchronization is very efficient since it copies only the changed data.
 - # vxsnap -g appdg snapvol source=appvol
- When you need to setup the *testdevdg* environment again, recreate the break-off snapshot.
 - # vxsnap -q appdq make src=appvol/nmirror=1/new=snapvol
- Split the diskgroup containing the mirror breakoff snapshot.
 - # vxdg split appdg testdevdg snapvol
- Deport the diskgroup from the production application host
 - # vxdq deport testdevdq
- Import the *testdev* disk group on the host that will run the test environment.
 - # vxdg import testdevdg

Once this step is done, the *snapvol* present in *testdevdg* is ready to be used for testing or development purposes.

You can also create further snapshots of *snapvol* in order to create more test or development environments using the same snapshot. For this purpose, the following mechanisms can be used:

- Mirror breakoff snapshots See "Preparing a full-sized instant snapshot for a backup" on page 56.
- Space-optimized snapshot See "Preparing a space-optimized snapshot for a database backup" on page 58.
- Veritas File System level checkpoints

See "Creating Storage Checkpoints" on page 86.

For more detailed information, see the $\mathit{Veritas}$ $\mathit{Storage}$ $\mathit{Foundation}^{\scriptscriptstyle\mathsf{TM}}$ Administrator's Guide

Chapter 9

Creating point-in-time copies of files

This chapter includes the following topics:

■ Using FileSnaps to create point-in-time copies of files

Using FileSnaps to create point-in-time copies of files

The key to obtaining maximum performance with FileSnaps is to minimize the copy-on-write overhead. You can achieved this by enabling lazy copy-on-write. Lazy copy-on-write is easy to enable and usually results in significantly better performance. If lazy copy-on-write is not a viable option for the use case under consideration, an efficient allocation of the source file can reduce the need of copy-on-write.

Using FileSnaps to provision virtual desktops

Virtual desktop infrastructure (VDI) operating system boot images are a good use case for FileSnaps. The parts of the boot images that can change are user profile, page files (or swap for UNIX/Linux) and application data. You should separate such data from boot images to minimize unsharing. You should allocate a single extent to the master boot image file.

Example of using FileSnaps to provision a virtual desktop

The following example uses a 4 GB master boot image that has a single extent that will be shared by all snapshots.

- # touch /vdi images/master image
- # /opt/VRTS/bin/setext -r 4g -f chgsize /vdi_images/master_image

The master image file can be presented as a disk device to the virtual machine for installing the operating system. Once the operating system is installed and configured, the file is ready for snapshots.

Using FileSnaps to optimize write intensive applications for virtual machines

When virtual machines are spawned to perform certain tasks that are write intensive, a significant amount of unsharing can take place. Symantec recommends that you optimize performance by enabling lazy copy-on-write. If the use case does not allow enabling lazy copy-on-write, with careful planning, you can reduce the occurrence of unsharing. The easiest way to reduce unsharing is to separate the application data to a file other than the boot image. If you cannot do this due to the nature of your applications, then you can take actions similar to the following example.

Example of using FileSnaps to optimize write intensive applications

Assume that the disk space required for a boot image and the application data is 20 GB. Out of this, only 4 GB is used by the operating system and the remaining 16 GB is the space for applications to write. Any data or binaries that are required by each instance of the virtual machine can still be part of the first 4 GB of the shared extent. Since most of the writes are expected to take place on the 16 GB portion, you should allocate the master image in such a way that the 16 GB of space is not shared, as shown in the following commands:

```
# touch /vdi_images/master_image
# /opt/VRTS/bin/setext -r 4g -f chqsize /vdi images/master image
# dd if=/dev/zero of=/vdi images/master image seek=16777215 \
bs=1024 count=1
```

The last command creates a 16 GB hole at the end of the file. Since holes do not have any extents allocated, the writes to hole do not need to be unshared.

Using FileSnaps to create multiple copies of data instantly

It is common to create one or more copies of production data for the purpose of generating reports, mining, and testing. These cases frequently update the copies of the data with the most current data, and one or more copies of the data always exists. FileSnaps can be used to create multiple copies instantly. The application that uses the original data can see a slight performance hit due to the unsharing of data that can take place during updates. This slight impact on performance

can still be present even when all FileSnaps have been deleted. However, you rarely see all FileSnaps being deleted since these use cases usually have one or more copies at any given time.

128 | Creating point-in-time copies of files | Using FileSnaps to create point-in-time copies of files

Section

Maximizing storage utilization

■ Chapter 10. Optimizing storage tiering with SmartTier

Optimizing storage tiering with SmartTier

This chapter includes the following topics:

- About SmartTier
- SmartTier building blocks
- SmartTier use cases for DB2 or Sybase
- Setting up a filesystem for storage tiering with SmartTier
- Relocating old archive logs to tier two storage using SmartTier
- Relocating inactive tablespaces or segments to tier two storage
- Relocating active indexes to premium storage
- Relocating all indexes to premium storage

About SmartTier

SmartTier matches data storage with data usage requirements. After data matching, the data can then be relocated based upon data usage and other requirements determined by the storage or database administrator (DBA).

As more and more data is retained over a period of time, eventually, some of that data is needed less frequently. The data that is needed less frequently still requires a large amount of disk space. SmartTier enables the database administrator to manage data so that less frequently used data can be moved to slower, less expensive disks. This also permits the frequently accessed data to be stored on faster disks for quicker retrieval.

Tiered storage is the assignment of different types of data to different storage types to improve performance and reduce costs. With SmartTier, storage classes are used to designate which disks make up a particular tier. There are two common ways of defining storage classes:

Note: SmartTier is the expanded and renamed feature previously known as Dynamic Storage Tiering (DST).

- Performance, or storage, cost class: The most-used class consists of fast, expensive disks. When data is no longer needed on a regular basis, the data can be moved to a different class that is made up of slower, less expensive disks.
- Resilience class: Each class consists of non-mirrored volumes, mirrored volumes, and n-way mirrored volumes.
 - For example, a database is usually made up of data, an index, and logs. The data could be set up with a three-way mirror because data is critical. The index could be set up with a two-way mirror because the index is important, but can be recreated. The redo and archive logs are not required on a daily basis but are vital to database recovery and should also be mirrored.

SmartTier policies control initial file location and the circumstances under which existing files are relocated. These policies cause the files to which they apply to be created and extended on specific subsets of a file systems's volume set, known as placement classes. The files are relocated to volumes in other placement classes when they meet specified naming, timing, access rate, and storage capacity-related conditions.

In addition to preset policies, you can manually move files to faster or slower storage with SmartTier, when necessary. You can also run reports that list active policies, display file activity, display volume usage, or show file statistics.

To use SmartTier, your storage must be managed using the following features:

- VxFS multi-volume file system
- VxVM volume set
- Volume tags
- SmartTier management at the file level
- SmartTier management at the sub-file level

SmartTier building blocks

To use SmartTier, your storage must be managed using the following features:

- VxFS multi-volume file system
- VxVM volume set
- Volume tags
- SmartTier management at the file level
- SmartTier management at the sub-file level

About VxFS multi-volume file systems

Multi-volume file systems are file systems that occupy two or more virtual volumes. The collection of volumes is known as a volume set, and is made up of disks or disk array LUNs belonging to a single Veritas Volume Manager (VxVM) disk group. A multi-volume file system presents a single name space, making the existence of multiple volumes transparent to users and applications. Each volume retains a separate identity for administrative purposes, making it possible to control the locations to which individual files are directed.

This feature is available only on file systems meeting the following requirements:

- The minimum disk group version is 140.
- The minimum file system layout version is 7 for file level SmartTier.
- The minimum file system layout version is 8 for sub-file level SmartTier.

To convert your existing VxFS system to a VxFS multi-volume file system, you must convert a single volume to a volume set.

The VxFS volume administration utility (fsvoladm utility) can be used to administer VxFS volumes. The fsvoladm utility performs administrative tasks, such as adding, removing, resizing, encapsulating volumes, and setting, clearing, or querying flags on volumes in a specified Veritas File System.

See the fsvoladm (1M) manual page for additional information about using this utility.

About VxVM volume sets

Volume sets allow several volumes to be represented by a single logical object. Volume sets cannot be empty. All I/O from and to the underlying volumes is directed via the I/O interfaces of the volume set. The volume set feature supports the multi-volume enhancement to Veritas File System (VxFS). This feature allows file systems to make best use of the different performance and availability characteristics of the underlying volumes. For example, file system metadata could be stored on volumes with higher redundancy, and user data on volumes with better performance.

About volume tags

You make a VxVM volume part of a placement class by associating a volume tag with it. For file placement purposes, VxFS treats all of the volumes in a placement class as equivalent, and balances space allocation across them. A volume may have more than one tag associated with it. If a volume has multiple tags, the volume belongs to multiple placement classes and is subject to allocation and relocation policies that relate to any of the placement classes.

Warning: Multiple tagging should be used carefully.

A placement class is a SmartTier attribute of a given volume in a volume set of a multi-volume file system. This attribute is a character string, and is known as a volume tag.

SmartTier use cases for DB2 or Sybase

Storage Foundation High Availability Solutions include SmartTier, a storage tiering feature which enables you to tier your data to achieve optimal use of your storage.

Example procedures illustrate the following use cases:

- Relocating archive logs older than 2 days to Tier-2 storage
- Relocating inactive tablespaces or segments to Tier-2 storage
- Relocating active indexes to Tier-0 storage
- Relocating all indexes to Tier-0 storage

Setting up a filesystem for storage tiering with **SmartTier**

In the use case examples, the following circumstances apply:

- The database containers are in the file system /DBdata
- The database archived logs are in the file system /DBarch

To create required filesystems for SmartTier

1 List the disks:

vxdisk list

DEVICE	TYPE	DISK	GROUP	STATUS
fas30700_0	auto:cdsdisk	fas30700_0		online thin
fas30700_1	auto:cdsdisk	fas30700_1		online thin
fas30700_2	auto:cdsdisk	fas30700_2		online thin
fas30700_3	auto:cdsdisk	fas30700_3		online thin
fas30700_4	auto:cdsdisk	fas30700 <u>4</u>		online thin
fas30700_5	auto:cdsdisk	fas30700_5		online thin
fas30700_6	auto:cdsdisk	fas30700_6		online thin
fas30700_7	auto:cdsdisk	fas30700_7		online thin
fas30700_8	auto:cdsdisk	fas30700_8		online thin

Assume there are 3 LUNs on each tier.

2 Create the disk group.

```
# Vxdg init DBdg fas30700 0 fas30700 1 fas30700 2 \
fas30700 3 fas30700 4 fas30700 5 fas30700 6 fas30700 7 \
fas30700 8
```

3 Create the volumes *datavol* and *archvol*.

```
# vxassist -g DBdg make datavol 200G alloc=fas30700 3,\
fas30700 4,fas30700 5
# vxassist -q DBdq make archvol 50G alloc= fas30700 3,\
fas30700_4,fas30700_5
```

Tag datavol and archvol as tier-1.

```
# vxassist -g DBdg settag datavol vxfs.placement_class.tier1
# vxassist -g DBdg settag archvol vxfs.placement class.tier1
```

4 Create the Tier-0 volumes.

```
# vxassist -g DBdg make tier0 vol1 50G alloc= fas30700 0,\
fas30700_1,fas30700_2
# vxassist -g DBdg make tier0 vol2 50G alloc= fas30700 0,\
fas30700 1,fas30700 2
# vxassist -g DBdg settag tier0 vol1 vxfs.placement class.tier0
# vxassist -g DBdg settag tier0_vol2 vxfs.placement_class.tier0
```

5 Create the Tier-2 volumes.

```
# vxassist -g DBdg make tier2 vol1 50G alloc= fas30700 6,\
fas30700 7,fas30700 8
# vxassist -g DBdg make tier2 vol2 50G alloc= fas30700 6,\
fas30700 7,fas30700 8
# vxassist -g DBdg settag tier2 vol1 vxfs.placement class.tier2
# vxassist -g DBdg settag tier2 vol2 vxfs.placement class.tier2
```

6 Convert *datavol* and *archvol* to a volume set.

```
# vxvset -g DBdg make datavol mvfs datavol
# vxvset -g DBdg make archvol mvfs archvol
```

Add the volumes *Tier-0* and *Tier-2* to *datavol mvfs*.

```
# vxvset -g DBdg addvol datavol_mvfs tier0_vol1
# vxvset -g DBdg addvol datavol mvfs tier2 vol1
```

8 Add the volume *Tier-2* to *archvol mvfs*

```
# vxvset -g DBdg archvol_mvfs tier2_vol2
```

Make the file system and mount *datavol mvfs* and *archvol mvfs*.

```
# mkfs -t vxfs /dev/vx/rdsk/DBdg/datavol mvfs
```

10 Mount the *DBdata* file system

```
# mount -t vxfs /dev/vx/rdsk/DBdg/datavol mvfs /DBdata
```

11 Mount the *DBarch filesystem*

```
# mount -t vxfs /dev/vx/rdsk/DBdg/datavol mvfs /DBarch
```

12 Migrate the database into the newly created, SmartTier-ready file system. You can migrate the database either by restoring from backup or copying appropriate files into respective filesystems.

See the database documentation for more information.

Relocating old archive logs to tier two storage using **SmartTier**

A busy database can generate few hundred gigabytes of archivelogs per day. Restoring these archive logs from tape backup is not ideal because it increases database recovery time. Regulatory requirements could mandate that these archive logs be preserved for several weeks.

To save storage costs, you can relocate archive logs older than two days (for example) into tier two storage. To achieve this you must create a policy file, for example, archive policy.xml.

Note: The relocaing archive logs use case applies for both DB2 and Sybase environments.

To relocate archive logs that are more than two days old to Tier-2

Create a policy file. A sample XML policy file is provided below.

```
<?xml version="1.0"?>
<!DOCTYPE PLACEMENT POLICY SYSTEM "/opt/VRTSvxfs/etc\</pre>
   /placement policy.dtd">
<PLACEMENT_POLICY Version="5.0" Name="access_age_based">
    <RULE Flags="data" Name="Key-Files-Rule">
         <COMMENT>
            This rule deals with key files such as archive logs.
         </COMMENT>
    <SELECT Flags="Data">
         <COMMENT>
             You want all files. So choose pattern as '*'
         </COMMENT>
         <PATTERN> * </PATTERN>
     </SELECT>
    <CREATE>
        <0N>
            <DESTINATION>
                <CLASS> tier1 </CLASS>
            </DESTINATION>
        </ON>
    </CREATE>
    <RELOCATE>
    <TO>
          <DESTINATION>
              <CLASS> tier2 </CLASS>
          </DESTINATION>
    </TO>
          <WHEN>
                  <ACCAGE Units="days">
                      <MIN Flags="gt">2</MIN>
                  </ACCAGE>
          </WHEN>
    </RELOCATE>
    </RULE>
</PLACEMENT POLICY>
```

Notice the ACCAGE units in the WHEN clause.

To locate additional sample policy files, go to /opt/VRTSvxfs/etc.

The access age-based policy is appropriate for this use case. Pay attention to the CREATE ON and RELOCATE TO sections of the XML file.

To apply a policy file

- As root, validate archive policy.xml
 - # fsppadm validate /DBarch archive_policy.xml
- If the validation process is not successful, correct the problem. Validate archive policy.xml successfully before proceeding.
- Assign the policy to /DBarch filesystem
 - # fsppadm assign /DBarch archive policy.xml
- Enforce the policy. The relocation of two day old archive logs happens when the enforcement step is performed. The policy enforcements must be done every day to relocate aged archive logs. This enforcement can be performed on demand as needed or by using a cron-like scheduler.
 - # fsppadm enforce /DBarch

Relocating inactive tablespaces or segments to tier two storage

It is general practice to use partitions in databases. Each partition maps to a unique tablespace. For example in a shopping goods database, the orders table can be portioned into orders of each quarter. Q1 orders can be organized into Q1 order tbs tablespace or Q1 order tbs segment, Q2 order can be organized into Q2 order tbs.

As the quarters go by, the activity on older quarter data decreases. By relocating old quarter data into Tier-2, significant storage costs can be saved. The relocation of data can be done when the database is online.

For the following example use case, the steps illustrate how to relocate Q1 order data into Tier-2 in the beginning of Q3. The example steps assume that all the database data is in /DBdata filesystem.

To prepare to relocate Q1 order data into Tier-2 storage for DB2

- Obtain a list of containers belonging to *Q1_order_tbs*.
 - \$ db2inst1\$ db2 list tablespaces
- 2 Find the tablespace-id for the tablespace *Q1 order tbs*.
 - \$ db2inst1\$ db2 list tablespace containers for <tablespace-id>
- **3** Find the path names for the containers and store them in file Q1 order files.txt.

```
#cat Q1 order_files.txt
         NODE0000/Q1 order file1.f
         NODE0000/Q1 order file2.f
         NODE0000/Q1 order fileN.f
```

To prepare to relocate Q1 order data into Tier-2 storage for Sybase

Obtain a list of datafiles belonging to segment Q1 order tbs. System Procedures sp helpsegment and *sp_helpdevice* can be used for this purpose.

```
sybsadmin$ sp helpsegment Q1 order tbss
```

Note: In Sybase terminology, a "tablespace" is same as a "segment."

- 2 Note down the device names for the segment *Q1 order tbs*.
- 3 For each device name use the sp helpdevice system procedure to get the physical path name of the datafile.

```
sybsadmin$ sp helpdevice <device name>
```

Save all the datafile path names in *Q1* order files.txt

```
# cat Q1 order files.txt
         NODE0000/Q1 order file1.f
         NODE0000/Q1 order file2.f
         NODE0000/Q1 order fileN.f
```

To relocate Q1 order data into Tier-2

Prepare a policy XML file. For the example, the policy file name is Q1 order policy.xml. Below is a sample policy.

This is policy is for unconditional relocation and hence there is no when clause. There are multiple Pattern statements as part of the select clause. Each PATTERN selects a different file.

```
<?xml version="1.0"?>
<!DOCTYPE PLACEMENT POLICY SYSTEM "/opt/VRTSvxfs/etc/\</pre>
placement policy.dtd">
<PLACEMENT POLICY Version="5.0" Name="selected files">
    <RULE Flags="data" Name="Key-Files-Rule">
        <COMMENT>
            This rule deals with key important files.
        </COMMENT>
        <SELECT Flags="Data">
           <DIRECTORY Flags="nonrecursive" > NODE0000/DIRECTORY>
            <PATTERN> Q1 order file1.f </pattern>
           <PATTERN> Q1 order file2.f </pattern>
            <PATTERN> Q1 order fileN.f </pattern>
        </SELECT>
        <RELOCATE>
             <COMMENT>
                Note that there is no WHEN clause.
             </COMMENT>
                <DESTINATION>
                   <CLASS> tier2 </CLASS>
                </TO>
         </RELOCATE>
    </RULE>
</PLACEMENT POLICY>
```

- Validate the policy Q1 order policy.xml.
 - # fsppadm validate /DBdata Q1 order policy.xml

- Assign the policy.
 - # fsppadm assign /DBdata Q1 order policy.xml
- Enforce the policy.
 - # fsppadm enforce /DBdata

Relocating active indexes to premium storage

Database transaction rate depends upon how fast indexes can be accessed. If Indexes reside on slow storage, the database transaction rate suffers. Tier-0 storage is generally too expensive to be practical to relocate the entire table data to Tier-0. Indexes are generally much smaller in size and are created to improve the database transaction rate, hence it is more practical to relocate active indexes to Tier-0 storage. Using SmartTier you can move active indexes to Tier-0 storage.

For the following telephone company database example procedure, assume the call details table has an index call idx on the column customer id.

To prepare to relocate call_idx to Tier-0 storage for DB2

Find the tablespace where *call idx* resides.

```
$ db2inst1$ db2 connect to PROD
$ db2inst1$ db2 select index tbspace from syscat.tables \
where tabname='call details'
```

2 In this example, the index is in tablespace *tbs_call_idx*. To get the tablespace id for tbs call idx and the list of containers:

```
$ db2inst1$ db2 list tablespaces
```

Note the tablespace id for the call idx.

List the containers and record the filenames in the tabelspace *tbs call idx*.

```
$ db2inst1$ db2 list tablespace containers for <tablespace-id>
```

Store the files in *index files.txt*.

```
# cat index files.txt
/DB2data/NODE0000/IDX/call1.idx
/DB2data/NODE0000/IDX/call2.idx
/DB2data/NODE0000/IDX/call3.idx
```

To prepare to relocate call_idx to premium storage for Sybase

1 Obtain a list of datafiles for the *call_idx* segment.

```
$ sybsadmin$ sp helpsegment call idx
```

- Note down the device names for the segment *call_idx*. 2
- 3 For each device name use the sp helpdevice system procedure to get the physical pathname of the datafile.

```
sybsadmin$ sp helpdevice <device name>
```

4 Save all the datafile path names in *index_files.txt*.

```
# cat index files.txt
```

```
/DB2data/NODE0000/IDX/call1.idx
/DB2data/NODE0000/IDX/call2.idx
/DB2data/NODE0000/IDX/call3.idx
```

To relocate call_idx to Tier-0 storage

Prepare the policy *index_policy.xml*.

Example policy:

```
<?xml version="1.0"?>
<!DOCTYPE PLACEMENT POLICY SYSTEM "/opt/VRTSvxfs/etc/\</pre>
placement policy.dtd">
<PLACEMENT POLICY Version="5.0" Name="selected files">
    <RULE Flags="data" Name="Key-Files-Rule">
        <COMMENT>
            This rule deals with key important files.
        </COMMENT>
        <SELECT Flags="Data">
            <DIRECTORY Flags="nonrecursive" > NODE0000/DIRECTORY>
            <PATTERN> call*.idx </pattern>
        </select>
        <RELOCATE>
            <COMMENT>
                Note that there is no WHEN clause.
         </COMMENT>
         <TO>
            <DESTINATION>
                <CLASS> tier0 </CLASS>
            </DESTINATION>
         </TO>
         </RELOCATE>
    </RULE>
</PLACEMENT POLICY>
```

Assign and enforce the policy.

```
# fsppadm validate /DBdata index_policy.xml
# fsppadm assign /DBdata index_policy.xml
# fsppadm enforce /DBdata
```

Relocating all indexes to premium storage

It is a common practice for DBAs to name index files with some common extensions. For example, all index files are named with ".inx" extensions. If your Tier-0 storage has enough capacity, you can relocate all indexes of the database to Tier-0 storage. You can also make sure all index containers created with this special extension are automatically created on Tier-0 storage by using the ${\tt CREATE}$ and RELOCATE clause of policy definition.

To relocate all indexes to Tier-0 storage

Create a policy such as the following example:

```
# cat index policy.xml
```

```
<?xml version="1.0"?>
<!DOCTYPE PLACEMENT POLICY SYSTEM "/opt/VRTSvxfs/etc/\</pre>
placement policy.dtd">
<PLACEMENT POLICY Version="5.0" Name="selected files">
    <RULE Flags="data" Name="Key-Files-Rule">
        <COMMENT>
            This rule deals with key important files.
        </comment>
        <SELECT Flags="Data">
            <PATTERN> *.inx </PATTERN>
        </SELECT>
        <CREATE>
            <COMMENT>
               Note that there are two DESTINATION.
            </COMMENT>
            <NO>
               <DESTINATION>
                   <CLASS> tier0 </CLASS>
               </DESTINATION>
               <DESTINATION>
                   <CLASS> tier1</CLASS>
               </ON>
        </CREATE>
             <RELOCATE>
                 <COMMENT>
                    Note that there is no WHEN clause.
                 </COMMENT>
                 <TO>
                    <DESTINATION>
                        <CLASS> tier0 </CLASS>
                    </TO>
            </RELOCATE>
    </RULE>
</PLACEMENT POLICY>
```

- 2 To make sure file creation succeeds even if Tier-0 runs out of space, add two ON clauses as in the example policy in 1.
- Assign and enforce the policy.
 - # fsppadm validate /DBdata index policy.xml
 - # fsppadm assign /DBdata index_policy.xml
 - # fsppadm enforce /DBdata

Section

Migrating data

- Chapter 11. Understanding data migration
- Chapter 12. Offline migration from LVM to VxVM
- Chapter 13. Migrating storage arrays
- Chapter 14. Migrating data between platforms

Understanding data migration

This chapter includes the following topics:

■ Types of data migration

Types of data migration

This section describes the following types of data migration:

- Migrating data from LVM to Storage Foundation using offline migration When you install Storage Foundation, you may already have some volumes that are controlled by the Logical Volume Manager. You can preserve your data and convert these volumes to Veritas Volume Manager volumes. See "About migration from LVM" on page 153.
- Migrating data between platforms using Cross-platform Data Sharing (CDS) Storage Foundation lets you create disks and volumes so that the data can be read by systems running different operating systems. CDS disks and volumes cannot be mounted and accessed from different operating systems at the same time. The CDS functionality provides an easy way to migrated data between one system and another system running a different operating system.

 See "Overview of the Cross-Platform Data Sharing (CDS) feature" on page 185.
- Migrating data between arrays

 Storage Foundation supports arrays from various vendors. If your storage needs change, you can move your data between arrays.

 See "Array migration for storage using Linux" on page 173.

Note: The procedures are different if you plan to migrate to a thin array from a thick array.

Offline migration from LVM to VxVM

This chapter includes the following topics:

- About migration from LVM
- Converting unused LVM physical volumes to VxVM disks
- LVM volume group to VxVM disk group conversion
- LVM volume group restoration

About migration from LVM

Veritas Volume Manager (VxVM) provides the vxvmconvert utility for converting Logical Volume Manager (LVM) volume groups and the objects that they contain to the equivalent VxVM disk groups and objects. Conversion of LVM2 volume groups is supported provided that the version of LVM2 is 2.00.33 or later.

Disks on your system that are managed by LVM can be of two types:

- Unused disks or disk partitions, which contain no user data, and are not used by any volume group, but which have LVM disk headers written by pvcreate.

 See "Converting unused LVM physical volumes to VxVM disks" on page 154.
- LVM disks or disk partitions in volume groups, and which contain logical volumes and volume groups.
- See "LVM volume group to VxVM disk group conversion" on page 155.

A converted VxVM disk group can also be reverted to an LVM volume group.

See "LVM volume group restoration" on page 171.

See the vxvmconvert(1M) manual page.

Converting unused LVM physical volumes to VxVM disks

LVM disks or disk partitions that are not part of any volume group, and which contain no user data, can be converted by removing the LVM disk headers.

Warning: Make sure that the disks to be converted are not in use in any LVM configuration. Any user data on these disks is destroyed during conversion.

To convert unused LVM physical volumes to VxVM disks

Use the pyscan command to make sure that the disk is not part of any volume group as shown in this example:

pvscan

```
pvscan -- reading all physical volumes (this may take a while...)
pvscan -- inactive PV "/dev/sde1" is in no VG [8.48 GB]
pvscan -- ACTIVE PV "/dev/sdf" of VG "vg02" [8.47 GB / 8.47 GB free]
pvscan -- inactive PV "/dev/sdg" is in no VG [8.48 GB]
pvscan -- ACTIVE PV "/dev/sdh1" of VG "vg02" [8.47 GB / 8.47 GB free]
pvscan -- total: 4 [33.92 GB] / in use: 2 [16.96 GB] / in no
VG: 2 [16.96 GB]
```

This shows that the disk devices sdf and sdh1 are associated with volume group, vg02, but sde1 and sdg are not in any volume group.

Use the following commands to remove LVM header information from each

```
# dd if=/dev/zero of=/dev/diskdev bs=1k count=3
# blockdev --rereadpt /dev/diskdev
```

Warning: When running dd on a disk partition, make sure that you specify the device for the disk partition rather than the disk name. Otherwise, you will overwrite information for other partitions on the disk.

After overwriting the LVM header, use the fdisk or sfdisk command to edit the partition table on the disk:

fdisk -l /dev/diskdev

If the LVM disk was created on an entire disk, relabel it as a DOS or SUN partition.

If the LVM disk was created on a disk partition, change the partition type from "Linux LVM" to "Linux".

After writing the partition table to the disk, a disk or disk partition (where there is no other useful partition on the disk) may be initialized as a VM disk by running the vxdiskadm command and selecting item 1 Add or initialize one or more disks, or by using the VEA GUI. For a disk partition that coexists with other partitions on a disk, initialize the partition as a simple disk.

LVM volume group to VxVM disk group conversion

Read these guidelines carefully before beginning any volume group conversion. The conversion process involves many steps. Although the tools provided help you with the conversion, some of the steps cannot be automated. Make sure that you understand how the conversion process works and what you need to do before trying to convert a volume group. Make sure that you have taken backups of the data on the volumes.

The conversion utility, vxvmconvert, is an interactive, menu-driven program that walks you through most of the steps for converting LVM volume groups. LVM volume groups are converted to VxVM disk groups in place. The public areas of the disks that contain user data, (file systems, databases, and so on) are not affected by the conversion. However, the conversion process overwrites the LVM configuration areas on the disks, and changes the names of the logical storage objects. For this reason, conversion is necessarily an off-line procedure. All applications must be shut down that would normally access the volume groups that are undergoing conversion.

During the conversion, the wxvmconvert utility tries to create space for the VxVM private region by using on-disk data migration. If a disk has enough available free space, no intervention is required. If there is insufficient space on the disk, the vxvmconvert utility displays a list of suitable disks in the same volume group to which the data can be migrated. After selecting a disk, the data is migrated to create space for the VxVM private region.

Volume group conversion limitations

Some LVM volume configurations cannot be converted to VxVM. The following are some reasons why a conversion might fail:

- Existing VxVM disks use enclosure-based naming (EBN). The vxvmconvert utility requires that the disks use operating system-based naming (OSN). If the system to be converted uses enclosure-based naming, change the disk naming scheme to OSN before conversion. After the conversion, you can change the naming scheme back to EBN.
 - For more information about disk device naming in VxVM, see the *Veritas* Storage Foundation Administrator's Guide.
- The volume group has insufficient space for its configuration data. During conversion, the areas of the disks that used to store LVM configuration data are overwritten with VxVM configuration data. If the VxVM configuration data that needs to be written cannot fit into the space occupied by LVM configuration data, the volume group cannot be converted unless additional disks are specified.
- A volume group contains a root volume. The vxvmconvert utility does not currently support conversion to VxVM root volumes. The root disk can be converted to a VxVM volume if it is not an LVM volume.
- There is insufficient space on the root disk to save information about each physical disk. For large volume groups (for example, 200GB or more total storage on twenty or more 10GB drives), the required space may be as much as 30MB.
- An attempt is made to convert a volume which contains space-optimized snapshots. Such snapshots cannot be converted. Remove the snapshot and restart the conversion. After conversion, use the features available in VxVM to create new snapshots.
- Unsupported devices (for example, Linux metadevices or RAM disks) are in use as physical volumes.
- To create a VxVM private region, the vxvmconvert utility can use the LVM2 pymove utility to move physical extents across a disk. This requires that the dm mirror device mapper is loaded into the kernel. If extent movement is required for an LVM volume, you are instructed to use the vgconvert utility to convert the volume group to an LVM2 volume group.
- The volume group contains a volume which has an unrecognized partitioning scheme. Adding a disk device to VxVM control requires that VxVM recognize the disk partitioning scheme. If the Sun partitions are overwritten with LVM metadata, so that the disk has no VxVM recognized partition table, the conversion will fail.

■ The volume group contains more than one physical extent on a specific disk device.

You can use the analyze option in vxvmconvert to help you in identifying which volume groups can be converted.

See "Examples of second stage failure analysis" on page 169.

Converting LVM volume groups to VxVM disk groups

To convert LVM volume groups to VxVM disk groups

Identify the LVM disks and volume groups that are to be converted. Use LVM administrative utilities such as vgdisplay to identify the candidate LVM volume groups and the disks that comprise them. You can also use the listvg operation in vxvmconvert to examine groups and their member disks, and the list operation to display the disks known to the system as shown here:

```
# vxvmconvert
Select an operation to perform: list
Enter disk device or "all" [<address>,all,q,?] (default: all) all
DEVICE
            DISK
                       GROUP
                                  STATUS
cciss/c0d0
                                  online invalid
cciss/c0d1
                                  online
sda
                                  online
sdb
           disk01
                      rootda
                                 online
sdc
           disk02
                      rootdg
                                  online
sdd
           disk03
                      rootdg
                                  online
sde
                                   error
sdf
                                  error
sda
                                  error
sdh
                                   error
Device to list in detail [<address>, none, q,?] (default: none)
```

The DEVICE column shows the disk access names of the physical disks. If a disk has a disk media name entry in the DISK column, it is under VM control, and the GROUP column indicates its membership of a disk group. The STATUS column shows the availability of the disk to VxVM. LVM disks are displayed in the error state as they are unusable by VxVM.

To list LVM volume group information, use the listvg operation:

```
Select an operation to perform: listvg
Enter Volume Group (i.e.- vg04) or "all"
[<address>,all,q,?] (default: all) all
```

```
LVM VOLUME GROUP INFORMATION
Name Type Physical Volumes
vg02
            Non-Root /dev/sdf /dev/sdh1
Volume Group to list in detail
[<address>, none, q,?] (default: none) vg02
--- Volume group ---
VG Name
                            vg02
VG Access
                            read/write
VG Status
                            available/resizable
VG #
MAX LV
                            256
Cur LV
Open LV
MAX LV Size
                            255.99 GB
Max PV
                            256
Cur PV
                            2.
Act PV
VG Size
                            16.95 GB
PE Size
                            4 MB
Total PE
                            4338
Alloc PE / Size
                            0 / 0
Free PE / Size
                            4338 / 16.95 GB
VG UUID
                            IxlERp-poi2-GO2D-od2b-G7fd-3zjX-PYycMn
--- No logical volumes defined in "vg02" ---
--- Physical volumes ---
PV Name (#)
                           /dev/sdf (2)
PV Status
                           available / allocatable
Total PE / Free
                           PE 2169 / 2169
PV Name (#)
                            /dev/sdh1 (1)
PV Status
                            available / allocatable
Total PE / Free PE
                            2169 / 2169
List another LVM Volume Group? [y,n,q,?] (default: n)
```

Plan for the new VxVM logical volume names. Conversion changes the device names by which your system accesses data in the volumes. LVM creates device nodes for its logical volumes in /dev under directories named for the volume group. VxVM create device nodes in /dev/vx/dsk/diskgroup and

/dev/vx/rdsk/diskgroup. After conversion is complete, the LVM device nodes no longer exist on the system.

For file systems listed in /etc/fstab, vxvmconvert substitutes the new VxVM device names for the old LVM volume names, to prevent problems with fsck, mount, and other such utilities. However, other applications that refer to specific device node names may fail if the device no longer exists in the same place.

Examine the following types of application to see if they reference LVM device names, and are at risk:

- Databases that access raw logical devices.
- Backups that are performed on device nodes named in private files. Labeling of backups may also record device names.
- Scripts run by cron.
- Other administrative scripts.

Select item 1 Analyze LVM Volume Groups for Conversion from the vxvmconvert main menu to see if conversion of each LVM volume group is possible.

This step is optional. Analysis can be run on a live system while users are accessing their data. This is useful when you have a large number of groups and disks for conversion to allow for the optimal planning and management of conversion downtime.

The following is sample output from the successful analysis of a volume group:

```
Select an operation to perform: 1
Select Volume Groups to analyze:
[<pattern-list>,all,list,listvq,q,?] vq02
vg02
Analyze this Volume Group? [y,n,q,?] (default: y) \boldsymbol{y}
Conversion Analysis of the following devices was successful.
/dev/sdf /dev/sdh1
Hit RETURN to continue.
Second Stage Conversion Analysis of vg02
Volume Group vg02 has been analyzed and prepared for conversion.
Volume Group Analysis Completed
Hit RETURN to continue.
```

If off-disk data migration is required because there is insufficient space for on-disk data migration, you are prompted to select additional disks that can be used.

The analysis may fail for one of a number of reasons.

See "Volume group conversion limitations" on page 156.

The messages output by vxvmconvert explain the type of failure, and detail actions that you can take before retrying the analysis.

See "Examples of second stage failure analysis" on page 169.

Back up your LVM configuration and user data before attempting the conversion to VxVM. Similarly, you should back up the LVM configuration itself.

Warning: During a conversion, any spurious reboots, power outages, hardware errors, or operating system bugs can have unpredictable consequences. You are advised to safeguard your data with a set of verified backups.

Before running vxvmconvert, you can use the vqcfqbackup utility to save a copy of the configuration of an LVM volume group, as shown here:

vgcfgbackup volume group name

This creates a backup file, /etc/lvmconf/volume group name.conf. Save this file to another location (such as off-line on tape or some other medium) to prevent the conversion process from overwriting it. If necessary, the LVM configuration can be restored from the backup file.

The vxvmconvert utility also saves a snapshot of the LVM configuration data during conversion of each disk. This data is saved in a different format from that of vgcfgbackup, and it can only be used with the vxvmconvert program. With certain limitations, you can use the data to reinstate the LVM volumes after they have been converted to VxVM. Even though vxvmconvert provides this mechanism for backing up the LVM configuration, you are advised to use vgcfgbackup to save the LVM configuration information for each LVM volume group.

Before performing a backup of the user data, note that backup procedures may have dependencies on the volume names that are currently in use on your system. Conversion to VxVM changes the volume names. You need to understand the implications that such name changes have for restoring from any backups that you make.

Prevent access by applications to volumes in the volume groups to be converted. This may require you to stop databases, unmount file systems, and so on.

vxvmconvert attempts to unmount mounted file systems before starting conversion. However, it makes no attempt to stop applications that are using those file systems, nor does it attempt to deal with applications such as databases that are running on raw LVM volumes.

The LVM logical volumes to be converted must all be available to the vxvmconvert process. Do not deactivate the volume group or any logical volumes before running vxvmconvert.

You can use the following command to activate a volume group:

vgchange -a y volume_group name

6 Start the conversion of each volume group by selecting item 2 Convert LVM Volume Groups to VxVM from the vxvmconvert main menu. The volume group is analyzed to ensure that conversion is possible. If the analysis is successful, you are asked whether you wish to perform the conversion.

Convert one volume group at a time to avoid errors during conversion.

The following is sample output from a successful conversion:

```
Select an operation to perform: 2
Select Volume Groups to convert:
[<pattern-list>,all,list,listvq,q,? vq02
vg02
Convert this Volume Group? [y,n,q,?] (default: y) y
Conversion Analysis of the following devices was successful.
/dev/sdf /dev/sdh1
Hit RETURN to continue.
Second Stage Conversion Analysis of vg02
Volume Group vg02 has been analyzed and prepared for conversion.
Are you ready to commit to these changes?[y,n,q,?](default: y) y
vxlvmconv: making log directory /etc/vx/lvmconv/vg02.d/log.
vxlvmconv: starting conversion for VG "vg02" -
Thu Feb 26 09:08:57 IST 2004
vgchange -- volume group "vg02" successfully deactivated
vxlvmconv: checking disk connectivity
Starting Conversion of vg02 to VxVM
fdisk ..
disksetup ..
dginit ..
make .
```

```
volinit ..
vxlvmconv: Conversion complete.
Convert other LVM Volume Groups? [y,n,q,?] (default: n)
```

If off-disk data migration is required because there is insufficient space for on-disk data migration, you are prompted to select additional disks that can be used.

After converting the LVM volume groups, you can use the list operation in vxvmconvert to examine the status of the converted disks, as shown in this example:

```
Select an operation to perform: list
Enter disk device or "all"[<address>,all,q,?](default: all) all
DEVICE
       DISK
                                    STATUS
                        GROUP
cciss/c0d0
                                    online invalid
cciss/c0d1
                                    online
                                    online
sda
sdb
           disk01
                      rootdg
                                    online
sdc
           disk02
                        rootdg
                                    online
sdd
           disk03
                        rootdg
                                    online
sde1
           vg0101
                        vq01
                                    online
           vg0201
sdf
                        vq02
                                    online
```

Device to list in detail [<address>, none, q,?] (default: none)

vq01

vq02

online

online

The LVM disks that were previously shown in the error state are now displayed as online to VxVM.

You can also use the vxprint command to display the details of the objects in the converted volumes (the TUTILO and PUTILO columns are omitted for clarity):

```
# vxprint
```

sdq sdh1

Disk group: rootdg

vg0102

vq0202

TY	NAME	ASSOC	KSTATE	LENGTH	PLOFFS	STATE
dg	rootdg	rootdg	-	-	-	-
dm	disk01	sdb	_	17778528	-	-
dm	disk02	sdc	_	17778528	-	-
dm	disk03	sdd	_	17778528	-	-

Disk group: vg01

TY NAME	ASSOC	KSTATE	LENGTH	PLOFFS	STATE				
dg vg01	vg01	-	-	-	-				
dm vg0101	sde1	-	17774975	-	-				
dm vg0102	sdg	-	17772544	-	-				
v stripevol	gen	ENABLED	1638400	-	ACTIVE				
pl stripevol-0	lstripevol	ENABLED	1638400	-	ACTIVE				
sd vg0102-01	stripevol-01	ENABLED	819200	0	-				
sd vg0101-01	stripevol-01	ENABLED	819200	0	-				
Disk group: vg02									
TY NAME	ASSOC	KSTATE	LENGTH	PLOFFS	STATE				
dg vg02	vg02	-	-	-	-				
dm vg0201	sdf	-	17772544	-	-				
dm vg0202	sdh1	-	17774975	-	-				
v concatvol	gen	ENABLED	163840	-	ACTIVE				
pl concatvol-0	lconcatvol	ENABLED	163840	-	ACTIVE				
sd vg0202-02	concatvol-01	ENABLED	163840	0	-				
v stripevol	gen	ENABLED	81920	-	ACTIVE				
pl stripevol-0	lstripevol	ENABLED	81920	-	ACTIVE				
pl stripevol-03 sd vg0202-01	-		81920 40960	0	ACTIVE				

Implement the changes to applications and configuration files that are required for the new VxVM volume names. (You prepared the information $\,$ for this step in step 2.)

- File systems can now be mounted on the new devices, and applications can be restarted. If you unmounted any file systems before running vxvmconvert, remount them using their new volume names. The vxvmconvert utility automatically remounts any file systems that were left mounted.
- 10 The disks in each new VxVM disk group are given VM disk media names that are based on the disk group name. For example, if a disk group is named mydg, its disks are assigned names such as mydq01, mydq02, and so on. Plexes within each VxVM volume are named mydg01-01, mydg01-02, and so on. If required, you can rename disks and plexes.

Only rename VxVM objects in the converted disk groups when you are fully satisfied with the configuration. Renaming VxVM objects prevents you from using vxvmconvert to restore the original LVM volume groups.

Examples of second stage failure analysis

Second stage failure analysis examines the existing LVM volume groups, and reports where manual intervention is required to correct a problem because the existing volume groups do not meet the conversion criteria.

See "Volume group conversion limitations" on page 156.

Snapshot in the volume group

The following sample output is from an analysis that has failed because of the presence of a snapshot in the volume group:

Snapshot conversion is not supported in this version. Please remove this volume and restart the conversion process if you want to continue.

The solution is to remove the snapshot volume from the volume group.

dm mirror module not loaded in the kernel

The following sample output is from an analysis that has failed because the dm mirror module (required by the LVM2 pymove utility) is not loaded in the kernel:

Conversion requires some extent movement which cannot be done without the dm mirror target in the kernel. Please consider installing the dm mirror target in kernel and retry the conversion.

The solution is to ensure that the dm mirror module is loaded in the kernel.

Conversion requires extent movement on an LVM1 volume group

The following sample output is from an analysis that has failed because the LVM2 pymove utility cannot be used to move extents on an LVM1 volume group:

Conversion requires some extent movement which cannot be done on a LVM1 volume group. Please consider converting the volume group to LVM2 and retry the conversion analysis again.

The solution is to use the LVM2 vgconvert command to convert the LVM1 volume group to an LVM2 volume group, before retrying the conversion.

Unrecognized partition in volume group

The following sample output is from an analysis that has failed because of the presence of a snapshot in the volume group:

LVM VG(<VG name>) uses unrecognised partitioning, and cannot be converted. Please remove the VG from the list of conversion candidates and retry the conversion operation.

The solution is to use the fdisk utility to create a new empty DOS partition table on the device. For example:

fdisk /dev/sdf

The following is the typical output from the fdisk utility:

Device contains neither a valid DOS partition table, nor Sun, SGI or OSF disklabel

Building a new DOS disklabel. Changes will remain in memory only, until you decide to write them. After that, of course, the previous content won't be recoverable.

The number of cylinders for this disk is set to 17769. There is nothing wrong with that, but this is larger than 1024, and could in certain setups cause problems with:

- 1) software that runs at boot time (e.g., old versions of LILO)
- 2) booting and partitioning software from other OSs

(e.g., DOS FDISK, OS/2 FDISK)

Warning: invalid flag 0x0000 of partition table 4 will be corrected

```
by w(rite)
Command (m for help): w
The partition table has been altered!
Calling ioctl() to re-read partition table.
Syncing disks.
```

LVM volume group restoration

In some circumstances, you may want to restore an LVM volume group from a VxVM disk group, for example:

- An error occurred during conversion, such as a system crash or a disk failure, that caused the conversion to be corrupted.
- Conversion was only partially successful for a set of LVM volume groups.

The ability to restore the original LVM configuration using vxvmconvert depends on whether any changes have been made to the VxVM configuration since the original conversion was performed. Any of the following actions changes the VxVM configuration, and makes restoration by vxvmconvert impossible:

- Adding or removing disks to a converted disk group.
- Adding or removing converted disk groups.
- Changing the names of VxVM objects in a converted disk group.
- Resizing of volumes.

Complete restoration from backups of the LVM configuration and user data is required if the VxVM configuration has changed.

If a conversion is interrupted, you can complete it by running the command /etc/vx/bin/vxlvmconv, provided that you have not made any changes to the system that would make conversion impossible.

Restoring an LVM volume group

Provided that the configuration of the converted disk groups has not been changed, you can use the vxvmconvert command to convert the disk groups back to the original LVM volume groups. The information that was recorded during conversion about the LVM configuration and other configuration files such as /etc/fstab and LVM device files is used to restore the LVM volume groups. User data is not changed.

If the configuration has changed, an error is displayed. You must then use full restoration from backups instead.

Warning: A record of the LVM configuration information is stored in the root file system. However, this should not be taken as assurance that a full restoration from backups will not be needed.

To restore an LVM volume group

Select item 3 Roll back from VxVM to LVM from the main menu of the vxvmconvert command, as shown in this example:

```
Select an operation to perform: 3
Select Volume Group(s) to rollback : [all,list,q,?] list
mddev
vg01
vg02
Select Volume Group(s) to rollback : [all,list,q,?] vq02
Rolling back LVM configuration records for Volume Group vg02
Starting Rollback for VG "vg02"
Selected Volume Groups have been restored.
Hit any key to continue
```

Migrating storage arrays

This chapter includes the following topics:

- Array migration for storage using Linux
- Overview of storage mirroring for migration
- Allocating new storage
- Initializing the new disk
- Checking the current VxVM information
- Adding a new disk to the disk group
- Mirroring
- **■** Monitoring
- Mirror completion
- Removing old storage
- Post-mirroring steps

Array migration for storage using Linux

The array migration example documented for this use case uses a Linux system. The example details would be different for AIX, Solaris, or Windows systems.

Veritas Storage Foundation and High Availability Solutions (SFHA Solutions) products provide enterprise-class software tools which enable companies to achieve data management goals which would otherwise require more expensive hardware or time-consuming consultative solutions.

For many organizations, both large and small, storage arrays tend to serve as useful storage repositories for periods of 3-6 years. Companies are constantly

evaluating new storage solutions in their efforts to drive down costs, improve performance and increase capacity. The flexibility of Storage Foundation and High Availability Solutions enable efficient migration to new storage and improve the overall availability of data.

While there are several methods for accomplishing the migration, the most basic and traditional method is using a volume level mirror. The example procedures:

- Provide system administrators responsible for SFHA Solutions systems within their organization a demonstration of the steps required for performing an online storage array migration from one array to another.
- Illustrate the migration process using a Linux system which is connected to two different storage arrays through a SAN.
- Provide steps for starting with a file system with a single volume, mirroring the volume to a volume to another array, and then detaching the original storage.
- Are performed from the command prompt.
- Use Operating System Based Naming (OSN) for disk devices (sdb, sdc, etc).

There are two user interface options:

- The SFHA Solutions command line interface (CLI).
- The Veritas Operations Manager (VOM) graphical user interface (GUI) has a storage migration wizard.
 - See the Veritas Operations Manager documentation for details: https://sortsymanteccom/public/documents/vom/40ru1/windowsandunix/productguides/pdf/vom.sp.addon.userspdf

Note: Symantec's NetBackup PureDisk comes bundled with the Veritas Storage Foundation and High Availability Solutions software for the purpose of enhanced storage management and high availability. Storage arrays used with PureDisk can also be migrated using the SFHA Solutions methodologies.

Overview of storage mirroring for migration

The migration example occurs between a Hitachi 9900 array, 350 GB disk/LUN and a NetApps 3050 Fibre-Attached 199GB disk/LUN.

To migrate storage using storage mirroring

- Connect the new array to the SAN.
- Zone the array controller ports(s) to the server HBA port(s).
- Create or present the new LUN(s) on the array.

- Map the new LUN(s) to the server HBA port(s).
- 5 Stop any processes that are running on this volume or file system.
- 6 Rescan hardware using rescan-scsi-bus.sh and scsidev commands, or reboot (optional).
- Confirm that the operating system has access to the new target storage (Array-B).
- Bring new disks under Veritas Volume Manager (VxVM) control.
- 9 Start the VxVM mirroring process to synchronize the plexes between the source and target array enclosures.
- **10** Monitor the mirroring process.
- **11** After mirroring is complete, logically remove disks from VxVM control.

Note: The example Linux system happens to be running as a Symantec NetBackup Puredisk server which includes the Storage Foundation software. Puredisk also supports this mode of storage array migration.

12 Disconnect the old storage array (enclosure).

Allocating new storage

The first step to migrating array storage is to allocate new storage to the server.

To allocate new storage as in the example

- 1 Create the LUN(s) on the new array.
- 2 Map the new LUN(s) to the server.
- Zone the new LUN(s) to the server.
- Reboot or rescan using a native OS tool such as "fdisk" and the new external disk is now visible.

In the example, the original disk (/dev/sdb) has already been initialized by Veritas Volume Manager (VxVM). Note that it has a partition layout already established. Note also the different disk sizes. It may turn out that you want to use smaller or larger LUNs. This is fine, but if you are going to mirror to a smaller LUN you will need to shrink the original volume so that it can fit onto the physical disk device or LUNs.

To shrink the original volume

- ◆ You can shrink the new volume size to *n* gigabytes:
 - # vxassist -g diskgroup_name shrinkto volume_name ng

Then resize the file system:

/opt/VRTS/bin/fsadm -t vxfs -b new_size_in_sectors /Storage

Alternately, use the ${\tt vxresize}$ command to resize both the volume and the file system.

To grow the original volume

- You can increase the new volume size to *n* gigabytes:
 - # vxassist -g diskgroup name growto volume name ng

Then resize the file system:

/opt/VRTS/bin/fsadm -t vxfs -b new size in sectors /Storage

Alternately, use the ${\tt vxresize}$ command to resize both the volume and the file system.

Note: SmartMove enables you to migrate from thick array LUNs to thin array LUNs on those enclosures that support Thin Provisioning.

Initializing the new disk

Now that the operating system recognizes the new disk, the next step is to initialize it.

To initialize the disk as in the example

Use the vxdisksetup command to establish the appropriate VxVM-friendly partition layout for Veritas Volume Manager.

Note below that the internal name *OLDDISK* is assigned to the old disk. The new disk is assigned a unique name later for the sake of clarity.

```
GROUP
DEVICE
                              DISK
                                                         STATUS
                                                         online invalid
ıda
             auto:none
                              OLDDISK
ıdb
             auto:sliced
                                                         online
de
                                                         online invalid
oot@ny-puredisk:
coot@ny-puredisk
oot@ny-puredisk:/usr/lib/vxvm/bin/vxdisksetup_sdc
coot@ny-puredisk:vxdisk list
        TYPE
auto:none
auto:sliced
                                            GROUP
                                                         STATUS
od a
                                                         online invalid
                             OLDDISK
                                           PDDG
                                                         online
db
                                                         online invalid
            auto:none
oot@ny-puredisk:
```

The disk is now initialized under VxVM control. Note below, that the disk has a new partition table similar to the existing disk (sdb)and is ready to be joined to the Veritas disk group *PDDG* (name of the example disk group).

```
oot@ny-puredisk:fdisk -1 /dev/sdc
Disk /dev/sdc: 213.6 GB, 213676323840 bytes
255 heads, 63 sectors/track, 25978 cylinders
Units - cylinders of 16065 * 512 - 8225280 bytes
                                                         208652188+ 5 Extended
1165+ 7f Unknown
208650865+ 7e Unknown
dev/sdc6
 oot@ny-puredisk:
```

Checking the current VxVM information

Check the VxVM information after initializing the new disk. The screen shot below illustrates all the disks on the server along with their corresponding partition tables. Note that disks *sdb* and *sdc* are partitioned in the same manner since they were both set up with the vxdisksetup command.

```
ot@ny-puredisk:fdisk -1
isk /dev/sda: 80.0 GB, 80026361856 bytes
55 heads, 63 sectors/track, 9729 cylinders
hits - cylinders of 16065 * 512 - 8225280 bytes
  Device Boot
                                                        Blocks
                                                     104391 83 Linux
12586927+ 82 Linux swap / Solaris
65456842+ 83 Linux
                                          13
1580
dev/sdal
Disk /dev/sdb: 375.8 GB, 375813308416 bytes
255 heads, 63 sectors/track, 45690 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
                      Start End

1 45683 36

1 1

1 45683 36
                                                       Blocks
  Device Boot
                                                                    Id System
                                                          48666 5 Extended
1165+ 7f Unknown
dev/sdb4
                                                    366948666
dev/sdb5
Disk /dev/sdc: 213.6 GB, 213676323840 bytes
255 heads, 63 sectors/track, 25978 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
                        Start
                                           End
                                                       Blocks
                                                                    Id System
                                                                    5 Extended
dev/sdc4
                                                                     0 Empty
  ot@ny-puredisk:
```

The screen shot below shows the VxVM hierarchy for existing storage objects. Remember that we are working with a live and running server. We are using a logical disk group called PDDG which has other storage objects subordinate to it. The most important storage object here is the volume which is called *Storage*. The volume name can be any arbitrary name that you want, but for this example, the volume name is "Storage". The volume object is denoted by "v" in the output of the vxprint command. Other objects are subdisks (sd) which represents a single contiguous range of blocks on a single LUN. The other object here is a plex ("pl") which represents the virtual object or container to which the OS reads and writes. In vxprint, the length values are expressed in sectors, which in Linux are 512 bytes each. The raw volume size is 377487360 sectors in length, or when multiplied by 512 bytes (512*377487360) is 193273528320 bytes, or about 193 GB(2).

Notice that when the new disk was added it was 213GB yet the original existing Storage volume was 250GB. The Storage volume had to first be shrunk to a size equal the same (or smaller) number of sectors as the disk to which it would be mirrored.

ry na Purii		ASSOC	KSTATE	LENGTH	PLOFFS	STATE	TUTIL0	
dg PC		PDDG	-	-	-	-	-	-
am OI	DDISK	sdb	-	733894672	-	-	-	_
am so	ic	adc	-	417301712	-	-	-	-
, St	orage	fsgen	ENABLED	377487360	-	ACTIVE	-	_
ol St	corage-02	Storage	ENABLED	377487360	-	ACTIVE	-	-
		Storage-02	ENABLED	377487360	0	_	-	-

To shrink a volume as in the example Storage volume

Use the vxresize command:

```
# vxresize -f -t my-shrinktask -g PDDG Storage 193g
```

The original physical disk ("dm") that has been grouped into the *PDDG* diskgroup is called *sdb* but we have assigned the internal name *OLDDISK* for the purpose of this example. This can be done with the vxedit command using the rename operand. We also see the new disk (sdc) under VxVM control. It has been initialized but not yet assigned to any disk group.



Adding a new disk to the disk group

The next step is adding the new disk into the PDDG disk group and assigning the name of NEWDISK to the disk.

To add a new disk to the example disk group

- Initialize the disk.
- Add the disk into the *PDDG* disk group


```
root@ny-puredisk:vxdisk init sdc
root@ny-puredisk:vxdg -g PDDG adddisk sdo
root@ny-puredisk:vxprint
v Storage fsgen ENABLED 377487360 - ACTIVE -
pl Storage-02 Storage ENABLED 377487360 - ACTIVE -
sd OLDDISK-01 Storage-02 ENABLED 377487360 0 - -
```

The internal VxVM name of the new disk is changed from the default disk to NEWDISK.

TY N	AME	ASSOC	KSTATE	LENGTH	PLOFFS	STATE	TUTILO	PUT
ig P	PDDG	PDDG	-	-	-	-	-	-
in O	LDDISK	adb	-	73389467	12 -	-	-	_
in M	REMDISK	sdc	-	41730171	12 -	-	-	-
v 8	Storage	fsgen	ENABLED	37748736	50 -	ACTIVE	-	_
ol s	Storage-02	Storage	ENABLED	37748736	50 -	ACTIVE	-	-
pl s	Storage-02 OLDDISK-01	Storage Storage-02			50 -			

Mirroring

The next step is to start the mirroring process. We used the vxassist command to transform the Storage volume from a simple, concatenated volume into a mirrored volume. Optionally, a DRL (Dirty Region Log) can be added to the volume. If enabled, the DRL speeds recovery of mirrored volumes after a system crash. It requires an additional 1 Megabyte of extra disk space.



To add a DRL as in the example Storage volume

Use:

vxassist -g PDDG addlog Storage logtype=drl

For more information about DRL logging,:

See the Veritas Storage Foundation Administrator's Guide


Monitoring

The mirroring process must complete before you can proceed. During this time there may be a heavy I/O load on the system as the mirroring process reads from one disk and writes to another.

To monitor the mirroring progress

Use the vxtask list command.

Raw I/O statistics can also be monitored with the vxstat command. Mirroring should be done either during times of low demand on the server, or, optionally, to have the services stopped completely. While the initial synchronization is underway, the STATE of the new plex is still TEMPRMSD.



To pause and resume mirroring

Use the vxtask command.

To throttle the mirroring process and free up I/O if needed

Use the vxtask command.


```
oot@ny-puredisk:vxtask list
TASKID PTID TYPE/STATE
                               PROGRESS
                ATCOPY/R 00.12% 0/377487360/449792 PLXATT Storage Storage-01 PDDG
```

The TEMPRMSD plex state is used by wassist when attaching new data plexes to a volume. If the synchronization operation does not complete, the plex and its subdisks are removed.

See http://www.symantec.com/docs/TECH19044

Mirror completion

When the mirroring completes, you can see that the output from vxprint shows the volume now has two active plexes associated with it. This is the mirrored volume comprised of two plexes, each plex residing on separate physical storage arrays.



To confirm completion of the mirror task

Use the vxtask command.

Removing old storage

After the mirroring process completes, you can remove the old storage.

To remove the old storage

- Break the mirror.
- 2 Logically detach the old disk (*OLDDISK*, *sdb*).
- 3 Check the viability of the volume. Services do not need to be stopped during this phase.
- Remove the old storage from the diskgroup.

coot@ny-pr	uredisk:vxdisk lis	st		
DEVICE	TYPE	DISK	GROUP	STATUS
sda	auto:none	-	-	online invalid
sdb	auto:sliced		-	online
sdo	auto:sliced	NEWDISK	PDDG	online

)is	ik group: PDI	og.						
Y	NAME	ASSOC	KSTATE	LENGTH	PLOFFS	STATE	TUTIL0	PUTILO
ig	PDDG	PDDG	-	-	-	-	-	-
in.	NEWDISK	adc	-	417301712	2 -	-	-	-
'n	OLDDISK	adb	-	733894672	2 -	-	-	-
,	Storage	fagen	ENABLED	377487360	-	ACTIVE	-	-
1	Storage-01	Storage	ENABLED	377487360) -	ACTIVE	-	-
d	NEMDISK-01	Storage-01	ENABLED	377487360	0 0	-	-	-

The use of the backslash is necessary to override the significance of "!" to the bash Shell which is the default shell for root user. Without the "\", the bash (or C Shell) command line interpreter would look for some history of command event.

Post-mirroring steps

The last step is to check on application services by running whatever utilities you have to ensure the applicatio is up. At some point, a reboot should be done at this point to ensure that the system properly starts and can access the disks during a reboot. No additional modifications need to be made to the file system mount table (etc/fstab, for example) since all storage, disk group, and volume object names remain unchanged.

Migrating data between platforms

This chapter includes the following topics:

- Overview of the Cross-Platform Data Sharing (CDS) feature
- CDS disk format and disk groups
- Setting up your system to use Cross-platform Data Sharing (CDS)
- Maintaining your system
- **■** File system considerations
- Alignment value and block size
- Migrating a snapshot volume

Overview of the Cross-Platform Data Sharing (CDS) feature

This section presents an overview of the Cross-Platform Data Sharing (CDS) feature of Symantec's Veritas Storage Foundation™ software. CDS provides you with a foundation for moving data between different systems within a heterogeneous environment. The machines may be running HP-UX, AIX, Linux or the Solaris™ operating system (OS), and they may all have direct access to physical devices holding data. CDS allows Symantec's Veritas products and applications to access data storage independently of the operating system platform, enabling them to work transparently in heterogeneous environments.

The Cross-Platform Data Sharing feature is also known as Portable Data Containers (PDC). For consistency, this document uses the name Cross-Platform Data Sharing throughout.

The following levels in the device hierarchy, from disk through file system, must provide support for CDS to be used:

End-user applications Application level.

Veritas™ File System (VxFS) File system level.

Veritas[™] Volume Manager (VxVM) Volume level.

Device level. Operating system

CDS is a license-enabled feature that is supported at the disk group level by VxVM and at the file system level by VxFS.

CDS utilizes a new disk type (auto:cdsdisk). To effect data sharing, VxVM supports a new disk group attribute (cds) and also supports different OS block sizes.

Note: CDS allows data volumes and their contents to be easily migrated between heterogeneous systems. It does not enable concurrent access from different types of platform unless such access is supported at all levels that are required.

Shared data across platforms

While volumes can be exported across platforms, the data on the volumes can be shared only if data sharing is supported at the application level. That is, to make data sharing across platforms possible, it must be supported throughout the entire software stack.

For example, if a VxFS file system on a VxVM volume contains files comprising a database, then the following functionality applies:

- Disks can be recognized (as cds disks) across platforms.
- Disk groups can be imported across platforms.
- The file system can be mounted on different platforms.

However, it is very likely that, because of the inherent characteristics of databases, you may not be able to start up and use the database on a platform different from the one on which it was created.

An example is where an executable file, compiled on one platform, can be accessed across platforms (using CDS), but may not be executable on a different platform. Note: You do not need a file system in the stack if the operating system provides access to raw disks and volumes, and the application can utilize them. Databases and other applications can have their data components built on top of raw volumes without having a file system to store their data files.

Disk drive sector size

Sector size is an attribute of a disk drive (or SCSI LUN for an array-type device), which is set when the drive is formatted. Sectors are the smallest addressable unit of storage on the drive, and are the units in which the device performs I/O. The sector size is significant because it defines the atomic I/O size at the device level. Any multi-sector writes which VxVM submits to the device driver are not guaranteed to be atomic (by the SCSI subsystem) in the case of system failure.

Block size issues

The block size is a platform-dependent value that is greater than or equal to the sector size. Each platform accesses the disk on block boundaries and in quantities that are multiples of the block size.

Data that is created on one platform, and then accessed by a platform of a different block size, can suffer from the following problems:

- Addressing issues

 The data may not have been created on a block boundary compatible with that used by the accessing platform.
 - The accessing platform cannot address the start of the data.

Bleed-over issues

The size of the data written may not be an exact multiple of the block size used by the accessing platform. Therefore the accessing platform cannot constrain its I/O within the boundaries of the data on disk.

Operating system data

Some operating systems (OS) require OS-specific data on disks in order to recognize and control access to the disk.

CDS disk format and disk groups

This section provides additional information about CDS disk format and CDS disk groups.

CDS disk access and format

For a disk to be accessible by multiple platforms, the disk must be consistently recognized by the platforms, and all platforms must be capable of performing I/O on the disk. CDS disks contain specific content at specific locations to identify or control access to the disk on different platforms. The same content and location are used on all CDS disks, independent of the platform on which the disks are initialized.

In order for a disk to be initialized as, or converted to a CDS disk, it must satisfy the following requirements:

- Must be a SCSI disk
- Must be the entire physical disk (LUN)
- Only one volume manager (such as VxVM) can manage a physical disk (LUN)
- There can be no disk partition (slice) which is defined, but which is not configured on the disk
- Cannot contain a volume whose use-type is either root or swap (for example, it cannot be a boot disk)

The CDS conversion utility, vxcdsconvert, is provided to convert non-CDS VM disk formats to CDS disks, and disk groups with a version number less than 110 to disk groups that support CDS disks.

See "Converting non-CDS disks to CDS disks" on page 197.

CDS disk types

The CDS disk format, cdsdisk, is recognized by all VxVM platforms. The cdsdisk disk format is the default for all newly-created VM disks unless overridden in a defaults file. The vxcdsconvert utility is provided to convert other disk formats and types to CDS.

See "Defaults files" on page 200.

Note: Disks with format cdsdisk can only be added to disk groups with version 110 or later.

Private and public regions

A VxVM disk usually has a private and a public region.

The private region is a small area on the disk where VxVM configuration information is stored, such as a disk header label, configuration records for VxVM objects (such as volumes, plexes and subdisks), and an intent log for the

configuration database. The default private region size is 32MB, which is large enough to record the details of several thousand VxVM objects in a disk group.

The public region covers the remainder of the disk, and is used for the allocation of storage space to subdisks.

The private and public regions are aligned and sized in multiples of 8K to permit the operation of CDS. The alignment of VxVM objects within the public region is controlled by the disk group alignment attribute. The value of the disk group alignment attribute must also be 8K to permit the operation of CDS.

Note: With other (non-CDS) VxVM disk formats, the private and public regions are aligned to the platform-specific OS block size.

Disk access type auto

The disk access (DA) type auto supports multiple disk formats, including cdsdisk, which is supported across all platforms. It is associated with the DA records created by the VxVM auto-configuration mode. Disk type auto automatically determines which format is on the disk.

Platform block

The platform block resides on disk sector 0, and contains data specific to the operating system for the platforms. It is necessary for proper interaction with each of those platforms. The platform block allows a disk to perform as if it was initialized by each of the specific platforms.

AIX coexistence label

The AIX coexistence label resides on the disk, and identifies the disk to the AIX logical volume manager (LVM) as being controlled by VxVM.

HP-UX coexistence label

The HP-UX coexistence label resides on the disk, and identifies the disk to the HP logical volume manager (LVM) as being controlled by VxVM.

VxVM ID block

The VxVM ID block resides on the disk, and indicates the disk is under VxVM control. It provides dynamic VxVM private region location and other information.

About Cross-platform Data Sharing (CDS) disk groups

A Cross-platform Data Sharing (CDS) disk group allows cross-platform data sharing of Veritas Volume Manager (VxVM) objects, so that data written on one of the

supported platforms may be accessed on any other supported platform. A CDS disk group is composed only of CDS disks (VxVM disks with the disk format cdsdisk), and is only available for disk group version 110 and greater.

Starting with disk group version 160, CDS disk groups can support disks of greater than 1 TB.

Note: The CDS conversion utility, vxcdsconvert, is provided to convert non-CDS VxVM disk formats to CDS disks, and disk groups with a version number less than 110 to disk groups that support CDS disks.

See "Converting non-CDS disks to CDS disks" on page 197.

All VxVM objects in a CDS disk group are aligned and sized so that any system can access the object using its own representation of an I/O block. The CDS disk group uses a platform-independent alignment value to support system block sizes of up to 8K.

See "Disk group alignment" on page 191.

CDS disk groups can be used in the following ways:

- Initialized on one system and then used "as-is" by VxVM on a system employing a different type of platform.
- Imported (in a serial fashion) by Linux, Solaris, AIX, and HP-UX systems.
- Imported as private disk groups, or shared disk groups (by CVM).

You cannot include the following disks or volumes in a CDS disk group:

- Volumes of usage type root and swap. You cannot use CDS to share boot devices.
- Encapsulated disks.

Note: On Solaris and Linux systems, the process of disk encapsulation places the slices or partitions on a disk (which may contain data or file systems) under VxVM control. On AIX and HP-UX systems, LVM volumes may similarly be converted to VxVM volumes.

Device quotas

Device quotas limit the number of objects in the disk group which create associated device nodes in the file system. Device quotas are useful for disk groups which to be transferred between Linux with a pre-2.6 kernel and other supported platforms. Prior to the 2.6 kernel, Linux supported only 256 minor devices per major device.

You can limit the number of devices that can be created in a given CDS disk group by setting the device quota.

See "Setting the maximum number of devices for CDS disk groups" on page 208.

When you create a device, an error is returned if the number of devices would exceed the device quota. You then either need to increase the quota, or remove some objects using device numbers, before the device can be created.

See "Displaying the maximum number of devices in a CDS disk group" on page 212.

Minor device numbers

Importing a disk group will fail if it will exceed the maximum devices for that platform.

Note: There is a large disparity between the maximum number of devices allowed for devices on the Linux platform with a pre-2.6 kernel, and that for other supported platforms.

Non-CDS disk groups

Any version 110 (or greater) disk group (DG) can contain both CDS and non-CDS disks. However, only version 110 (or greater) disk groups composed entirely of CDS disks have the ability to be shared across platforms. Whether or not that ability has been enabled is a controlled by the cds attribute of the disk group. Enabling this attribute causes a non-CDS disk group to become a CDS disk group.

Although a non-CDS disk group can contain a mixture of CDS and non-CDS disks having dissimilar private region alignment characteristics, its disk group alignment will still direct how all subdisks are created.

Disk group alignment

One of the attributes of the disk group is the block alignment, which represents the largest block size supported by the disk group.

The alignment constrains the following attributes of the objects within a disk group:

- Subdisk offset
- Subdisk length
- Plex offset
- Volume length
- Log length
- Stripe width

The offset value specifies how an object is positioned on a drive.

The disk group alignment is assigned at disk group creation time.

See "Disk group tasks" on page 205.

Alignment values

The disk group block alignment has two values: 1 block or 8k (8 kilobytes).

All CDS disk groups must have an alignment value of 8k.

All disk group versions before version 110 have an alignment value of 1 block, and they retain this value if they are upgraded to version 110 or later.

A disk group that is not a CDS disk group, and which has a version of 110 and later, can have an alignment value of either 1 block or 8k.

The alignment for all newly initialized disk groups in VxVM 4.0 and later releases is 8k. This value, which is used when creating the disk group, cannot be changed. However, the disk group alignment can be subsequently changed.

See "Changing the alignment of a non-CDS disk group" on page 206.

Note: The default usage of vxassist is to set the layout=diskalign attribute on all platforms. The layout attribute is ignored on 8K-aligned disk groups, which means that scripts relying on the default may fail.

Dirty region log alignment

The location and size of each map within a dirty region log (DRL) must not violate the disk group alignment for the disk group (containing the volume to which the DRL is associated). This means that the region size and alignment of each DRL map must be a multiple of the disk group alignment, which for CDS disk groups is 8K. (Features utilizing the region size can impose additional minimums and size increments over and above this restriction, but cannot violate it.)

In a version 110 disk group, a traditional DRL volume has the following region requirements:

- Minimum region size of 512K
- Incremental region size of 64K

In a version 110 disk group, an instant snap DCO volume has the following region requirements:

- Minimum region size of 16K
- Incremental region size of 8K

Object alignment during volume creation

For CDS disk groups, VxVM objects that are used in volume creation are automatically aligned to 8K. For non-CDS disk groups, the vxassist attribute, dgalign checking, controls how the command handles attributes that are subject to disk group alignment restrictions. If set to strict, the volume length and values of attributes must be integer multiples of the disk group alignment value, or the command fails and an error message is displayed. If set to round (default), attribute values are rounded up as required. If this attribute is not specified on the command-line or in a defaults file, the default value of round is used.

The diskalign and nodiskalign attributes of vxassist, which control whether subdisks are aligned on cylinder boundaries, is honored only for non-CDS disk groups whose alignment value is set to 1.

Setting up your system to use Cross-platform Data **Sharing (CDS)**

In order to migrate data between platforms using Cross-platform Data Sharing (CDS), set up your system to use CDS disks and CDS disk groups. The CDS license must be enabled. You can use the default files to configure the appropriate settings for CDS disks and disk groups.

Table 14-1 describes the tasks for setting up your system to use CDS.

Table 14-1 Setting up CDS disks and CDS disk groups

Task	Procedures
Create the CDS disks.	You can create a CDS disk in one of the following ways: ■ Creating CDS disks from uninitialized disks See "Creating CDS disks from uninitialized disks" on page 194. ■ Creating CDS disks from initialized VxVM disks See "Creating CDS disks from initialized VxVM disks" on page 195. ■ Converting non-CDS disks to CDS disks
	See "Converting non-CDS disks to CDS disks" on page 197.

Task	Procedures		
Create the CDS disk groups.	You can create a CDS disk group in one of the following ways:		
	 Creating CDS disk groups See "Creating CDS disk groups" on page 196. Converting a non-CDS disk group to a CDS disk group See "Converting a non-CDS disk group to a CDS disk group" on page 198. 		
Verify the CDS license.	Verifying licensingSee "Verifying licensing" on page 200.		
Verify the system defaults related to CDS.	Defaults files See "Defaults files" on page 200.		

Setting up CDS disks and CDS disk groups (continued) Table 14-1

Creating CDS disks from uninitialized disks

You can create a CDS disk from an uninitialized disk by using one of the following methods:

- Creating CDS disks by using vxdisksetup
- Creating CDS disks by using vxdiskadm

Creating CDS disks by using vxdisksetup

To create a CDS disk by using the vxdisksetup command

■ Type the following command:

vxdisksetup -i disk [format=disk format]

The format defaults to cdsdisk unless this is overridden by the /etc/default/vxdisk file, or by specifying the disk format as an argument to the format attribute.

See "Defaults files" on page 200.

See the vxdisksetup(1M) manual page.

Creating CDS disks by using vxdiskadm

To create a CDS disk by using the vxdiskadm command

■ Run the vxdiskadm command, and select the "Add or initialize one or more disks" item from the main menu. You are prompted to specify the format.

Warning: On CDS disks, the CDS information occupies the first sector of that disk, and there is no fdisk partition information. Attempting to create an fdisk partition (for example, by using the fdisk or format commands) erases the CDS information, and can cause data corruption.

Creating CDS disks from initialized VxVM disks

How you create a CDS disk depends on the current state of the disk, as follows:

- Creating a CDS disk from a disk that is not in a disk group
- Creating a CDS disk from a disk that is already in a disk group

Creating a CDS disk from a disk that is not in a disk group

To create a CDS disk from a disk that is not in a disk group

- Run the following command to remove the VM disk format for the disk:
 - # vxdiskunsetup disk

This is necessary as non-auto types cannot be reinitialized by vxdisksetup.

- If the disk is listed in the /etc/vx/darecs file, remove its disk access (DA) record using the command:
 - # vxdisk rm disk

(Disk access records that cannot be configured by scanning the disks are stored in an ordinary file, /etc/vx/darecs, in the root file system. Refer to the vxintro(1M) manual page for more information.)

- Rescan for the disk using this command:
 - # vxdisk scandisks
- Type this command to set up the disk:
 - # vxdisksetup -i disk

Creating a CDS disk from a disk that is already in a disk group

To create a CDS disk from a disk that is already in a disk group

■ Run the vxcdsconvert command. See "Converting non-CDS disks to CDS disks" on page 197.

Creating CDS disk groups

You can create a CDS disk group in the following ways:

- Creating a CDS disk group by using vxdg init
- Creating a CDS disk group by using vxdiskadm

Creating a CDS disk group by using vxdg init

Note: The disk group version must be 110 or greater.

To create a CDS disk group by using the vxdq init command

■ Type the following command:

```
# vxdg init diskgroup disklist [cds={on|off}]
```

The format defaults to a CDS disk group, unless this is overridden by the /etc/default/vxdg file, or by specifying the cds argument.

See the vxdq(1M) manual page for more information.

Creating a CDS disk group by using vxdiskadm

You cannot create a CDS disk group when encapsulating an existing disk, or when converting an LVM volume.

When initializing a disk, if the target disk group is an existing CDS disk group, vxdiskadm will only allow the disk to be initialized as a CDS disk. If the target disk group is a non-CDS disk group, the disk can be initialized as either a CDS disk or a non-CDS disk.

If you use the vxdiskadm command to initialize a disk into an existing CDS disk group, the disk must have be added with the cdsdisk format.

The CDS attribute for the disk group remains unchanged by this procedure.

To create a CDS disk group by using the vxdiskadm command

■ Run the vxdiskadm command, and select the "Add or initialize one or more disks" item from the main menu. Specify that the disk group should be a CDS disk group when prompted.

Converting non-CDS disks to CDS disks

Note: The disks must be of type of auto in order to be re-initialized as CDS disks.

To convert non-CDS disks to CDS disks

- If the conversion is not going to performed on-line (that is, while access to the disk group continues), stop any applications that are accessing the disks.
- Make sure that the disks have free space of at least 256 sectors before doing the conversion.
- Add a disk to the disk group for use by the conversion process. The conversion process evacuates objects from the disks, reinitializes the disks, and relocates objects back to the disks.

Note: If the disk does not have sufficient free space, the conversion process will not be able to relocate objects back to the disk. In this case, you may need to add additional disks to the disk group.

Type one of the following forms of the CDS conversion utility (vxcdsconvert) to convert non-CDS disks to CDS disks.

```
# vxcdsconvert -g diskgroup [-A] [-d defaults_file] \
  [-o novolstop] disk name [attribute=value] ...
# vxcdsconvert -g diskgroup [-A] [-d defaults file] \
  [-o novolstop] alldisks [attribute=value] ...
```

The alldisks and disk keywords have the following effect

alldisks Converts all non-CDS disks in the disk group into CDS disks. disk

Specifies a single disk for conversion. You would use this option under the following circumstances:

- If a disk in the non-CDS disk group has cross-platform exposure, you may want other VxVM nodes to recognize the disk, but not to assume that it is available for initialization.
- If the native Logical Volume Manager (LVM) that is provided by the operating system needs to recognize CDS disks, but it is not required to initialize or manage these disks.
- Your intention is to move the disk into an existing CDS disk group.

Specify the -o novolstop option to perform the conversion on-line (that is, while access to the disk continues). If the -o novolstop option is not specified, stop any applications that are accessing the disks, and perform the conversion off-line.

Warning: Specifying the -o novolstop option can greatly increase the amount of time that is required to perform conversion.

Before you use the vxcdsconvert command, make sure you understand its options, attributes, and keywords.

See the vxcdsconvert(1M) manual page.

Converting a non-CDS disk group to a CDS disk group

To convert a non-CDS disk group to a CDS disk group

- If the disk group contains one or more disks that you do not want to convert to CDS disks, use the vxdq move or vxdq split command to move the disks out of the disk group.
- The disk group to be converted must have the following characteristics:
 - No dissociated or disabled objects.
 - No sparse plexes.
 - No volumes requiring recovery.
 - No volumes with pending snapshot operations.
 - No objects in an error state.

To verify whether a non-CDS disk group can be converted to a CDS disk group, type the following command:

vxcdsconvert -g diskgroup -A group

- If the disk group does not have a CDS-compatible disk group alignment, the objects in the disk group must be relayed out with a CDS-compatible alignment.
- If the conversion is not going to performed on-line (that is, while access to the disk group continues), stop any applications that are accessing the disks.
- Type one of the following forms of the CDS conversion utility (vxcdsconvert) to convert a non-CDS disk group to a CDS disk group.

```
# vxcdsconvert -g diskgroup [-A] [-d defaults file] \
  [-o novolstop] alignment [attribute=value] ...
# vxcdsconvert -g diskgroup [-A] [-d defaults file] \
  [-o novolstop] group [attribute=value] ...
```

The alignment and group keywords have the following effect:

alignment	Specifies alignment conversion where disks are not converted,
	and an object relayout is performed on the disk group. A
	successful completion results in an 8K-aligned disk group. You
	might consider this option, rather than converting the entire
	disk group, if you want to reduce the amount of work to be done
	for a later full conversion to CDS disk group.
group	Specifies group conversion of all non-CDS disks in the disk group
	before realying out objects in the disk group.

The conversion involves evacuating objects from the disk, reinitializing the disk, and relocating objects back to disk. You can specify the -o novolstop option to perform the conversion on-line (that is, while access to the disk group continues). If the -o novolstop option is not specified, stop any applications that are accessing the disks, and perform the conversion off-line.

Warning: Specifying the -o novolstop option can greatly increase the amount of time that is required to perform conversion.

Conversion has the following side effects:

■ Non-CDS disk group are upgraded by using the vxdq_upgrade command. If the disk group was originally created by the conversion of an LVM volume group (VG), rolling back to the original LVM VG is not possible. If you decide to go through with the conversion, the rollback records for the

disk group will be removed, so that an accidental rollback to an LVM VG cannot be done.

- Stopped, but startable volumes, are started for the duration of the conversion.
- Any volumes or other objects in the disk group that were created with the layout=diskalign attribute specified can no longer be disk aligned.
- Encapsulated disks may lose the ability to be unencapsulated.
- Performance may be degraded because data may have migrated to different regions of a disk, or to different disks.

In the following example, the disk group, mydg, and all its disks are converted to CDS while keeping its volumes are still online:

```
# vxcdsconvert -g mydg -o novolstop group \
 move subdisks ok=yes evac subdisks ok=yes \
 evac disk list=disk11,disk12,disk13,disk14
```

The evac disk list attrinute specifies a list of disks (disk11 through disk14) to which subdisks can be evacuated to disks if required.

Before you use the vxcdsconvert command, make sure you understand its options, attributes, and keywords.

See the vxcdsconvert(1M) manual page.

Verifying licensing

The ability to create or import a CDS disk group is controlled by a CDS license. CDS licenses are included as part of the Veritas Storage Foundation license.

To verify the CDS enabling license

■ Type the following command:

```
# vxlicrep
```

Verify the following line in the output:

```
Cross-platform Data Sharing = Enabled
```

Defaults files

The following system defaults files in the /etc/default directory are used to specify the alignment of VxVM objects, the initialization or encapsulation of VM disks, the conversion of LVM disks, and the conversion of disk groups and their disks to the CDS-compatible format

vxassist

Specifies default values for the following parameters to the vxcdsconvert command that have an effect on the alignment of VxVM objects: dgalign checking, diskalign, and nodiskalign.

See "Object alignment during volume creation" on page 193.

See the vxassist(1M) manual page.

vxcdsconvert

Specifies default values for the following parameters to the vxcdsconvertcommand:evac disk list, evac subdisks ok, min split size, move subdisks ok, privlen, and split subdisks ok.

The following is a sample vxcdsconvert defaults file:

evac subdisks ok=no min split size=64k move subdisks_ok=yes privlen=2048 split subdisks ok=move

An alternate defaults file can be specified by using the -d option with the vxcdsconvert command.

See the vxcdsconvert(1M) manual page.

vxdq

Specifies default values for the cds, default activation mode and enable activation parameters to the vxdg command. The default activation mode and enable activation parameters are only used with shared disk groups in a cluster.

The following is a sample vxdg defaults file:

cds=on

See the vxdg(1M) manual page.

vxdisk

Specifies default values for the format and privlen parameters to the vxdisk and vxdisksetup commands. These commands are used when disks are initialized by VxVM for the first time. They are also called implicitly by the vxdiskadm command and the Veritas Operations Manager (VOM) GUI.

The following is a sample vxdisk defaults file:

format=cdsdisk privlen=2048

See the vxdisk(1M) manual page.

See the vxdisksetup(1M) manual page.

vxencap

Specifies default values for the format, privlen, privoffset and puboffset parameters to the vxencap and vxlvmencap commands. These commands are used when disks with existing partitions or slices are encapsulated, or when LVM disks are converted to VM disks. It is also called implicitly by the vxdiskadm, vxconvert (on AIX) and vxvmconvert (on HP-UX) commands, and by the VOM.

The following is a sample vxencap defaults file:

format=sliced privlen=4096 privoffset=0 puboffset=1

See the vxencap(1M) manual page.

See the vxconvert(1M) manual page.

See the vxvmconvert(1M) manual page.

In the defaults files, a line that is empty, or that begins with a "#" character in the first column, is treated as a comment, and is ignored.

Apart from comment lines, all other lines must define attributes and their values using the format attribute=value. Each line starts in the first column, and is terminated by the value. No white space is allowed around the = sign.

Maintaining your system

You may need to perform maintenance tasks on the CDS disks and CDS disk groups. Refer to the respective section for each type of task.

Disk tasks

See "Disk tasks" on page 203.

- Disk group tasks See "Disk group tasks" on page 205.
- Displaying information See "Displaying information" on page 211.
- Default activation mode of shared disk groups See "Default activation mode of shared disk groups" on page 214.
- Additional considerations when importing CDS disk groups See "Defaults files" on page 200.

Disk tasks

The following disk tasks are supported:

- Changing the default disk format
- Restoring CDS disk labels

Changing the default disk format

When disks are put under VxVM control, they are formatted with the default cdsdisk layout. This happens during the following operations:

- Initialization of disks
- Encapsulation of disks with existing partitions or slices (Linux and Solaris systems)
- Conversion of LVM disks (AIX, HP-UX and Linux systems)

You can override this behavior by changing the settings in the system defaults files. For example, you can change the default format to sliced for disk initialization by modifying the definition of the format attribute in the /etc/default/vxdisk defaults file.

To change the default format for disk encapsulation or LVM disk conversion

■ Edit the /etc/default/vxencap defaults file, and change the definition of the format attribute.

See "Defaults files" on page 200.

Restoring CDS disk labels

CDS disks have the following labels:

■ Platform block

- AIX coexistence label
- HP-UX coexistence or VxVM ID block

There are also backup copies of each. If any of the primary labels become corrupted, VxVM will not bring the disk online and user intervention is required.

If two labels are intact, the disk is still recognized as a cdsdisk (though in the error state) and vxdisk flush can be used to restore the CDS disk labels from their backup copies.

Note: For disks larger than 1 TB, cdsdisks use the EFI layout. The procedure to restore disk labels does not apply to cdsdisks with EFI layout.

Primary labels are at sectors 0, 7, and 16; and a normal flush will not flush sectors 7 and 16. Also, the private area is not updated as the disk is not in a disk group. There is no means of finding a "good" private region to flush from. In this case, it is possible to restore the CDS disk labels from the existing backups on disk using the flush operation.

If a corruption happened after the labels were read and the disk is still online and part of a disk group, then a flush operation will also flush the private region.

Warning: Caution and knowledge must be employed because the damage could involve more than the CDS disk labels. If the damage is constrained to the first 128K, the disk flush would fix it. This could happen if another system on the fabric wrote a disk label to a disk that was actually a CDS disk in some disk group.

To rewrite the CDS ID information on a specific disk

- Type the following command:
 - # vxdisk flush disk access name

This rewrites all labels except sectors 7 and 16.

To rewrite all the disks in a CDS disk group

- Type the following command:
 - # vxdg flush diskgroup

This rewrites all labels except sectors 7 and 16.

To forcibly rewrite the AIX coexistence label in sector 7 and the HP-UX coexistence label or VxVM ID block in sector 16

■ Type the following command:

vxdisk -f flush disk access name

This command rewrites all labels if there exists a valid VxVM ID block that points to a valid private region. The -f option is required to rewrite sectors 7 and 16 when a disk is taken offline due to label corruption (possibly by a Windows system on the same fabric).

Disk group tasks

The following disk group tasks are supported:

- Changing the alignment of a disk group during disk encapsulation
- Changing the alignment of a non-CDS disk group
- Determining the setting of the CDS attribute on a disk group
- Splitting a CDS disk group
- Moving objects between CDS disk groups and non-CDS disk groups
- Moving objects between CDS disk groups
- Joining disk groups
- Changing the default CDS setting for disk group creation
- Creating non-CDS disk groups
- Upgrading an older version non-CDS disk group
- Replacing a disk in a CDS disk group
- Setting the maximum number of devices for CDS disk groups

Changing the alignment of a disk group during disk encapsulation

If you use the vxdiskadm command to encapsulate a disk into a disk group with an alignment of 8K, the disk group alignment must be reduced to 1.

If you use the vxencap command to perform the encapsulation, the alignment is carried out automatically without a confirmation prompt.

To change the alignment of a disk group during disk encapsulation

■ Run the vxdiskadm command, and select the "Add or initialize one or more disks" item from the main menu. As part of the encapsulation process, you are asked to confirm that a reduction of the disk group alignment from 8K to 1 is acceptable.

Changing the alignment of a non-CDS disk group

The alignment value can only be changed for disk groups with version 110 or greater.

For a CDS disk group, alignment can only take a value of 8k. Attempts to set the alignment of a CDS disk group to 1 fail unless you first change it to a non-CDS disk group.

Increasing the alignment may require vxcdsconvert to be run to change the layout of the objects in the disk group.

To display the current alignment value of a disk group, use the vaprint command.

See "Displaying the disk group alignment" on page 213.

To change the alignment value of a disk group

■ Type the vxdg set command:

```
# vxdq -q diskgroup set align={1|8k}
```

The operation to increase the alignment to 8K fails if objects exist in the disk group that do not conform to the new alignment restrictions. In that case, use the vxcdsconvert alignment command to change the layout of the objects:

```
# vxcdsconvert -g diskgroup [-A] [-d defaults file] \
  [-o novolstop] alignment [attribute=value] ...
```

This command increases the alignment value of a disk group and its objects to 8K, without converting the disks.

The sequence 8K to 1 to 8K is possible only using vxdg set as long as the configuration does not change after the 8K to 1 transition.

See "Converting a non-CDS disk group to a CDS disk group" on page 198.

Splitting a CDS disk group

You can use the yxdq split command to create a CDS disk group from an existing CDS disk group. The new (target) disk group preserves the setting of the CDS attribute and alignment in the original (source) disk group.

To split a CDS disk group

■ Use the vxdq split command to split CDS disk groups. See the Veritas Volume Manager Adminstrator's Guide.

Moving objects between CDS disk groups and non-CDS disk groups

The alignment of a source non-CDS disk group must be 8K to allow objects to be moved to a target CDS disk group. If objects are moved from a CDS disk group to a target non-CDS disk group with an alignment of 1, the alignment of the target disk group remains unchanged.

To move objects between a CDS disk group and a non-CDS disk group

■ Use the vxdg move command to move objects between a CDS disk group and a non-CDS disk groups.

See the Veritas Volume Manager Adminstrator's Guide.

Moving objects between CDS disk groups

The disk group alignment does not change as a result of moving objects between CDS disk groups.

To move objects between CDS disk groups

■ Use the vxdq move command to move objects between CDS disk groups. See the Veritas Volume Manager Adminstrator's Guide.

Joining disk groups

Joining two CDS disk groups or joining two non-CDS disk groups is permitted, but you cannot join a CDS disk group to a non-CDS disk group. If two non-CDS disk groups have different alignment values, the alignment of the resulting joined disk group is set to 1, and an informational message is displayed.

To join two disk groups

■ Use the vxdg join command to join two disk groups. See the Veritas Volume Manager Adminstrator's Guide.

Changing the default CDS setting for disk group creation

To change the default CDS setting for disk group creation

■ Edit the /etc/default/vxdq file, and change the setting for the cds attribute.

Creating non-CDS disk groups

A disk group with a version lower than 110 is given an alignment value equal to 1 when it is imported. This is because the dg align value is not stored in the configuration database for such disk groups.

To create a non-CDS disk group with a version lower than 110

■ Type the following vxdg command:

```
# vxdg -T version init diskgroup disk name=disk access name
```

Upgrading an older version non-CDS disk group

You may want to upgrade a non-CDS disk group with a version lower than 110 in order to use new features other than CDS. After upgrading the disk group, the cds attribute is set to off, and the disk group has an alignment of 1.

Note: You must also perform a disk group conversion (using the vxcdsconvert utility) to use the CDS feature.

To upgrade the non-CDS pre-version 110 disk group

- Type the following vxdg command:
 - # vxdq upgrade diskgroup

Replacing a disk in a CDS disk group

Note: When replacing a disk in a CDS disk group, you cannot use a non-CDS disk as the replacement.

To replace a disk in a CDS disk group

■ Type the following commands:

```
# vxdg -g diskgroup -k rmdisk disk name
# vxdg -g diskgroup -k adddisk disk_name=disk_access_name
```

The -k option retains and reuses the disk media record for the disk that is being replaced. The following example shows a disk device disk21 being reassigned to disk mydg01.

```
# vxdg -g diskgroup -k rmdisk mydg01
# vxdg -g diskgroup -k adddisk mydg01=disk21
```

For other operating systems, use the appropriate device name format.

Setting the maximum number of devices for CDS disk groups

To set the maximum number of devices that can be created in a CDS disk group

■ Type the following vxdg set command:

```
# vxdq -q diskgroup set maxdev=max-devices
```

The maxdev attribute can take any positive integer value that is greater than the number of devices that are currently in the disk group.

Changing the DRL map and log size

If DRL is enabled on a newly-created volume without specifying a log or map size, default values are used. You can use the command line attributes logmap len and loglen in conjunction with the vxassist, vxvol, and vxmake commands to set the DRL map and DRL log sizes. The attributes can be used independently, or they can be combined.

You can change the DRL map size and DRL log size only when the volume is disabled and the DRL maps are not in use. Changes can be made to the DRL map size only for volumes in a CDS disk group.

The logmap len attribute specifies the required size, in bytes, for the DRL log. It cannot be greater than the number of bytes available in the map on the disk.

To change the DRL map and log size

■ Use the following commands to remove and rebuild the logs:

```
# vxassist -g diskgroup remove log volume nlog=0
# vxassist -q diskgroup addlog volume nlog=nlogs \
 logtype=drl logmap len=len-bytes [loglen=len-blocks]
```

Note the following restrictions

If only logmap_len is specified	The DRL log size is set to the default value (33 * disk group alignment).
$\begin{array}{cccccccccccccccccccccccccccccccccccc$	The command fails, and you need to either provide a sufficiently large loglen value or reduce logmap_len.
For CDS disk groups	The DRL map and log sizes are set to a minimum of 2 * (disk group alignment).

Creating a volume with a DRL log

To create a volume with a traditional DRL log by using the vxassist command

■ Type the following command:

vxassist -g diskgroup make volume length mirror=2 \ logtype=drl [loglen=len-blocks] [logmap len=len-bytes]

This command creates log subdisks that are each equal to the size of the DRL

Note the following restrictions

If neither logmap len nor loglen is specified

- loglen is set to a default value that is based on disk group alignment.
- maplen is set to a reasonable value.

If only loglen is specified

- For pre-version 110 disk groups, maplen is set to zero.
- For version 110 and greater disk groups, maplen is set to use all the bytes available in the on-disk map.

If only logmap len is specified

- For pre-version 110 disk groups, logmap len is not applicable.
- For version 110 and greater disk groups, maplen must be less than the number of available bytes in the on-disk map for the default log length.

Setting the DRL map length

To set a DRL map length

- Stop the volume to make the DRL inactive.
- Type the following command:

```
# vxvol -g diskgroup set [loglen=len-blocks] \
  [logmap len=len-bytes] volume
```

This command does not change the existing DRL map size.

Note the following restrictions

If both logmap len and loglen are specified

- if logmap len is greater than loglen/2, vxvol fails with an error message. Either increase loglen to a sufficiently large value, or decrease logmap len to a sufficiently small value.
- The value of logmap len cannot exceed the number of bytes in the on-disk map.

If logmap len is specified

- The value is constrained by size of the log, and cannot exceed the size of the on-disk map. The size of the on-disk map in blocks can be calculated from the following formula:
 - round(loglen/nmaps) 24 where nmaps is 2 for a private disk group, or 33 for a shared disk group.
- The value of logmap len cannot exceed the number of bytes in the on-disk map.

If loglen is specified

- Specifying a value that is less than twice the disk group alignment value results in an error message.
- The value is constrained by size of the logging subdisk.

Displaying information

This section describes the following tasks:

- Determining the setting of the CDS attribute on a disk group
- Displaying the maximum number of devices in a CDS disk group
- Displaying map length and map alignment of traditional DRL logs
- Displaying the disk group alignment
- Displaying the log map length and alignment
- Displaying offset and length information in units of 512 bytes

Determining the setting of the CDS attribute on a disk group

To determine the setting of the CDS attribute on a disk group

■ Use the vxdq list command or the vxprint command to determine the setting of the CDS attribute, as shown in the following examples:

STATE ID NAME enabled,cds 1063238039.206.vmesc1 dgTestSol2 # vxdq list dqTestSol2 Group: dgTestSol2 dgid: 1063238039.206.vmesc1 import-id: 1024.205 flags: cds version: 110 alignment: 8192 (bytes) # vxprint -F %cds -G -g dgTestSol2 on

The disk group, dgTestSol2, is shown as having the CDS flag set.

Displaying the maximum number of devices in a CDS disk group

To display the maximum number of devices in a CDS disk group

■ Type the following command:

vxdq list

```
# vxprint -q diskgroup -G -F %maxdev
```

Displaying map length and map alignment of traditional DRL logs

To display the map length and map alignment of traditional DRL logs

■ Type the following commands

```
# vxprint -g diskgroup -vl volume
# vxprint -q diskgroup -vF '%name %logmap len %logmap align' \
 volume
```

Displaying the disk group alignment

To display the disk group alignment

■ Type the following command:

```
# vxprint -g diskgroup -G -F %align
```

Utilities such as vxprint and vxdg list that print information about disk group records also output the disk group alignment.

Displaying the log map length and alignment

To display the log map length and alignment

■ Type the following command:

```
# vxprint -g diskgroup -lv volume
```

For example, to print information for the volume vol1 in disk group dg1:

```
# vxprint -g dg1 -lv vol1
```

The output is of the form:

```
logging: type=REGION loglen=0 serial=0/0 mapalign=0
maplen=0 (disabled)
```

This indicates a log map alignment (logmap align) value of 0, and a log map length (logmap len) value of 0.

If the log map is set and enabled, the command and results may be in the following form:

```
# vxprint -lv drlvol
```

```
Disk group: dgTestSol
Volume: drlvol
info:
       len=20480
type: usetype=fsgen
state: state=ACTIVE kernel=ENABLED cdsrecovery=0/0 (clean)
assoc: plexes=drlvol-01, drlvol-02, drlvol-03
policies: read=SELECT (round-robin) exceptions=GEN DET SPARSE
flags: closed writecopy writeback
```

```
logging: type=REGION loglen=528 serial=0/0 mapalign=16
maplen=512 (enabled)
apprecov: seqno=0/0
recovery: mode=default
recov id=0
device: minor=46000 bdev=212/46000 cdev=212/46000
path=/dev/vx/dsk/dgTestSol/drlvol
perms: user=root group=root mode=0600
quid: {d968de3e-1dd1-11b2-8fc1-080020d223e5}
```

Displaying offset and length information in units of 512 bytes

To display offset and length information in units of 512 bytes

■ Specify the -b option to the vxprint and vxdisk commands, as shown in these examples:

```
# vxprint -bm
# vxdisk -b list
```

Specifying the -b option enables consistent output to be obtained on different platforms. Without the -b option, the information is output in units of sectors. The number of bytes per sector differs between platforms.

When the vxprint -bm or vxdisk -b list command is used, the output also contains the b suffix, so that the output can be fed back to vxmake.

Default activation mode of shared disk groups

The default activation mode of shared disk groups involves a local in-kernel policy that differs between platforms. This means that, regardless of the platform on which the disk group was created, the importing platform will have platform-specific behavior with respect to activation of shared disk groups. Specifically, with the exception of HP-UX, importing a shared disk group results in the volumes being active and enabled for shared-write. In the case of HP-UX. the shared volumes will be inactive and require other actions to activate them for shared-write operations.

Additional considerations when importing CDS disk groups

Before you attempt to use CDS to move disk groups between different operating systems, and if the configuration of the disks has changed since the target system was last rebooted, you should consider the following points

Does the target system know about the disks? For example, the disks may not have been connected to the system either physically (not cabled) or logically (using FC zoning or LUN masking) when the system was booted up, but they have subsequently been connected without rebooting the system. This can happen when bringing new storage on-line, or when adding an additional DMP path to existing storage. On the target system, both the operating system and VxVM must be informed of the existence of the new storage. Issue the appropriate command to tell the operating system to look for the storage. (On Linux, depending on the supported capabilities of the host adapter, you may need to reboot the target system to achieve this.) Having done this, run either of the following commands on the target system to have VxVM recognize the storage:

- # vxdctl enable
- # vxdisk scandisks

Do the disks contain partitions or slices?

Both the Solaris and Linux operating systems maintain information about partitions or slices on disks. If you repartition a disk after the target system was booted, use the appropriate command to instruct the operating system to rescan the disk's TOC or partition table. For example, on a target Linux system, use the following command:

blockdev --rereadpt

Having done this, run either of the following commands on the target system to have VxVM recognize the storage:

- # vxdctl enable
- # vxdisk scandisks

any of the disks changed since the target system was last booted?

Has the format of For example, if you use the vxdisksetup -i command to format a disk for VxVM on one system, the vxdisk list command on the target system may still show the format as being auto:none. If so, use either of the following commands on the target system to instruct VxVM to rescan the format of the disks:

- # vxdctl enable
- # vxdisk scandisks

File system considerations

To set up or migrate volumes with VxFS file systems with CDS, you must consider the file system requirements. This section describes these requirements. It also describes additional tasks required for migrating or setting up in CDS.

Considerations about data in the file system

Data within a file system might not be in the appropriate format to be accessed if moved between different types of systems. For example, files stored in proprietary binary formats often require conversion for use on the target platform. Files containing databases might not be in a standard format that allows their access when moving a file system between various systems, even if those systems use the same byte order. Oracle 10g's Cross-Platform Transportable Tablespace is a notable exception; if used, this feature provides a consistent format across many platforms.

Some data is inherently portable, such as plain ASCII files. Other data is designed to be portable and the applications that access such data are able to access it irrespective of the system on which it was created, such as Adobe PDF files.

Note that the CDS facilities do not convert the end user data. The data is uninterpreted by the file system. Only individual applications have knowledge of the data formats, and thus those applications and end users must deal with this issue. This issue is not CDS-specific, but is true whenever data is moved between different types of systems.

Even though a user might have a file system with data that cannot be readily interpreted or manipulated on a different type of system, there still are reasons for moving such data by using CDS mechanisms. For example, if the desire is to bring a file system off line from its primary use location for purposes of backing it up without placing that load on the server or because the system on which it will be backed up is the one that has the tape devices directly attached to it, then using CDS to move the file system is appropriate.

An example is a principal file server that has various file systems being served by it over the network. If a second file server system with a different operating system was purchased to reduce the load on the original server, CDS can migrate the file system instead of having to move the data to different physical storage over the network, even if the data could not be interpreted or used by either the original or new file server. This is a scenario that often occurs when the data is only accessible or understood by software running on PCs and the file server is UNIX or Linux-based.

File system migration

File system migration refers to the system management operations related to stopping access to a file system, and then restarting these operations to access the file system from a different computer system. File system migration might be required to be done once, such as when permanently migrating a file system to another system without any future desire to move the file system back to its original system or to other systems. This type of file system migration is referred to as one-time file system migration. When ongoing file system migration between multiple systems is desired, this is known as ongoing file system migration. Different actions are required depending on the kind of migration, as described in the following sections.

Specifying the migration target

Most of the operations performed by the CDS commands require the target to which the file system is to be migrated to be specified by target specifiers in the following format:

```
os name=name[,os rel=release][,arch=arch name]
[, vxfs version=version][, bits=nbits]
```

The CDS commands require the following target specifiers:

os_name= <i>name</i>	Specifies the name of the target operating system to which the file system is planned to be migrated. Possible values are HP-UX, AIX, SunOS, or Linux. The os_name field must be specified if the target is specified.
os_rel=release	Specifies the operating system release version of the target. For example, 11.31.
arch=arch_name	Specifies the architecture of the target. For example, specify ia or ${\tt pa}$ for HP-UX.
vxfs_version=version	Specifies the VxFS release version that is in use at the target. For example, 5.1.
bits=nbits	Specifies the kernel bits of the target. <i>nbits</i> can have a value of 32 or 64 to indicate whether the target is running a 32-bit kernel or 64-bit kernel.

While os name must be specified for all fscdsadm invocations that permit the target to be specified, all other target specifiers are optional and are available for the user to fine tune the migration target specification.

The CDS commands use the limits information available in the default CDS limits file, /etc/vx/cdslimitstab. If the values for the optional target specifiers are not specified, fscdsadm will choose the defaults for the specified target based on the information available in the limits file that best fits the specified target, and proceed with the CDS operation. The chosen defaults are displayed to the user before proceeding with the migration.

Note: The default CDS limits information file, /etc/vx/cdslimitstab, is installed as part of the VxFS package. The contents of this file are used by the VxFS CDS commands and should not be altered.

Examples of target specifications

The following are examples of target specifications:

os_name=AIX	Specifies the target operating system and use defaults for the remainder.
os_name=HP-UX, os_rel=11.23, arch=ia, vxfs_version=5.0, bits=64	Specifies the operating system, operating system release version, architecture, VxFS version, and kernel bits of the target.
os_name=SunOS, arch=sparc	Specifies the operating system and architecture of the target.
os_name=Linux, bits=32	Specifies the operating system and kernel bits of the target.

Using the fscdsadm command

The fscdsadm command can be used to perform the following CDS tasks:

- Checking that the metadata limits are not exceeded
- Maintaining the list of target operating systems
- Enforcing the established CDS limits on a file system
- Ignoring the established CDS limits on a file system
- Validating the operating system targets for a file system
- Displaying the CDS status of a file system

Checking that the metadata limits are not exceeded

To check that the metadata limits are not exceeded

■ Type the following command to check whether there are any file system entities with metadata that exceed the limits for the specified target operating system:

```
# fscdsadm -v -t target mount point
```

Maintaining the list of target operating systems

When a file system will be migrated on an ongoing basis between multiple systems, the types of operating systems that are involved in these migrations are maintained in a target list file. Knowing what these targets are allows VxFS to determine file system limits that are appropriate to all of these targets. The file system limits that are enforced are file size, user ID, and group ID. The contents of the target list file are manipulated by using the fscdsadm command.

Adding an entry to the list of target operating systems

To add an entry to the list of target operating systems

■ Type the following command:

```
# fscdsadm -o add -t target mount point
See "Specifying the migration target" on page 217.
```

Removing an entry from the list of target operating systems

To remove an entry from the list of target operating systems

■ Type the following command:

```
# fscdsadm -o remove -t target mount_point
See "Specifying the migration target" on page 217.
```

Removing all entries from the list of target operating systems

To remove all entries from the list of target operating systems

■ Type the following command:

```
# fscdsadm -o none mount point
```

Displaying the list of target operating systems

To display a list of all target operating systems

■ Type the following command:

```
# fscdsadm -o list mount point
```

Enforcing the established CDS limits on a file system

By default, CDS ignores the limits that are implied by the operating system targets that are listed in the target list file.

To enforce the established CDS limits on a file system

- Type the following command:
 - # fscdsadm -1 enforce mount point

Ignoring the established CDS limits on a file system

By default, CDS ignores the limits that are implied by the operating system targets that are listed in the target list file.

To ignore the established CDS limits on a file system

- Type the following command:
 - # fscdsadm -l ignore mount_point

Validating the operating system targets for a file system

To validate the operating system targets for a file system

- Type the following command:
 - # fscdsadm -v mount point

Displaying the CDS status of a file system

The CDS status that is maintained for a file system includes the following information:

- the target list file
- the limits implied by the target list file
- whether the limits are being enforced or ignored
- whether all files are within the CDS limits for all operating system targets that are listed in the target list file

To display the CDS status of a file system

- Type the following command:
 - # fscdsadm -s mount point

Migrating a file system one time

This example describes a one-time migration of data between two operating systems. Some of the following steps require a backup of the file system to be created. To simplify the process, you can create one backup before performing any of the steps instead of creating multiple backups as you go.

To perform a one-time migration

If the underlying Volume Manager storage is not contained in a CDS disk group, it must first be upgraded to be a CDS disk group, and all other physical considerations related to migrating the storage physically between systems must first be addressed.

See "Converting a non-CDS disk group to a CDS disk group" on page 198.

If the file system is using a disk layout version prior to 7, upgrade the file system to Version 7.

See the Veritas Storage Foundation Installation Guide.

Use the following command to ensure that there are no files in the file system that will be inaccessible after migrating the data due to large file size or to differences in user or group ID between platforms:

```
# fscdsadm -v -t target mount point
```

If such files exist, move the files to another file system or reduce the size of the files.

Unmount the file system:

```
# umount mount point
```

5 Use the fscdsconv command to convert the file system to the opposite endian.

```
See "Converting the byte order of a file system" on page 223.
```

Make the physical storage and Volume Manager logical storage accessible on the Linux system by exporting the disk group from the source system and importing the disk group on the target system after resolving any other physical storage attachment issues.

```
See "Disk tasks" on page 203.
```

Mount the file system on the target system.

Migrating a file system on an ongoing basis

This example describes how to migrate a file system between platforms on an ongoing basis. Some of the following steps require a backup of the file system to be created. To simplify the process, you can create one backup before performing any of the steps instead of creating multiple backups as you go.

To perform an ongoing migration

Use the following command to ensure that there are no files in the file system that will be inaccessible after migrating the data due to large file size or to differences in user or group ID between platforms:

```
# fscdsadm -v -t target mount point
```

If such files exist, move the files to another file system or reduce the size of the files.

- Add the platform on the target list file:
 - If migrating a file system between the Solaris and Linux, add sunos and Linux to the target list file:

```
# fscdsadm -o add -t os name=SunOS /mnt1
# fscdsadm -o add -t os name=Linux /mnt1
```

■ If migrating a file system between the HP-UX and Linux, add HP-UX and Linux to the target list file:

```
# fscdsadm -o add -t os name=HP-UX /mnt1
# fscdsadm -o add -t os name=Linux /mnt1
```

Enforce the limits:

```
# fscdsadm -1 enforce mount point
```

This is the last of the preparation steps. When the file system is to be migrated, it must be unmounted, and then the storage moved and mounted on the target system.

4 Unmount the file system:

```
# umount mount point
```

5 Make the file system suitable for use on the specified target.

See "Converting the byte order of a file system" on page 223.

Make the physical storage and Volume Manager logical storage accessible on the target system by exporting the disk group from the source system and importing the disk group on the target system after resolving any other physical storage attachment issues.

See "Disk tasks" on page 203.

7 Mount the file system on the target system.

Stopping ongoing migration

To stop performing ongoing migration

Type the following commands:

```
# fscdsadm -l ignore mount point
# fscdsadm -o none mount point
```

The file system is left on the current system.

When to convert a file system

When moving a file system between two systems, it is essential to run the fscdsconv command to perform all of the file system migration tasks. The fscdsconv command validates the file system to ensure that it does not exceed any of the established CDS limits on the target, and converts the byte order of the file system if the byte order of the target is opposite to that of the current system.

Warning: Prior to VxFS 4.0 and disk layout Version 6, VxFS did not officially support moving file systems between different platforms, although in many cases a user may have successfully done so. Do not move file systems between platforms when using versions of VxFS prior to Version 4, or when using disk layouts earlier than Version 6. Instead, upgrade to VxFS 4.0 or higher, and disk layout Version 6 or later. Failure to upgrade before performing cross-platform movement can result in data loss or data corruption.

Note: If you replicate data from a little-endian to a big-endian system (or vice versa), you must convert the application after the replication completes.

Converting the byte order of a file system

Use the fscdsconv command to migrate a file system from one system to another.

To convert the byte order of a file system

Determine the disk layout version of the file system that you will migrate:

```
# fstyp -v /dev/vx/rdsk/diskgroup/volume | grep version
```

```
magic a501fcf5 version 9 ctime Thu Jun 1 16:16:53 2006
```

Only file systems with disk layout Version 7 or later can be converted. If the file system has an earlier disk layout version, convert the file system to disk layout Version 7 or later before proceeding.

See the vxfsconvert(1M) manual page.

See the vxupgrade(1M) manual page.

- 2 Perform a full file system back up. Failure to do so could result in data loss or data corruption under some failure scenarios in which restoring from the backup is required.
- Designate a file system with free space where fscdsconv may create a file that will contain recovery information for usage in the event of a failed conversion.

Depending on the nature of the file system to be converted, for example if it is mirrored, you may wish to designate the recovery file to reside in a file system with the same level of failure tolerance. Having the same level of failure tolerance reduces the number of failure scenarios that would require trestoration from the backup.

Unmount the file system to be converted:

```
# umount mount point
```

Use the fscdsconv command to export the file system to the required target:

```
# fscdsconv -f recovery file -t target OS -e special device
```

target OS specifies the operating system to which you are migrating the file system.

See "Specifying the migration target" on page 217.

recovery file is the name of the recovery file to be created by the fscdsconv command.

special device is the raw device or volume that contains the file system to be converted.

Include the file system that you chose in 3 when designating the recovery file.

For example, if the file system chosen to contain the recovery file is mounted on /data/fs3, the recovery file could be specified as

/data/fs3/jan04recovery. If there is not enough disk space on the chosen file system for the recovery file to be created, the conversion aborts and the file system to be converted is left intact.

The recovery file is not only used for recovery purposes after a failure, but is also used to perform the conversion. The directory that will contain the recovery file should not allow non-system administrator users to remove or replace the file, as this could lead to data loss or security breaches. The file should be located in a directory that is not subject to system or local scripts will remove the file after a system reboot, such as that which occurs with the /tmp and /var/tmp directories on the Solaris operating system.

The recovery file is almost always a sparse file. The disk utilization of this file can best be determined by using the following command:

du -sk filename

The recovery file is used only when the byte order of the file system must be converted to suit the specified migration target.

If you are converting multiple file systems at the same time, which requires the use of one recovery file per file system, record the names of the recovery files and their corresponding file systems being converted in the event that recovery from failures is required at a later time.

- Based on the information provided regarding the migration target, fscdsconv constructs and displays the complete migration target and prompts the use to verify all details of the target. If the migration target must be changed, enter n to exit fscdsconv without modifying the file system. At this point in the process, fscdsconv has not used the specified recovery file.
- If the byte order of the file system must be converted to migrate the file system to the specified target, fscdsconv prompts you to confirm the migration. Enter y to convert the byte order of the file system. If the byte order does not need to be converted, a message displays indicating this fact.
- The fscdsconv command indicates if any files are violating the maximum file size, maximum UID, or maximum GID limits on the specified target and prompts you if it should continue. If you must take corrective action to ensure that no files violate the limits on the migration target, enter n to exit fscdsconv. At this point in the process, fscdsconv has not used the specified recovery file.

If the migration converted the byte order of the file system, fscdsconv created a recovery file. The recovery file is not removed after the migration completes, and can be used to restore the file system to its original state if required at a later time.

- 10 If a failure occurs during the conversion, the failure could be one of the following cases:
 - System failure.
 - fscdsconv failure due to program defect or abnormal termination resulting from user actions.

In such cases, the file system being converted is no longer in a state in which it can be mounted or accessed by normal means through other VxFS utilities. To recover the file system, invoke the fscdsconv command with the recovery flag, -r:

fscdsconv -r -f recovery_file special_device

When the -r flag is specified, fscdsconv expects the recovery file to exist and that the file system being converted is the same file system specified in this second invocation of fscdsconv.

11 After invoking fscdsconv with the -r flag, the conversion process will restart and complete, given no subsequent failures.

In the event of another failure, repeat 10.

Under some circumstances, you will be required to restore the file system from the backup, such as if the disk fails that contains the recovery file. Failure to have created a backup would then result in total data loss in the file system. I/O errors on the device that holds the file system would also require a backup to be restored after the physical device problems are addressed. There may be other causes of failure that would require the use of the backup.

Importing and mounting a file system from another system

The fscdsconv command can be used to import and mount a file system that was previously used on another system.

To import and mount a file system from another system

Convert the file system:

```
# fscdsconv -f recovery file -i special device
```

If the byte order of the file system needs to be converted

Enter y to convert the byte order of the file system when prompted by fscdsconv. If the migration converted the byte order of the file system, fscdsconv creates a recovery file that persists after the migration completes. If required, you can use this file to restore the file system to its original state at a later time.

If the byte order of the file system does not need does not need to be converted. to be converted

A message displays that the byte order of the file system

Alignment value and block size

On the AIX, Linux and Solaris operating systems, an alignment value of 1 is equivalent to a block size of 512 bytes. On the HP-UX operating system, it is equivalent to a block size of 1024 bytes.

The block size on HP-UX is different from that on other supported platforms. Output from commands such as vxdisk and vxprint looks different on HP-UX for the same disk group if the -b option is not specified.

Migrating a snapshot volume

This example demonstrates how to migrate a snapshot volume containing a VxFS file system from a Solaris SPARC system (big endian) to a Linux system (little endian) or HP-UX system (big endian) to a Linux system (little endian).

To migrate a snapshot volume

- Create the instant snapshot volume, snapvol, from an existing plex in the volume, vol, in the CDS disk group, datadg:
 - # vxsnap -q datadq make source=vol/newvol=snapvol/nmirror=1
- Quiesce any applications that are accessing the volume. For example, suspend updates to the volume that contains the database tables. The database may have a hot backup mode that allows you to do this by temporarily suspending writes to its tables.
- Refresh the plexes of the snapshot volume using the following command:
 - # vxsnap -q datadg refresh snapvol source=yes syncing=yes
- The applications can now be unquiesced.
 - If you temporarily suspended updates to the volume by a database in 2, release all the tables from hot backup mode.
- Use the vxsnap syncwait command to wait for the synchronization to complete:
 - # vxsnap -q datadq syncwait snapvol
- 6 Check the integrity of the file system, and then mount it on a suitable mount point:
 - # fsck -F vxfs /dev/vx/rdsk/datadg/snapvol # mount -F vxfs /dev/vx/dsk/datadg/snapvol /mnt
- 7 Confirm whether the file system can be converted to the target operating system:
 - # fscdstask validate Linux /mnt

- Unmount the snapshot:
 - # umount /mnt
- Convert the file system to the opposite endian:

```
# fscdsconv -e -f recoveryfile -t target_specifiers special
```

For example:

```
# fscdsconv -e -f /tmp/fs_recov/recov.file -t Linux \
/dev/vx/dsk/datadg/snapvol
```

This step is only required if the source and target systems have the opposite endian configuration.

- 10 Split the snapshot volume into a new disk group, migdg, and deport that disk group:
 - # vxdg split datadg migdg snapvol
 - # vxdg deport migdg
- 11 Import the disk group, migdg, on the Linux system:
 - # vxdg import migdg

It may be necessary to reboot the Linux system so that it can detect the disks.

- **12** Use the following commands to recover and restart the snapshot volume:
 - # vxrecover -g migdg -m snapvol
- 13 Check the integrity of the file system, and then mount it on a suitable mount point:
 - # fsck -t vxfs /dev/vx/dsk/migdg/snapvol
 - # mount -t vxfs /dev/vx/dsk/migdg/snapvol /mnt

Index

Symbols	C
/etc/default/vxassist defaults file 201	CDS
/etc/default/vxcdsconvert defaults file 201	attribute 212
/etc/default/vxdg defaults file 201	changing setting 207
/etc/default/vxdisk defaults file 202	creating DGs 196
/etc/default/vxencap defaults file 202	creating disks 195
/etc/vx/darecs file 195	disk group alignment 188
	disk group device quotas 190
A	disks 188
access type 189	CDS disk groups
activation	alignment 213
default 212	joining 207
AIX coexistence label 189	moving 207
alignment 191	setting alignment 206
changing 206	CDS disks
ARCHIVELOG mode 86	creating 194
archiving	changing CDS setting 207
using NetBackup 89	changing default CDS setting 207
attribute	changing disk format 203
CDS 212	cluster file systems
attributes	off-host backup of 76
init 56, 78	co-existence label 189
ndcomirror 56, 78	concepts 185
nmirror 56, 78	Concurrent I/O
regionsize 59, 104	benefits 25
auto disk type 189	disabling 28–29
	enabling 26, 29
В	converting non-CDS disks to CDS 196
_	converting non-CDS disks to CDS disks 197
backing up	creating a DRL log 209
using NetBackup 89	creating CDS disk groups 196
backup of cluster file systems 76	creating CDS disks 194–195
of online databases 53	creating DRL logs 209
	creating non-CDS disk groups 207
backups areating for valumes, 42	creating pre-version 110 disk groups 207
creating for volumes 43 benefits of Concurrent I/O 25	cross-platform data sharing
block size 187	recovery file 224
blockdevrereadpt 215	current-rev disk groups 191
blockdevlefeaupt 213	

using for off-host processing 120 databases incomplete media recovery 87 integrity of data in 44 online backup of 53 rolling back 87 using Storage Checkpoints 85 decision support using point-in-time copy solutions 98 default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 labels 203 labels 203 labels 203 disk format 188 disk group alignment 206 displaying 213 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk types 188 disks setficts of formatting or partitioning 214 displaying disk group alignment 213 displaying bolk map size 212 displaying Volume log map values 213 disting disk groups 214 displaying volume log map values 213	D	DRL log size
databases incomplete media recovery 87 integrity of data in 44 online backup of 53 rolling back 87 using Storage Checkpoints 85 decision support using point-in-time copy solutions 98 default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk format 188 disk group alignment 206 displaying 213 disk group s189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk quotas setting 208 disk quotas setting 208 disk types 188 disk seffects of formatting or partitioning 214 displaying DRL map size 212 displaying Volume log map values 213	data on Secondary	displaying 212
incomplete media recovery 87 integrity of data in 44 online backup of 53 rolling back 87 using Storage Checkpoints 85 decision support using point-in-time copy solutions 98 default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk group 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk quotas setting 208 disk types 188 disk yeo disk quotas setting 208 disk types 188 disk seeffects of formatting or partitioning 214 displaying DRL log size 212 displaying DRL log size 212 displaying log map values 213 displaying volume log map values 213	using for off-host processing 120	e
integrity of data in 44 online backup of 53 rolling back 87 using Storage Checkpoints 85 decision support using point-in-time copy solutions 98 default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk group alignment 206 displaying 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk vpes 188 disk yes 188 disks weffects of formatting or partitioning 214 displaying DRL log size 212 displaying DRL log size 212 displaying bog map values 213 displaying volume log map values 213 DRL map length 210 DRL map size 212 displaying 212 setting 209 DSS. See Decision Support E enabling Concurrent I/O 26, 29 encapsulation 203 FastResync Persistent 43 file systems mounting for shared access 78 FileSnaps about 45 data mining, reporting, and testing 120 virtual desktops 125 write intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 init attribute 36, 78 init	databases	_
online backup of 53 rolling back 87 using Storage Checkpoints 85 decision support using point-in-time copy solutions 98 default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 labels 203 labels 203 labels 203 laving 208 disk group alignment 206 displaying 213 disk group alignment 206 disk group alignment 206 disk group 189 alignment 191 creating 207 poining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk group alignment 213 displaying device quotas 212 displaying DRL loap size 212 displaying DRL map size 2 displaying volume log map values 213 DRL map size displaying 212 setting 209 DSS. See Decision Support setting 209 encapsulation 203 FastResync Persistent 43 file systems mounting for shared access 78 FileSnaps about 45 data mining, reporting, and testing 126 virtual desktops 125 wite intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I JO block size 187 D block 189 init attribute 56, 78 init attribute 56, 78 init attribute 56, 78 init attribute 30	incomplete media recovery 87	
online backup of 53 rolling back 87 using Storage Checkpoints 85 decision support using point-in-time copy solutions 98 default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk group alignment 213 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying volume log map values 213	integrity of data in 44	
using Storage Checkpoints 85 decision support using point-in-time copy solutions 98 default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disabling Concurrent I/O 28-29 disabling Concurrent 203 labels 203 LVM 203 replacing 208 disk access type 189 change format 206 displaying 213 disk group alignment 206 displaying 213 disk group alignment 206 displaying 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk group alignment 213 displaying device quotas 212 displaying disk group alignment 213 displaying log size 212 displaying log map values 213 displaying volume log map values 213	online backup of 53	
decision support using point-in-time copy solutions 98 default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 207 joining CDS disk groups 207 joining disk groups 207 joining disk groups 207 joining disk groups 207 displaying bog map values 213 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213	rolling back 87	
using point-in-time copy solutions 98 default CDS setting changing 207 defaults files 197, 200 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 26, 29 encapsulation 203 F FastResync Persistent 43 file systems mounting for shared access 78 FileSnaps about 45 data mining, reporting, and testing 126 virtual desktops 125 write intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 207 joining CDS disk groups 207 joining disk groups 207 licensing 200 listing disk groups 214	using Storage Checkpoints 85	e
default activation 212 default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk types 188 disk types 188 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying disk group alignment 213 displaying device quotas 212 displaying log size 212 displaying log size 212 displaying vlogmap values 213 displaying volume log map values 213	decision support	DSS. See Decision Support
default CDS setting changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk access 187 stike group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk types 188 disks effects of formatting or partitioning 214 displaying DRL log size 212 displaying DRL map size 212 displaying DRL map size 212 displaying Use Mark 213 displaying volume log map values 213 displaying volume log values 213 displaying vol	using point-in-time copy solutions 98	
changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks disks effects of formatting or partitioning 214 displaying DRL map size 212 displaying DRL map size 212 displaying values 213 displaying volume log map values 213 disting disk groups 207 encapsulation 203 encapsulation 203 encapsulation 203 encapsulation 203 F FastResync Persistent 43 file systems mounting for shared access 78 FileSnaps about 45 data mining, reporting, and testing 126 virtual desktops 125 write intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 instant snapshots reattaching 85, 120 intent logging 44 L L length listing 214 licensing 200 listing disk groups 214	default activation 212	E
changing 207 defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying volume log map values 213	default CDS setting	enabling Concurrent I/O 26, 29
defaults files 197, 200 device quotas 190, 212 displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying Volgmap values 213 displaying volume log map values 213 FastResync Persistent 43 file systems mounting for shared access 78 FileSnaps about 45 data mining, reporting, and testing 126 virtual desktops 125 write intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 instant snapshots reattaching 85, 120 intent logging 44 L length listing 214 licensing 200 listing disk groups 214	changing 207	
displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk group 207 joining 207 non-CDS 191 upgrading 208 disk types 189 disk types 188 disk youtas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying log map values 213 displaying volume log map values 213 FastResync Persistent 43 file systems mounting for shared access 78 FileSnaps about 45 data mining, reporting, and testing 126 virtual desktops 125 write intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 initent logging 44 joining CDS disk groups 207 joining disk groups 207 joining disk groups 207 joining disk groups 207 joining disk groups 207 joining disk groups 207 length listing 214 licensing 200 listing disk groups 214	defaults files 197, 200	-
displaying 212 setting 208 disabling Concurrent I/O 28-29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk types 188 disk youtas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying DRL log size 212 displaying DRL map size 212 displaying volume log map values 213	device quotas 190, 212	E
disabling Concurrent I/O 28–29 disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL map size 212 displaying log size 212 displaying volume log map values 213	displaying 212	-
disk access type 189 change format 203 labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying DRL log size 212 displaying DRL map size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213 disting disk groups 214 displaying volume log map values 213 file systems mounting for shared access 78 FileSnaps about 45 data mining, reporting, and testing 126 virtual desktops 125 write intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 instant snapshots reattaching 85, 120 intent logging 44 J joining CDS disk groups 207 joining disk groups 207 join	setting 208	•
access type 189 change format 203 labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying V_logmap values 213 displaying volume log map values 213 mounting for shared access 78 FileSnaps about 45 data mining, reporting, and testing 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 init attribute 56, 7	disabling Concurrent I/O 28-29	
change format 203 labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log size 212 displaying volume log map values 213 FileSnaps about 45 data mining, reporting, and testing 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 instant snapshots reattaching 85, 120 intent logging 44 J joining CDS disk groups 207 joining disk groups 207 joining disk groups 207 L length listing 214 licensing 200 listing disk groups 214	disk	•
labels 203 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying disk group alignment 213 displaying DRL log size 212 displaying log size 212 displaying log size 212 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213 disting disk groups 214 displaying volume log map values 213 disting disk groups 214 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213 disting disk groups 214 displaying volume log map values 213 disting disk groups 214	access type 189	•
laters 205 LVM 203 replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk quotas setting 208 disk ypes 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying disk group alignment 213 displaying DRL log size 212 displaying log size 212 displaying log size 212 displaying log size 212 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213 distant snapshots reattaching 85, 120 intent logging 44 L data mining, reporting, and testing 126 virtual desktops 125 write intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 instant snapshots reattaching 85, 120 intent logging 44 L L L L L L L L L L L L	change format 203	
replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying log size 212 displaying log size 212 displaying log size 212 displaying volume log map values 213 displaying vice quotas 214 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213 displaying disk groups 214 virtual desktops 125 write intensive applications 126 best practices 125 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 instant snapshots reattaching 85, 120 intent logging 44 displaying CDS disk groups 207 joining CDS disk groups 207 L length listing 214 licensing 200 listing disk groups 214	labels 203	
replacing 208 disk access 187 disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying disk group alignment 213 displaying DRL map size 212 displaying log size 212 displaying log size 212 displaying log size 212 displaying volume log map values 213	LVM 203	
disk format 188 disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log size 212 displaying log size 212 displaying log size 212 displaying volume log map values 213	replacing 208	•
disk group alignment 206 displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying log map values 213 displaying volume log map values 213 displaying disk groups 206 FlashSnap 42 fscdsadm 218 fscdsconv 223 I/O block size 187 ID block 189 init attribute 56, 78 instant snapshots reattaching 85, 120 intent logging 44 J joining CDS disk groups 207 joining disk groups 207 L length listing 214 licensing 200 listing disk groups 214	disk access 187	= =
displaying 213 disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying log map values 213 displaying v_logmap values 213 displaying volume log map values 213 displaying volume log map values 213	disk format 188	*
disk groups 189 alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying v_logmap values 213 displaying volume log map values 213	disk group alignment 206	_
alignment 191 creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 disting disk groups 214 displaying volume log map values 213 displaying volume log map values 213 disting disk groups 214		
creating 207 joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213 disting disk groups 214 displaying v_logmap values 213 displaying volume log map values 213 disting disk groups 214	disk groups 189	iscasconv 223
joining 207 non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213 disting disk groups 214	alignment 191	
non-CDS 191 upgrading 208 disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 displaying volume log map values 213 displaying volume log map values 213 disting disk groups 214 licensing 200 listing disk groups 214	creating 207	I
upgrading 208 disk quotas setting 208	joining 207	I/O block size 187
disk quotas setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying volume log map values 213 disting disk groups 207 instant snapshots reattaching 85, 120 intent logging 44 joining CDS disk groups 207 joining disk groups 207 L length listing 214 licensing 200 listing disk groups 214	non-CDS 191	ID block 189
setting 208 disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log map values 213 displaying v_logmap values 213 displaying volume log map values 213 disting disk groups 207 reattaching 85, 120 intent logging 44 joining CDS disk groups 207 L L length listing 214 dicensing 200 disting disk groups 214	upgrading 208	init attribute 56, 78
disk types 188 disks effects of formatting or partitioning 214 displaying device quotas 212 displaying disk group alignment 213 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 licensing 200 displaying device quotas 214 joining CDS disk groups 207 joining disk groups 207 L length listing 214 licensing 200 listing disk groups 214	disk quotas	instant snapshots
disks effects of formatting or partitioning 214 displaying device quotas 212 displaying disk group alignment 213 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 licensing 200 displaying volume log map values 213		reattaching 85, 120
effects of formatting or partitioning 214 displaying device quotas 212 displaying disk group alignment 213 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 licensing 200 displaying device quotas 212 licensing 200 listing disk groups 207 L licensing 214 licensing 200 listing disk groups 214	disk types 188	intent logging 44
displaying device quotas 212 displaying disk group alignment 213 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 licensing 200 displaying device quotas 212 joining CDS disk groups 207 L L length listing 214 licensing 200 listing disk groups 214		
displaying disk group alignment 213 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 licensing 200 displaying volume log map values 213	effects of formatting or partitioning 214	J
displaying disk group alignment 213 displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 licensing 200 displaying volume log map values 213 listing disk groups 207		ioining CDS disk groups 207
displaying DRL log size 212 displaying DRL map size 212 displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying v_logmap values 213 displaying volume log map values 213 licensing 200 displaying volume log map values 213 listing disk groups 214		
displaying log map values 213 displaying log size 212 displaying v_logmap values 213 displaying volume log map values 213 displaying volume log map values 213 licensing 200 listing disk groups 214		Johning disk groups 207
displaying log size 212 length listing 214 displaying v_logmap values 213 licensing 200 displaying volume log map values 213 listing disk groups 214		•
displaying v_logmap values 213 licensing 200 lisplaying volume log map values 213 listing disk groups 214		L
displaying volume log map values 213 listing disk groups 214	displaying log size 212	
	displaying volume log map values 213	listing disk groups 214 listing disks 214

listing offset and length information 207	R
log size	recovery
displaying 212 setting 209	using Storage Checkpoints 85
Logical Volume Manager (LVM) 153	recovery file, cross-platform data sharing 224
LVM	regionsize attribute 59, 104
conversion to VxVM 153	replacing disks 208
converting unused physical volumes 154	resetlogs option 88 restoring
converting volume groups 155	using NetBackup 89
limitations on converting volume groups 156	restoring CDS disk labels 203
restoring a volume group 171	restoring disk labels 203
LVM disks 203	Teoreting alon labels 200
	S
M	Secondary
minor device numbers 191	using data 120
mounting	setting CDS disk group alignment 206
shared-access file systems 78	setting device quotas 208
moving CDS disk groups 207	setting disk quotas 208
moving disk group objects 207	setting DRL log size 209
	setting DRL map length 210
N	setting DRL map size 209
ndcomirror attribute 56, 78	setting log size 209
NetBackup	shared access
overview 89	mounting file systems for 78
nmirror attribute 56, 78	Sistina LVM 153
	snapshots
0	reattaching instant 85, 120
objects	Storage Checkpoints 44 creating 86
moving 207	database recovery 85
off-host backup of cluster file systems	Storage Rollback
using point-in-time copy solutions 76	implementing using Storage Checkpoints 85
offset	using VxDBA 87
listing 214	
offset information 214	U
online database backup	upgrading disk groups 208
using point-in-time copy solutions 53	upgrading pre-version 110 disk groups 208
operating system data 187	upgrading pre version 110 disk groups 200
P	V
Persistent FastResync 43	v_logmap
platform block 189	displaying 213
point-in-time copy solutions	volumes
applications 41	backing up 43
for decision support 98	vradmin utility
for off-host cluster file system backup 76	ibc
for online database backup 53	using off-host processing 120
private region 188	vxcdsconvert 197
public region 188	vxdctl enable 215

vxdg init 196 vxdg split 206 vxdisk scandisks 215 vxdiskadm 194, 196 vxdisksetup 194 vxlvmconv completing conversion 171 vxsnap reattaching instant snapshots 85, 120 VxVMdevices 187 vxvmconvert converting an LVM volume group 158 restoring an LVM volume group 171 vxvol 210