Veritas Storage Foundation™ and High Availability Solutions 6.0 Platform Release 1

Solutions Guide

Solaris



Veritas Storage Foundation and High Availability Solutions Guide

The software described in this book is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

Product version: 6.0 PR1

Document version: 6.0PR1.0

Legal Notice

Copyright © 2012 Symantec Corporation. All rights reserved.

Symantec, the Symantec logo, Veritas, Veritas Storage Foundation, CommandCentral, NetBackup, Enterprise Vault, and LiveUpdate are trademarks or registered trademarks of Symantec corporation or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Symantec Corporation and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. SYMANTEC CORPORATION SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, "Rights in Commercial Computer Software or Commercial Computer Software Documentation", as applicable, and any successor regulations. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Symantec Corporation 350 Ellis Street Mountain View, CA 94043

http://www.symantec.com

Technical Support

Symantec Technical Support maintains support centers globally. Technical Support's primary role is to respond to specific queries about product features and functionality. The Technical Support group also creates content for our online Knowledge Base. The Technical Support group works collaboratively with the other functional areas within Symantec to answer your questions in a timely fashion. For example, the Technical Support group works with Product Engineering and Symantec Security Response to provide alerting services and virus definition updates.

Symantec's support offerings include the following:

- A range of support options that give you the flexibility to select the right amount of service for any size organization
- Telephone and/or Web-based support that provides rapid response and up-to-the-minute information
- Upgrade assurance that delivers software upgrades
- Global support purchased on a regional business hours or 24 hours a day, 7 days a week basis
- Premium service offerings that include Account Management Services

For information about Symantec's support offerings, you can visit our Web site at the following URL:

www.symantec.com/business/support/index.jsp

All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policy.

Contacting Technical Support

Customers with a current support agreement may access Technical Support information at the following URL:

www.symantec.com/business/support/contact techsupp static.jsp

Before contacting Technical Support, make sure you have satisfied the system requirements that are listed in your product documentation. Also, you should be at the computer on which the problem occurred, in case it is necessary to replicate the problem.

When you contact Technical Support, please have the following information available:

Product release level

- Hardware information
- Available memory, disk space, and NIC information
- Operating system
- Version and patch level
- Network topology
- Router, gateway, and IP address information
- Problem description:
 - Error messages and log files
 - Troubleshooting that was performed before contacting Symantec
 - Recent software configuration changes and network changes

Licensing and registration

If your Symantec product requires registration or a license key, access our technical support Web page at the following URL:

www.symantec.com/business/support/

Customer service

Customer service information is available at the following URL:

www.symantec.com/business/support/

Customer Service is available to assist with non-technical questions, such as the following types of issues:

- Questions regarding product licensing or serialization
- Product registration updates, such as address or name changes
- General product information (features, language availability, local dealers)
- Latest information about product updates and upgrades
- Information about upgrade assurance and support contracts
- Information about the Symantec Buying Programs
- Advice about Symantec's technical support options
- Nontechnical presales questions
- Issues that are related to CD-ROMs or manuals

Support agreement resources

If you want to contact Symantec regarding an existing support agreement, please contact the support agreement administration team for your region as follows:

Asia-Pacific and Japan customercare_apac@symantec.com

Europe, Middle-East, and Africa semea@symantec.com

North America and Latin America supportsolutions@symantec.com

Documentation

Your feedback on product documentation is important to us. Send suggestions for improvements and reports on errors or omissions. Include the title and document version (located on the second page), and chapter and section titles of the text on which you are reporting. Send feedback to:

doc_feedback@symantec.com

About Symantec Connect

Symantec Connect is the peer-to-peer technical community site for Symantec's enterprise customers. Participants can connect and share information with other product users, including creating forum posts, articles, videos, downloads, blogs and suggesting ideas, as well as interact with Symantec product teams and Technical Support. Content is rated by the community, and members receive reward points for their contributions.

http://www.symantec.com/connect/storage-management

Contents

Technical Sup	port	4
Section 1	Solutions for Veritas Storage Foundation and High Availability products	15
Chapter 1	Solutions for Veritas Storage Foundation and High Availability products	17
	About Storage Foundation and High Availability Solutions	
	Availability Solutions 6.0 products	
	management feature information	22
Section 2	Improving database performance	23
Chapter 2	Overview of database accelerators	25
	About Storage Foundation and High Availability Solutions products database accelerators	25
Chapter 3	Improving database performance with Veritas Quick	27
	About Quick I/O	
	How Quick I/O works	
	How Quick I/O improves database performance	
	How to set up Quick I/O	31
	Creating DB2 database containers or Sybase files as Quick I/O files	
	using qiomkfile Preallocating space for Quick I/O files using the setext	32
	command	37
	Accessing regular VxFS files as Quick I/O files	
	About sparse files	

	Displaying Quick I/O status and file attributes	42
	Extending a Quick I/O file in a DB2 or Sybase environment	
	containers	46
	Creating Quick I/O files in Solaris local zone	
	Disabling Quick I/O	
	Disability Quick if 0	50
Chapter 4	Improving database performance with Veritas Cached Quick I/O	53
	About Cached Quick I/O	53
	How Cached Quick I/O works in a DB2 environment	
	How Cached Quick I/O works in a Sybase environment	
	How Cached Quick I/O improves database performance	
	Tasks for setting up Cached Quick I/O	
	Enabling Cached Quick I/O on a file system	
	Enabling and disabling the qio_cache_enable flag	
	Making Cached Quick I/O settings persistent across reboots and	07
	mounts	58
	Using vxtunefs to obtain tuning information	
	Determining candidates for Cached Quick I/O	
	Collecting I/O statistics	
	About I/O statistics for DB2	
	About I/O statistics for Sybase	
	Effects of read-aheads on I/O statistics	
	Other tools for analysis	
	Enabling and disabling Cached Quick I/O for individual files	
	Setting cache advisories for individual files	
	Making individual file settings for Cached Quick I/O	
	persistent	66
	Determining individual file settings for Cached Quick I/O using	
	qioadmin	67
Chapter E	Improving database performance with Verites	
Chapter 5	Improving database performance with Veritas	
	Concurrent I/O	69
	About Concurrent I/O	69
	How Concurrent I/O works	69
	Tasks for enabling and disabling Concurrent I/O	70
	Enabling Concurrent I/O for DB2	
	Disabling Concurrent I/O for DB2	
	Enabling Concurrent I/O for Sybase	
	Disabling Concurrent I/O for Sybase	

Section 3	Using point-in-time copies	75
Chapter 6	Understanding point-in-time copy methods	77
	About point-in-time copies	77
	host	78
	Implementing off-host point-in-time copy solutions	
	When to use point-in-time copies	
	About Storage Foundation point-in-time copy technologies	
	Volume-level snapshots	
	Storage Checkpoints	
	About FileSnaps	89
Chapter 7	Backing up and recovering	91
	About Storage Foundation and High Availability Solutions backup	0.4
	and recovery use cases	
	point-in-time copies	92
	Setting up a full image snapshot and incremental point-in-time	
	copies	
	Refreshing point-in-time copies	
	Recovering from logical corruption	
	Off-host processing using refreshed snapshot images	
	Online database backups	
	Making a backup of an online database on the same host	
	Making an off-host backup of an online database	
	Backing up on an off-host cluster file system	
	Mounting a file system for shared access	122
	Preparing a snapshot of a mounted file system with shared	100
	access	122
	Backing up a snapshot of a mounted file system with shared	104
	access	
	Resynchronizing a volume from its snapshot volume	
	Reattaching snapshot plexes	
	Database recovery using Storage Checkpoints	
	Creating Storage Checkpoints	
	Rolling back a database	131

Chapter 8	Backing up and recovering in a NetBackup environment	133
	About Veritas NetBackup	133
	About using Veritas NetBackup for backup and restore for DB2	
	About using NetBackup for backup and restore for Sybase	
	About using Veritas NetBackup to backup and restore Quick I/O files for DB2	136
	About using Veritas NetBackup to backup and restore Quick I/O files for Sybase	
	Using NetBackup in an SFHA Solutions product environment	
	Clustering a NetBackup Master Server	
	Backing up and recovering a VxVM volume using	
	NetBackup	
	Recovering a VxVM volume using NetBackup	141
Chapter 9	Off-host processing	143
	Storage Foundation off-host processing methods	143
	Using a replica database for decision support	144
	Creating a replica database on the same host	145
	Creating an off-host replica database	
	What is off-host processing?	166
	About using VVR for off-host processing	166
Chapter 10	Creating and refreshing test environments	167
	About test environments	167
	Creating a test environment	167
	Refreshing a test environment	168
Chapter 11	Creating point-in-time copies of files	171
	Using FileSnaps to create point-in-time copies of files	171
	Using FileSnaps to provision virtual desktops	171
	Using FileSnaps to optimize write intensive applications for virtual machines	170
	Using FileSnaps to create multiple copies of data instantly	
	Come the chart to create multiple copies of data installity	1/2

Section 4	Maximizing storage utilization	175
Chapter 12	Optimizing storage tiering with SmartTier	177
	About SmartTier	177
	SmartTier building blocks	178
	About VxFS multi-volume file systems	179
	About VxVM volume sets	179
	About volume tags	180
	SmartTier use cases for DB2 or Sybase	180
	Setting up a filesystem for storage tiering with SmartTier	180
	Relocating old archive logs to tier two storage using SmartTier	183
	Relocating inactive tablespaces or segments to tier two storage	
	Relocating active indexes to premium storage	
	Relocating all indexes to premium storage	190
Section 5	Migrating data	195
Chapter 13	Understanding data migration	197
	Types of data migration	197
Chapter 14	Offline migration from Solaris Volume Manager to Veritas Volume Manager	
	_	
	About migration from Solaris Volume Manager How Solaris Volume Manager objects are mapped to VxVM	199
	objects	201
	Conversion of soft partitions	203
	Overview of the conversion process	204
	Plan and prepare for the conversion	205
	Set up the conversion	205
	Perform the conversion	
	Perform post-conversion tasks	
	Planning the conversion	
	Scheduling considerations	
	Schedule downtime	
	Check metadevices	
	Identify references by applications	209
	Preparing a Solaris Volume Manager configuration for	
	conversion	
	Installing VxVM	209

	Setting up a Solaris Volume Manager configuration for	
	conversion	210
	Run preconvert	210
	Run showconvert	211
	Run convertname	211
	Make backups	213
	Converting from the Solaris Volume Manager software to VxVM	213
	Reboot the system	
	Change volume references	
	Post conversion tasks	
	Improve volume layouts	
	Remove the Solaris Volume Manager software	
	Converting a root disk	
Chapter 15	Online migration of a native file system to the VxFS file system	217
	About online migration of a native file system to the VxFS file	
	system	217
	to the VxFS file system	218
	Migrating a native file system to the VxFS file system	219
	Migrating a source file system to the VxFS file system over NFS	221
	v3	
	Restrictions of NFS v3 migration	
	file system	223
	VxFS features not available during online migration	223
Chapter 16	Migrating storage arrays	225
	Array migration for storage using Linux	225
	Overview of storage mirroring for migration	
	Allocating new storage	
	Initializing the new disk	
	Checking the current VxVM information	
	Adding a new disk to the disk group	
	Mirroring	
	Monitoring	
	Mirror completion	
	Removing old storage	
	Post-mirroring steps	

Chapter 17	Migrating data between platforms	237
	Overview of the Cross-Platform Data Sharing (CDS) feature	237
	Shared data across platforms	
	Disk drive sector size	239
	Block size issues	239
	Operating system data	239
	CDS disk format and disk groups	240
	CDS disk access and format	240
	Non-CDS disk groups	243
	Disk group alignment	243
	Setting up your system to use Cross-platform Data Sharing	
	(CDS)	245
	Creating CDS disks from uninitialized disks	246
	Creating CDS disks from initialized VxVM disks	247
	Creating CDS disk groups	248
	Converting non-CDS disks to CDS disks	
	Converting a non-CDS disk group to a CDS disk group	
	Verifying licensing	
	Defaults files	
	Maintaining your system	255
	Disk tasks	
	Disk group tasks	257
	Displaying information	
	Default activation mode of shared disk groups	
	Additional considerations when importing CDS disk groups	
	File system considerations	
	Considerations about data in the file system	
	File system migration	
	Specifying the migration target	
	Using the fscdsadm command	
	Migrating a file system one time	
	Migrating a file system on an ongoing basis	
	When to convert a file system	
	Converting the byte order of a file system	
	Alignment value and block size	
	Disk group alignment and encapsulated disks	
	Disk group import between Linux and non-Linux machines	
	Migrating a snapshot volume	
Indev		205

Section

Solutions for Veritas Storage Foundation and High Availability products

■ Chapter 1. Solutions for Veritas Storage Foundation and High Availability products

Chapter 1

Solutions for Veritas Storage Foundation and High Availability products

This chapter includes the following topics:

- About Storage Foundation and High Availability Solutions
- Feature support across Veritas Storage Foundation and High Availability Solutions 6.0 products
- Using SmartMove and Thin Provisioning with DB2 and Sybase
- Finding Veritas Storage Foundation and High Availability Solutions management feature information

About Storage Foundation and High Availability Solutions

Veritas Storage Foundation and High Availability (SFHA) Solutions product components and features can be used individually and in concert to improve performance, resilience, and ease of management for your storage and applications. This guide documents key use cases for the management features of SFHA Solutions products:

Key use cases for SFHA Solutions products Table 1-1

Table 1 1 Rey ase eases for Strint Solutions products								
Use case	SFHA Solutions feature							
Improve DB2 and Sybase database performance using SFHA Solutions database	Quick I/O							
accelerators to enable your database to	Cached Quick I/O							
achieve the speed of raw disk while retaining the management features and convenience of a file system.	Concurrent I/O							
Protect your data using SFHA Solutions	FlashSnap							
Flashsnap, Storage Checkpoints, and NetBackup point-in-time copy methods to	Storage Checkpoints							
back up and recover your data.	NetBackup with SFHA Solutions							
Process your data off-host to avoid performance loss to your production hosts by using SFHA Solutions volume snapshots.	FlashSnap							
Optimize copies of your production database for test, decision modeling, and development purposes by using SFHA Solutions point-in-time copy methods.	FlashSnap							
Make file level point-in-time snapshots using SFHA Solutions space-optimized FileSnap when you need finer granualarity for your point-in-time copies than file systems or volumes. You can use FileSnap for cloning virtual machines.	FileSnap							
Maximize your storage utilization using SFHA Solutions SmartTier to move data to storage tiers based on age, priority, and access rate criteria.	SmartTier							
Convert your data from native OS to VxFS	Offline conversion utility							
using SFHA Solutions Portable Data Containers.	Online migration utility							
Convert your data from raw disk to VxFS: use SFHA Solutions Portable Data Containers.	Offline conversion utility							
Migrate your data from one platform to another (server migration) using SFHA Solutions Portable Data Containers.	Portable Data Containers							

Table 1-1 Key use cases for SFHA Solutions products (continued)

Use case	SFHA Solutions feature
Migrate your data across arraysusing SFHA Solutions Portable Data Containers.	Volume mirroring

Feature support across Veritas Storage Foundation and High Availability Solutions 6.0 products

Storage solutions and use cases are based on the shared management features of Veritas Storage Foundation and High Availability (SFHA) Solutions products. Clustering features are available separately through Veritas Cluster Server (VCS) as well as through the SFHA Solutions products.

Table 1-2 lists the features supported across SFHA Solutions products. Table 1-3 lists the high availability and disaster recovery features available in VCS.

Storage management features in SFHA Solutions products Table 1-2

Storage management feature	SF Basic	SF Std.	SF Ent.	SF Std. HA	SF Ent. HA	SFCFS HA	SFRAC	SVS	SF Syb CE
Veritas Extension for Oracle Disk Manager	Y	Y	Y	Y	Y	Y	Y	Y	N
Veritas Extension for Cached Oracle Disk Manager	Y	Y	Y	Y	Y	Y	N	Y	Y
Quick I/O	Y	Y	Y	Y	Y	Y	Y	Y	Y
Cached Quick I/O	Y	Y	Y	Y	Y	Y	Y	Y	Y
Concurrent I/O	Y	Y	Y	Y	Y	Y	Y	Y	Y
Compression	N	Y	Y	Y	Y	Y	Y	Y	Y
Deduplication	N	N	Y	N	Y	Y	Y	Y	Y
SmartMove	Y	Y	Y	Y	Y	Y	Y	Y	Y
SmartTier	N	Y	Y	Y	Y	Y	Y	Y	Y
SmartTier for Oracle	N	N	Y	Y	Y	Y	Y	N	N
Thin Reclamation	N	N	Y	Y	Y	Y	Y	Y	Y
Portable Data Containers	N	N	Y	Y	Y	Y	Y	Y	Y

Storage management features in SFHA Solutions products Table 1-2 (continued)

Storage management feature	SF Basic	SF Std.	SF Ent.	SF Std. HA	SF Ent. HA	SFCFS HA	SFRAC	svs	SF Syb CE
FlashSnap	N	N	Y	Y	Y	Y	Y	Y	Y
Database FlashSnap	N	N	Y	Y	Y	Y	Y	N	N
Storage Checkpoints	N	N	Y	Y	Y	Y	Y	Y	Y
Database Storage Checkpoints	N	N	Y	Y	Y	Y	Y	N	N
FileSnap	N	N	N	Y	Y	Y	Y	Y	Y
Volume replication	О	О	0	О	О	0	О	0	О
File replication	О	О	0	О	О	0	О	Y	О
Advanced support for virtual storage	Y	Y	Y	Y	Y	Y	N	N	N
Symantec Storage Plug-in for VMWare vCenter	Y	Y	Y	Y	Y	Y	Y	Y	Y
Clustering features for high availability (HA)	N	N	N	Y	Y	Y	Y	Y	Y
Disaster recovery features (HA/DR)	N	N	N	0	0	0	О	N	0

Table 1-3 Availability management features in SFHA Solutions products

Availability management feature	VCS	VCS HA/DR
Clustering for high availability (HA)	Y	Y
Database and application/ISV agents	Y	Y
Advanced failover logic	Y	Y
Data integrity protection with I/O fencing	Y	Y
Advanced virtual machines support	Y	Y
Virtual Business Services	Y	Y
Replication agents	N	Y
Replicated Data Cluster	N	Y
Stretch cluster	N	Y

Table 1-3	Availability management features in SFHA Solutions products
	(continued)

Availability management feature	VCS	VCS HA/DR
Campus cluster	N	Y
Global clustering (GCO)	N	Y
Fire Drill	N	Y

Legend:

- Y=Feature is included in the product license.
- O=Feature is not included in the product license but may be licensed separately.
- N=Feature is not supported with the product license.

Notes:

- The Veritas File Replicator license includes file replication.
- The Veritas Replicator license includes both file replication and volume replication (also known as Veritas Volume Replicator, VVR).
- SmartTier is an expanded and renamed version of Dynamic Storage Tiering (DST).
- All features listed in Table 1-2 and Table 1-3 are supported on Solaris. Consult specific product documentation for information on supported operating systems.

Using SmartMove and Thin Provisioning with DB2 and **Sybase**

You can use SmartMove and Thin Provisioning with Veritas Storage Foundation and High Availability products and your DB2 or Sybase database.

When data files are deleted, you can reclaim the storage space used by these files if the underlying devices are thin reclaimable LUNs.

For information about the Storage Foundation Thin Reclamation feature, see the Veritas Storage Foundation Administrator's Guide.

Finding Veritas Storage Foundation and High **Availability Solutions management feature** information

The following Veritas Storage Foundation and High Availability Solutions management features are illustrated with use case examples in this guide:

- Improving database performance for DB2 and Sybase
- Backing up and recovering your data
- Processing data off-host
- Optimizing test and development environments
- Maximizing storage utilization
- Converting your data from native OS to VxFS
- Converting your data from raw disk to VxFS
- Migrating your data from one platform to another (server migration)
- Migrating your data across arrays

For Veritas Storage Foundations and High Availibitlity Solutions management features concept and administrative information, see the following guides:

- Veritas Storage Foundation™ Administrator's Guide
- Veritas Storage Foundation[™] for Cluster File System High Availability Administrator's Guide.
- Veritas Storage Foundation™ for Oracle RAC Administrator's Guide.
- Veritas Storage Foundation™ for Sybase ASE CE Administrator's Guide.

For Information on using Veritas Storage Foundations and High Availibitlity Solutions management features with Oracle databases, see: Veritas Storage Foundation™: Storage and Availability Management for Oracle Databases.

For Information on using Veritas Storage Foundations and High Availibitlity Solutions replication features, see: Veritas Storage Foundation and High Availability Solutions Replication Guide

Section

Improving database performance

- Chapter 2. Overview of database accelerators
- Chapter 3. Improving database performance with Veritas Quick I/O
- Chapter 4. Improving database performance with Veritas Cached Quick I/O
- Chapter 5. Improving database performance with Veritas Concurrent I/O

Chapter 2

Overview of database accelerators

This chapter includes the following topics:

 About Storage Foundation and High Availability Solutions products database accelerators

About Storage Foundation and High Availability Solutions products database accelerators

The major concern in any environment is maintaining respectable performance or meeting performance service level agreements (SLAs). Veritas Storage Foundation products improve the overall performance of database environments in a variety of ways.

- Quick I/O (QIO) and cached Quick I/O (CQIO) optimized for all database environments
- Concurrent I/O (CIO) optimized for DB2 and Sybase environments
- Oracle Disk Manager (ODM) and Cached Oracle Disk Manager (CODM) optimized specifically for Oracle environments

These database accelerator technologies enable database performance equal to raw disk partitions, but with the manageability benefits of a file system. With the Dynamic Multi-pathing (DMP) feature of Storage Foundation, performance is maximized by load-balancing I/O activity across all available paths from server to array. DMP supports all major hardware RAID vendors, hence there is no need for third-party multi-pathing software, reducing the total cost of ownership.

Storage Foundation database accelerators enable you to manage performance for your database with more precision.

- To achieve raw device performance for databases run on VxFS file systems, use Veritas Quick I/O.
- To further enhance database performance by leveraging large system memory to selectively buffer the frequently accessed data, use Veritas Cached Quick I/O.
- To achieve improved performance for DB2 or Sybase databases run on VxFS file systems, without restrictions on increasing file size, use Veritas Concurrent I/O.
- To improve Oracle performance and manage system bandwidth through an improved Application Programming Interface (API) that contains advanced kernel support for file I/O, use Veritas Oracle Disk Manager (ODM).
- To enable selected I/O to use caching to improve ODM I/O performance, use Veritas Extension for Cached Oracle Disk Manager (Cached ODM).

Chapter 3

Improving database performance with Veritas Quick I/O

This chapter includes the following topics:

- About Quick I/O
- How to set up Quick I/O
- Creating DB2 database containers or Sybase files as Quick I/O files using qiomkfile
- Preallocating space for Quick I/O files using the setext command
- Accessing regular VxFS files as Quick I/O files
- About sparse files
- Displaying Quick I/O status and file attributes
- Extending a Quick I/O file in a DB2 or Sybase environment
- Monitoring tablespace free space with DB2 and extending tablespace containers
- Creating Quick I/O files in Solaris local zone
- Disabling Quick I/O

About Quick I/O

Veritas Quick I/O is a VxFS feature included in Veritas Storage Foundation Standard and Enterprise products that enables applications access preallocated VxFS files as raw character devices. Quick I/O provides the administrative benefits of running databases on file systems without the typically associated degradation in performance.

How Quick I/O works

Veritas Quick I/O supports direct I/O and kernel asynchronous I/O and enables dataservers to access regular files on a VxFS file system as raw character devices.

The benefits of using Quick I/O are:

- Improved performance and processing throughput by having Quick I/O files act as raw devices.
- Ability to manage Quick I/O files as regular files, which simplifies administrative tasks such as allocating, moving, copying, resizing, and backing up DB2 containers.
- Ability to manage Quick I/O files as regular files, which simplifies administrative tasks such as allocating, moving, copying, resizing, and backing up Sybase dataservers.

How Quick I/O improves database performance

The benefits of using Quick I/O are:

- Improved performance and processing throughput by having Quick I/O files act as raw devices.
- Ability to manage Quick I/O files as regular files, which simplifies administrative tasks such as allocating, moving, copying, resizing, and backing up DB2 containers.
- Ability to manage Quick I/O files as regular files, which simplifies administrative tasks such as allocating, moving, copying, resizing, and backing up Sybase dataservers.

Quick I/O's ability to access regular files as raw devices improves database performance by:

Table 3-1

Table 3-1		
Quick I/O feature	Advantage	
Supporting direct I/O	I/O on files using read() and write() system calls typically results in data being copied twice: once between user and kernel space, and later between kernel space and disk. In contrast, I/O on raw devices is direct. That is, data is copied directly between user space and disk, saving one level of copying. As with I/O on raw devices, Quick I/O avoids extra copying.	
Avoiding kernel write locks on database files	When database I/O is performed using the write() system call, each system call acquires and releases a write lock inside the kernel. This lock prevents multiple simultaneous write operations on the same file. Because database systems usually implement their own locking to manage concurrent access to files, per file writer locks unnecessarily serialize I/O operations. Quick I/O bypasses file system per file locking and lets the database server control data access.	
Avoiding double buffering	Most database servers maintain their own buffer cache and do not need the file system buffer cache. Database data cached in the file system buffer is therefore redundant and results in wasted memory and extra system CPU utilization to manage the buffer. By supporting direct I/O, Quick I/O eliminates double buffering. Data is copied directly between the relational database management system (RDBMS) cache and disk, which lowers CPU utilization and frees up memory that can then be used by the database server buffer cache to further improve transaction processing throughput.	

Table 3-1(continued)

Quick I/O feature	Advantage
Supporting AIX Fastpath asynchronous I/O	AIX Fastpath asynchronous I/O is a form of I/O that performs non-blocking system level reads and writes, allowing the system to handle multiple I/O requests simultaneously. Operating systems such as AIX provide support for asynchronous I/O on raw devices, but not on regular files. As a result, even if the database server is capable of using asynchronous I/O, it cannot issue asynchronous I/O requests when the database runs on file systems. Lack of asynchronous I/O significantly degrades performance. Quick I/O lets the database server take advantage of kernel-supported asynchronous I/O on file system files accessed using the Quick I/O interface.
Supporting asynchronous I/O	HP-UX asynchronous I/O is a form of I/O that performs non-blocking system level reads and writes, allowing the system to handle multiple I/O requests simultaneously. Operating systems such as HP-UX provide kernel support for asynchronous I/O on raw devices, but not on regular files. As a result, even if the database server is capable of using asynchronous I/O, it cannot issue asynchronous I/O requests when the database runs on file systems. Lack of asynchronous I/O significantly degrades performance. Quick I/O enables the database server to take advantage of kernel-supported asynchronous I/O on file system files accessed using the Quick I/O interface.

(continued) Table 3-1

Quick I/O feature	Advantage
Supporting kernel asynchronous I/O	Solaris kernel asynchronous I/O is a form of I/O that performs non-blocking system level reads and writes, allowing the system to handle multiple I/O requests simultaneously. Operating systems such as Solaris provide kernel support for asynchronous I/O on raw devices, but not on regular files. As a result, even if the database server is capable of using asynchronous I/O, it cannot issue asynchronous I/O requests when the database runs on file systems. Lack of asynchronous I/O significantly degrades performance. Quick I/O enables the database server to take advantage of kernel-supported asynchronous I/O on file system files accessed using the Quick I/O interface.

How to set up Quick I/O

Quick I/O is included in the VxFS package shipped with Veritas Storage Foundation Standard and Enterprise products. By default, Quick I/O is enabled when you mount a VxFS file system.

If Quick I/O is not available in the kernel, or a Veritas Storage Foundation Standard or Enterprise product license is not installed, a file system mounts without Quick I/O by default, the Quick I/O file name is treated as a regular file, and no error message is displayed. If, however, you specify the -o qio option, the mount command prints the following error message and terminates without mounting the file system.

```
VxFDD: You don't have a license to run this program
vxfs mount: Quick I/O not available
```

Depending on whether you are creating a new database or are converting an existing database to use Quick I/O, you have the following options:

If you are creating a new database to use Quick I/O:

- You can use the giomkfile command to preallocate space for database files and make them accessible to the Quick I/O interface.
- You can use the setext command to preallocate space for database files and create the Quick I/O files.

If you are converting an existing database:

■ You can create symbolic links for existing VxFS files, and use these symbolic links to access the files as Quick I/O files.

Creating DB2 database containers or Sybase files as Quick I/O files using qiomkfile

The best way to preallocate space for tablespace containers and to make them accessible using the Quick I/O interface is to use the giomkfile. You can use the giomkfile to create the Quick I/O files for either temporary or permanent tablespaces.

For DB2, you can create Database Managed Space (DMS) containers with the type 'DEVICE' using Quick I/O.

Vou can create Quick I/O files only on VyFS file systems

•	You must have read/write permissions on the directory in which you intend to create database Quick I/Ofiles.
Usage notes ■	The qiomkfile command creates two files: a regular file with preallocated, contiguous space, and a file that is a symbolic link pointing to the Quick I/O name extension. See the qiomkfile(1M) manual page for more information.
fi H	Creates a symbolic link with an absolute path name for a specified ile. Use the —a option when absolute path names are required. However, the default is to create a symbolic link with a relative path name.
S	extends a file by a specified amount to allow tablespace resizing. See "Extending a Quick I/O file in a DB2 or Sybase environment" on page 44.
-r In	ncreases the file to a specified size to allow DB tablespace resizing. See "Extending a Quick I/O file in a DB2 or Sybase environment" on page 44.

Creating DB2 database containers or Sybase files as Quick I/O files using qiomkfile

Specifies the space to preallocate for a file in bytes, kilobytes, megabytes, gigabytes, or sectors (512 bytes) by adding a k, K, m, M, g, G, s, or S suffix. The default is bytes—you do not need to attach a suffix to specify the value in bytes. The size of the file that is preallocated is the total size of the file (including the header) rounded to the nearest multiple of the file system block size.

-s

Warning: Exercise caution when using absolute path names. Extra steps may be required during database backup and restore procedures to preserve symbolic links. If you restore files to directories different from the original paths, you must change the symbolic links that use absolute path names to point to the new path names before the database is restarted.

To create a DB2 container as a Quick I/O file using giomkfile

Create a Quick I/O-capable file using the giomkfile command:

```
# /opt/VRTS/bin/qiomkfile -s file size /mount point/filename
```

For example, to show how to create a 100MB Quick I/O-capable file named dbfile on the VxFS file system /db01 using a relative path name:

```
# /opt/VRTS/bin/qiomkfile -s 100m /db01/dbfile
# ls -al
-rw-r--r--
           1 db2inst1 db2iadm1 104857600 Oct 2 13:42 .dbfile
lrwxrwxrwx 1 db2inst1 db2iadm1 19 Oct 2 13:42 dbfile -> \
.dbfile::cdev:vxfs:
```

2 Create tablespace containers using this file with the following SQL statements:

```
$ db2 connect to database
$ db2 create tablespace tbsname managed by database using \
( DEVICE /mount point/filename size )
$ db2 terminate
```

In the example from 1, giomkfile creates a regular file named /db01/dbfile, which has the real space allocated. Then, giomkfile creates a symbolic link named /db01/dbfile. This symbolic link is a relative link to the Quick I/O interface for /db01/.dbfile.that is, to the .dbfile::cdev:vxfs: file. The symbolic link allows .dbfile to be accessed by any database or application using its Quick I/O interface.

We can then add the file to the DB2 database PROD:

```
$ db2 connect to PROD
$ db2 create tablespace NEWTBS managed by database using \
( DEVICE '/db01/dbfile' 100m )
$ db2 terminate
```

To create a Sybase database file as a Quick I/O file using qiomkfile

- Create a database file using the qiomkfile command:
 - # /opt/VRTS/bin/qiomkfile -s file size /mount point/filename

For example, to show how to create a 100MB database file named dbfile on the VxFS file system /db01 using a relative path name:

```
# /opt/VRTS/bin/qiomkfile -s 100m /db01/dbfile
```

\$ ls -al

```
-rw-r--r--
          1 sybase
                   sybase
                           104857600
                                     Oct 2 13:42
                                                  .dbfile
lrwxrwxrwx 1 sybase sybase 19 Oct 2 13:42
                                                 dbfile -> \
.dbfile::cdev:vxfs:
```

Creating DB2 database containers or Sybase files as Quick I/O files using giomkfile

Add a device to the Sybase dataserver device pool for the Quick I/O file using the disk init command:

```
$ isql -Usa -Psa password -Sdataserver name
> disk init
> name="device name",
> physname="/mount point/filename",
> vdevno="device number",
> size=51200
> qo
> alter database production on new device=file size
```

The size is in 2K units. The Enterprise Reference manual contains more information on the disk init command.

In the example from 1, qiomkfile creates a regular file named /db01/.dbfile, which has the real space allocated. Then, giomkfile creates a symbolic link named /db01/dbfile. The symbolic link is a relative link to the Quick I/O interface for /db01/.dbfile, that is, to the .dbfile::cdev:vxfs: file. The symbolic link allows .dbfile to be accessed by any database or application using its Quick I/O interface.

The device size is a multiple of 2K pages. In the example, 51200 times 2K pages is 104857600 bytes. The giomkfile command must use this size.

An example to show how to add a 100MB Quick I/O file named dbfile to the list of devices used by database production, using the disk init command:

```
$ isql -Usa -Psa_password -Sdataserver_name
> disk init
> name="new device",
> physname="/db01/dbfile",
> vdevno="device number",
> size=51200
> alter database production on new device=100
> go
```

See the Sybase Adaptive Server Enterprise Reference Manual.

Use the file to create a new segment or add to an existing segment.

To add a new segment:

```
$ isql -Usa -Psa password -Sdataserver name
> sp addsegment new segment, db name, device name
> ao
```

To extend a segment:

Usage notes

```
$ isql -Usa -Psa password -Sdataserver name
> sp extendsegment segment name, db name, device name
> go
```

An example to show how to create a new segment, named segment2, for device dbfile on database production:

```
$ isql -Usa_password -Sdataserver_name
> sp addsegment segment2, production, dbfile
> go
```

An example to show how to extend a segment, named segment1, for device dbfile on database production:

```
$ isql -Usa password -Sdataserver name
> sp extendsegment segment1, production, dbfile
> go
```

See the Sybase Adaptive Server Enterprise Reference Manual.

Preallocating space for Quick I/O files using the setext command

As an alternative to using the giomkfile command, you can also use the VxFS setext command to preallocate space for database files.

Before preallocating space with setext, make sure the following conditions have been met:

Prerequisites ■ The setext command requires superuser (root) privileges.

■ You can use the chown command to change the owner and group permissions on the file after you create it. See the setext (1M) manual page for more information.

To create a Quick I/O database file using setext

- Access the VxFS mount point and create a file:
 - # cd /mount point
 - # touch .filename
- 2 Use the setext command to preallocate space for the file:

```
# /opt/VRTS/bin/setext -r size -f noreserve -f chgsize \
.filename
```

3 Create a symbolic link to allow databases or applications access to the file using its Quick I/O interface:

```
# ln -s .filename::cdev:vxfs: filename
```

4 Change the owner and group permissions on the file.

```
For example, for DB2:
```

```
# chown db2inst1:db2iadm1 .filename
```

chmod 660 .dbfile

For example, for Sybase:

```
# chown sybase:sybase .filename
```

- # chmod 660 .filename
- To access the mountpoint for the database:

For example, for /db01, create a container, preallocate the space, and change the permissions:

```
# cd /db01
# touch .dbfile
# /opt/VRTS/bin/setext -r 100M -f noreserve -f chqsize .dbfile
# ln -s .dbfile::cdev:vxfs: dbfile
For DB2:
# chown db2inst1:db2iadm1 .dbfile
# chmod 660 .dbfile
For Sybase:
# chown sybase:sybase .dbfile
# chmod 660 .dbfile
```

Accessing regular VxFS files as Quick I/O files

You can access regular VxFS files as Quick I/O files using the ::cdev:vxfs:name extension.

While symbolic links are recommended because they provide easy file system management and location transparency of database files, the drawback of using symbolic links is that you must manage two sets of files (for instance, during database backup and restore).

Usage notes

■ If possible, use relative path names instead of absolute path names when creating symbolic links to access regular files as Quick I/O files. Using relative path names prevents copies of the symbolic link from referring to the original file when the directory is copied. This is important if you are backing up or moving database files with a command that preserves the symbolic link. However, some applications require absolute path names. If a file is then relocated to another directory, you must change the symbolic link to use the new absolute path. Alternatively, you can put all the symbolic links in a directory separate from the data directories. For example, you can create a directory named /database and put all the symbolic links there, with the symbolic links pointing to absolute path names.

To access an existing regular file as a Quick I/O file on a VxFS file system

Access the VxFS file system mount point containing the regular files:

```
$ cd /mount point
```

Create the symbolic link: 2

```
$ mv filename .filename
$ ln -s .filename::cdev:vxfs: filename
```

This example shows how to access the VxFS file dbfile as a Quick I/O file:

```
$ cd /db01
$ mv dbfile .dbfile
$ ln -s .dbfile::cdev:vxfs: dbfile
```

This example shows how to confirm the symbolic link was created:

```
$ ls -lo .dbfile dbfile
```

For DB2:

```
-rw-r--r- 1 db2inst1 104890368 Oct 2 13:42 .dbfile
lrwxrwxrwx 1 db2inst1 19 Oct 2 13:42 dbfile ->
.dbfile::cdev:vxfs:
```

For Sybase:

```
$ ls -lo .dbfile dbfile
```

```
-rw-r--r-- 1 sybase 104890368 Oct 2 13:42 .dbfile
lrwxrwxrwx 1 sybase 19 Oct 2 13:42 dbfile ->
.dbfile::cdev:vxfs:
```

About sparse files

Support for sparse files lets applications store information (in inodes) to identify data blocks that have only zeroes, so that only blocks containing non-zero data have to be allocated on disk.

For example, if a file is 10KB, it typically means that there are blocks on disk covering the whole 10KB. Assume that you always want the first 9K to be zeroes. The application can go to an offset of 9KB and write 1KB worth of data. Only a block for the 1KB that was written is allocated, but the size of the file is still 10KB.

The file is now sparse. It has a hole from offset 0 to 9KB. If the application reads any part of the file within this range, it will see a string of zeroes.

If the application subsequently writes a 1KB block to the file from an offset of 4KB, for example, the file system will allocate another block.

The file then looks like:

- 0-4KB hole
- 4-5KB data block
- 5-9KB hole
- 9-10KB data block

So a 1TB file system can potentially store up to 2TB worth of files if there are sufficient blocks containing zeroes. Quick I/O files cannot be sparse and will always have all blocks specified allocated to them.

Displaying Quick I/O status and file attributes

You can obtain and display information about Quick I/O status and file attributes using various options of the 1s command:

-al	Lists all files on a file system, including Quick I/O files and their links.
-----	--

Shows if Quick I/O was successfully installed and enabled. -1L

-a1L Shows how a Quick I/O file name is resolved to that of a raw device.

To list all files on the current file system, including Quick I/O files and their links

◆ Use the ls -al command with the file names:

\$ ls -al filename .filename

The following example shows how to use the -a option to display the absolute path name created using qiomkfile:

```
$ ls -al d* .d*
```

For DB2:

```
-rw-r--r- 1 db2inst1 db2iadm1 104890368 Oct 2 13:42 .dbfile
lrwxrwxrwx 1 db2inst1 db2iadm1 19 Oct 2 13:42 dbfile ->
 .dbfile::cdev:vxfs:
```

For Sybase:

```
-rw-r--r- 1 sybase sybase 104890368 Oct 2 13:42 .dbfile
lrwxrwxrwx 1 sybase sybase 19 Oct 2 13:42 dbfile ->
 .dbfile::cdev:vxfs:
```

To determine if a Sybase segment has been converted to Quick I/O

♦ Use the ls command as follows:

```
$ ls -lL filename
```

The following example shows how to determine if Quick I/O is installed and enabled:

```
$ ls -lL dbfile
crw-r--r-- 1 sybase dba 45, 1 Oct 2 13:42 dbfile
```

To show a Quick I/O file resolved to a raw device

Use the 1s command with the file names as follows:

\$ ls -alL filename .filename

The following example shows how the Quick I/O file name dbfile is resolved to that of a raw device:

\$ ls -alL d* .d*

For DB2:

-rw-rr	1 db2inst1	db2iadm1	104890368	Oct 2 13:42	.dbfile
For Sybase:					
crw-rr	1 sybase	sybase	45, 1	Oct 2 13:42	dbfile
-rw-rr	1 sybase	sybase	104890368	Oct 2 13:42	.dbfile

crw-r--r-- 1 db2inst1 db2iadm1 45, 1 Oct 2 13:42 dbfile

Extending a Quick I/O file in a DB2 or Sybase environment

Although Quick I/O files must be preallocated, they are not limited to the preallocated sizes. You can grow or "extend" a Quick I/O file by a specific amount or to a specific size, using options to the giomkfile command. Extending Quick I/O files is a fast, online operation and offers a significant advantage over using raw devices.

Before extending a Quick I/O file, make sure the following conditions have been met:

Prerequisites

■ You must have sufficient space on the file system to extend the Quick I/O file.

Usage notes

- You can also grow VxFS file systems online (provided the underlying disk or volume can be extended) using the fsadm command. You can expand the underlying volume and the filesystem with the vxresize command.
- You must have superuser (root) privileges to resize VxFS file systems using the fsadm command.
- For Sybase: although you have the ability to extend a Quick I/O file, you cannot resize a database device in Sybase once it is initialized. However, with the ability to grow the volumes and file systems online, you can easily allocate new database devices to be used for new segments and to extend existing segments.
- See the fsadm vxfs (1M) and giomkfile (1M) manual pages for more information.

The following options are available with the giomkfile command:

- Extends the file by a specified amount to allow resizing. -е
- Increases the file to a specified size to allow resizing.

To extend a Quick I/O file

If required, ensure the underlying storage device is large enough to contain a larger VxFS file system (see the vxassist(1M) manual page for more information), and resize the VxFS file system using fsadm command:

For Sybase, for example:

/opt/VRTS/bin/fsadm -b newsize /mount point

where:

- -b is the option for changing size
- *newsize* is the new size of the file system in bytes, kilobytes, megabytes, blocks, or sectors

- *mount point* is the file system's mount point
- Extend the Quick I/O file using the giomkfile command:

```
# /opt/VRTS/bin/qiomkfile -e extend amount /mount point/filename
or
```

/opt/VRTS/bin/qiomkfile -r newsize /mount point/filename

An example to show how to grow VxFS file system:

/db01 to 500MB and extend the tbs1 cont001 Quick I/O file by 20MB:

- # /opt/VRTS/bin/qiomkfile -e 20M /db01/tbs1 cont001
- # /opt/VRTS/bin/fsadm -b 500M /db01

An example to show how to grow VxFS file system for DB2:

/db01 to 500MB and resize the tbs1 cont001 Quick I/O file to 300MB:

- # /opt/VRTS/bin/fsadm -b 500M /db01
- # /opt/VRTS/bin/qiomkfile -r 300M /db01/tbs1 cont001

An example to show how to grow VxFS file system for Sybase:

/db01 to 500MB and resize the dbfile Quick I/O file to 300MB:

- # /opt/VRTS/bin/fsadm -b 500M /db01
- # /opt/VRTS/bin/qiomkfile -r 300M /db01/dbfile

Monitoring tablespace free space with DB2 and extending tablespace containers

DB2 does not automatically make use of extended DMS files. When tablespace space needs to be extended, a number of DB2 commands must be run. Unlike raw devices, a Database Administrator can easily extend Quick I/O files online. Using this method, a Database Administrator can monitor the free space available in the DB2 tablespaces and use the qiomkfile command to grow the Quick I/O files online as needed (typically when the file is about 80 to 90% full). This method does not require you to lock out unused disk space for Quick I/O files. The free space on the file system is available for use by other applications.

Before extending tablespaces, make sure the following conditions have been met:

Prerequisites

■ Log on as the DB2 instance owner.

Usage notes

- Monitor the free space available in the Quick I/O file, and grow the file as necessary with the giomkfile command.
- A Database Administrator can grow underlying VxFS file systems online (provided the underlying disk or volume can be extended) using the fsadm command. See the fsadm (1M) manual page for more information.
- It is strongly recommended that if a DB2 tablespace is running out of space, that all containers are grown by the same amount. It is possible to add extra containers to the tablespace, but this results in DB2 performing a relayout of the data to balance usage across all available containers in the tablespace.

Also refer to the DB2 Administration Guide section on Managing Storage and the DB2 SQL Reference Guide for information on the ALTER TABLESPACE command.

To monitor the free space available in a DB2 tablespace

- Use the following DB2 commands:
 - \$ db2 connect to database
 - \$ db2 list tablespaces show detail
 - \$ db2 terminate

To extend a Quick I/O file using giomkfile

- Use the giomkfile command to extend the Quick I/O file (if the container is running low on free blocks):
 - # /opt/VRTS/bin/qiomkfile -e extend amount filename

To extend a DB2 tablespace by a fixed amount

- Use the following DB2 commands:
 - \$ db2 connect to database
 - \$ db2 alter tablespace tablespace-name extend (ALL amount)
 - \$ db2 terminate

This example shows how to monitor the free space on the tablespaces in database PROD:

- \$ db2 connect to PROD
- \$ db2 list tablespaces show detail
- \$ db2 terminate

This example shows how to extend the three DB2 containers owned by tablespace EMP by 500MB using the giomkfile command:

- # /opt/VRTS/bin/qiomkfile -e 500M tbsEMP cont001
- # /opt/VRTS/bin/qiomkfile -e 500M tbsEMP_cont002
- # /opt/VRTS/bin/qiomkfile -e 500M tbsEMP cont003

This example shows how to notify DB2 that all containers in tablespace EMP have grown by 500MB:

- \$ db2 connect to PROD
- \$ db2 alter tablespace EMP extend (ALL 500M)
- \$ db2 terminate

This example shows how to verify the newly allocated space on the tablespace EMP in database PROD:

- \$ db2 connect to PROD
- \$ db2 list tablespaces show detail
- \$ db2 terminate

Creating Quick I/O files in Solaris local zone

Quick I/O files cannot be created in the Solaris local zones. This is because the VxFS command qiomkfile cannot run in the Solaris local zone.

You must use the following workaround procedure to create Quick I/O files in Solaris local zone. You must perform the following commands as root unless otherwise stated.

To create Quick I/O files in Solaris local zone

Install VRTSodm on the Solaris global zone.

You have to perform this step once on your system. You do not have to repeat it for each local zone.

Install your Storage Foundation product license on the Solaris global zone.

You need to perform this step once on your system. You do not need to repeat it for each local zone.

Export the license from the Solaris global zone to each Solaris local zone where you plan to use Quick I/O.

To do so, enter the following sequence of commands:

```
zonecfg -z <zone name>
```

For example, if the Solaris local zone name is **zone2**, then:

```
# zonecfg -z zone2
```

```
zonecfg:zone2> add fs
zonecfg:zone2:fs> set dir=/etc/vx/licenses/lic
zonecfg:zone2:fs> set special=/etc/vx/licenses/lic
zonecfg:zone2:fs> set type=lofs
zonecfg:zone2:fs> end
zonecfg:zone2> verify
zonecfg:zone2> commit
zonecfq:zone2> exit
```

In each local zone, mount the **odm** device to /dev/odm.

To do so, use the following command in the Solaris global zone:

```
# mkdir /zones/<zone name>/dev/odm
```

Then use the following command in the Solaris local zone:

```
# mount -F odm /dev/odm /dev/odm
```

For example, if the Solaris local zone name is zone2, you must use the following commands:

```
# mkdir /zones/zone2/dev/odm
# mount -F odm /dev/odm /dev/odm
```

As DBA, create a Quick I/O file in a Solaris local zone utilizing /opt/VRTS/bin/odmmkfile. Rename the file to a Quick I/O file.

To do so, enter the following sequence of commands:

```
# su - <DBA>
# cd <target dir>
# /opt/VRTS/bin/odmmkfile -s <size> filename
# mv filename .filename
# ln -s .filename::cdev:vxfs: filename
# chown <DBA> .filename
```

Disabling Quick I/O

Before disabling Quick I/O, make sure the following condition has been met:

Prerequisite The file system you are planning to remount must be located in the /etc/vfstab file.

If you need to disable the Quick I/O feature, you first need to convert any Quick I/O files back to regular VxFS files. Then, remount the VxFS file system using a special mount option.

To disable Quick I/O for DB2

- If the database is active, make it inactive by either shutting down the instance or disabling user connections.
- To remount the file system with Quick I/O disabled, use the mount -o nogio command as follows:
 - # /opt/VRTS/bin/mount -F vxfs -o remount,noqio /mount_point

To disable Quick I/O for Sybase

- If the database is running, shut it down.
- To remount the file system with Quick I/O disabled, use the mount o noqiocommand as follows:
 - # /opt/VRTS/bin/mount -F vxfs -o remount,noqio /mount_point

Chapter 4

Improving database performance with Veritas Cached Quick I/O

This chapter includes the following topics:

- About Cached Quick I/O
- Tasks for setting up Cached Quick I/O
- Enabling Cached Quick I/O on a file system
- Determining candidates for Cached Quick I/O
- Enabling and disabling Cached Quick I/O for individual files

About Cached Quick I/O

Veritas Cached Quick I/O maintains and extends the database performance benefits of Veritas Quick I/O by making more efficient use of large, unused system memory through a selective buffering mechanism. Cached Quick I/O also supports features that support buffering behavior, such as file system read-ahead.

How Cached Quick I/O works in a DB2 environment

Cached Quick I/O is a specialized external caching mechanism suitable for dynamically changing memory allocation available for caching DB2 tablespace data. Cached Quick I/O can be selectively applied to containers that are suffering an undesirable amount of physical disk I/O due to insufficient DB2 BufferPool reservation. Cached Quick I/O works by taking advantage of the available physical memory that is left over after the operating system reserves the amount it needs

and the DB2 BufferPools have been sized to their normal operating capacity. This extra memory serves as a cache to store file data, effectively serving as a second-level cache backing the BufferPool(s).

For example, consider a system configured with 12GB of physical memory, an operating system using 1GB, and a total DB2 BufferPool size of 3.5GB. Unless you have other applications running on your system, the remaining 7.5GB of memory is unused. If you enable Cached Quick I/O, these remaining 7.5GB become available for caching database files.

Note: You cannot allocate specific amounts of the available memory to Cached Quick I/O. When enabled, Cached Quick I/O takes advantage of available memory.

Cached Quick I/O is not beneficial for all containers in a database. Turning on caching for all database containers can degrade performance due to extra memory management overhead (double buffer copying). You must use file I/O statistics to determine which individual database containers benefit from caching, and then enable or disable Cached Quick I/O for individual containers.

If you understand the applications that generate load on your database and how this load changes at different times during the day, you can use Cached Quick I/O to maximize performance. By enabling or disabling Cached Quick I/O on a per-container basis at different times during the day, you are using Cached Quick I/O to dynamically tune the performance of a database.

For example, files that store historical data are not generally used during normal business hours in a transaction processing environment. Reports that make use of this historical data are generally run during off-peak hours when interactive database use is at a minimum. During normal business hours, you can disable Cached Quick I/O for database files that store historical data in order to maximize memory available to other user applications. Then, during off-peak hours, you can enable Cached Quick I/O on the same files when they are used for report generation. This will provide extra memory resources to the database server without changing any database configuration parameters. Enabling file system read-ahead in this manner and buffering read data can provide great performance benefits, especially in large sequential scans.

You can automate the enabling and disabling of Cached Quick I/O on a per-container basis using scripts, allowing the same job that produces reports to tune the file system behavior and make the best use of system resources. You can specify different sets of containers for different jobs to maximize file system and database performance.

Note: Modifying Cached Quick I/O settings does not require any database level changes. So, unlike modifying existing database global memory or bufferpool settings, Cached Quick I/O does not require the database to be restarted for changes to take effect.

How Cached Quick I/O works in a Sybase environment

Cached Quick I/O is a specialized external caching mechanism specifically suitable to 32-bit ports of the Sybase server. Cached Quick I/O can be used on 64-bit ports of the Sybase server, but the benefits are not as great. Cached Quick I/O can be selectively applied to datafiles that are suffering an undesirable amount of physical disk I/O due to insufficient dataserver buffer caches. Cached Quick I/O works by taking advantage of the available physical memory that is left over after the operating system reserves the amount it needs and the Sybase dataserver buffer cache has been sized to the maximum capacity allowed within a 32-bit virtual address space. This extra memory serves as a cache to store file data, effectively serving as a second-level cache backing the dataserver buffer caches.

For example, consider a system configured with 12GB of physical memory, an operating system using 1GB, and a total Sybase size of 3.5GB. Unless you have other applications running on your system, the remaining 7.5GB of memory is unused. If you enable Cached Quick I/O, these remaining 7.5GB become available for caching database files.

Note: You cannot allocate specific amounts of the available memory to Cached Quick I/O. When enabled, Cached Quick I/O takes advantage of available memory.

Cached Quick I/O is not beneficial for all device files in a database. Turning on caching for all database device files can degrade performance due to extra memory management overhead (double buffer copying). You must use file I/O statistics to determine which individual database device files benefit from caching, and then enable or disable Cached Quick I/O for individual device files.

If you understand the applications that generate load on your database and how this load changes at different times during the day, you can use Cached Quick I/O to maximize performance. By enabling or disabling Cached Quick I/O on a per-file basis at different times during the day, you are using Cached Quick I/O to dynamically tune the performance of a database.

For example, files that store historical data are not generally used during normal business hours in a transaction processing environment. Reports that make use of this historical data are generally run during off-peak hours when interactive database use is at a minimum. During normal business hours, you can disable

Cached Quick I/O for database files that store historical data in order to maximize memory available to other user applications. Then, during off-peak hours, you can enable Cached Quick I/O on the same files when they are used for report generation. This will provide extra memory resources to the database server without changing any database configuration parameters. Enabling file system read-ahead in this manner and buffering read data can provide great performance benefits, especially in large sequential scans.

You can automate the enabling and disabling of Cached Quick I/O on a per-file basis using scripts, allowing the same job that produces reports to tune the file system behavior and make the best use of system resources. You can specify different sets of files for different jobs to maximize file system and database performance.

How Cached Quick I/O improves database performance

Enabling Cached Quick I/O on suitable Quick I/O files improves database performance by using the file system buffer cache to store data. This data storage speeds up system reads by accessing the system buffer cache and avoiding disk I/O when searching for information.

Having data at the cache level improves database performance in the following ways:

- For read operations, Cached Quick I/O caches database blocks in the system buffer cache, which can reduce the number of physical I/O operations and therefore improve read performance.
- For write operations, Cached Ouick I/O uses a direct-write, copy-behind technique to preserve its buffer copy of the data. After the direct I/O is scheduled and while it is waiting for the completion of the I/O, the file system updates its buffer to reflect the changed data being written out. For online transaction processing, Cached Quick I/O achieves better than raw device performance in database throughput on large platforms with very large physical memories.
- For sequential table scans, Cached Quick I/O can significantly reduce the query response time because of the read-ahead algorithm used by Veritas File System. If a user needs to read the same range in the file while the data is still in cache, the system is likely to return an immediate cache hit rather than scan for data on the disk.

Tasks for setting up Cached Quick I/O

To set up and use Cached Quick I/O, you should do the following in the order in which they are listed:

- Enable Cached Quick I/O on the underlying file systems used for your database.
- Exercise the system in your production environment to generate file I/O statistics.
- Collect the file I/O statistics while the files are in use.
- Analyze the file I/O statistics to determine which files benefit from Cached Quick I/O.
- Disable Cached Quick I/O on files that do not benefit from caching.

Enabling Cached Quick I/O on a file system

Cached Quick I/O depends on Veritas Quick I/O running as an underlying system enhancement in order to function correctly. Follow the procedures listed here to ensure that you have the correct setup to use Cached Quick I/O successfully.

Prerequisites

- You must have permission to change file system behavior using the vxtunefs command to enable or disable Cached Quick I/O. By default, you need superuser (root) permissions to run the vxtunefs command, but other system users do not.
- You must enable Ouick I/O on the file system. Ouick I/O is enabled automatically at file system mount time.

If you have correctly enabled Quick I/O on your system, you can proceed to enable Cached Quick I/O as follows:

- Set the file system Cached Quick I/O flag, which enables Cached Quick I/O for all files in the file system.
- Setting the file system Cached Quick I/O flag enables caching for all files in the file system. You must disable Cached Quick I/O on individual Quick I/O files that do not benefit from caching to avoid consuming memory unnecessarily. This final task occurs at the end of the enabling process.

Enabling and disabling the gio cache enable flag

As superuser (root), set the qio cache enable flag using the vxtunefs command after you mount the file system.

To enable the gio_cache_enable flag for a file system

- Use the vxtunefs command as follows:
 - # /opt/VRTS/bin/vxtunefs -s -o qio_cache_enable=1 /mount_point For example:
 - # /opt/VRTS/bin/vxtunefs -s -o qio_cache_enable=1 /db02

where /db02 is a VxFS file system containing the Quick I/O files and setting the gio cache enable flag to "1" enables Cached Quick I/O. This command enables caching for all the Quick I/O files on this file system.

To disable the flag on the same file system

- Use the vxtunefs command as follows:
 - # /opt/VRTS/bin/vxtunefs -s -o qio cache enable=0 /mount point

For example:

/opt/VRTS/bin/vxtunefs -s -o qio cache enable=0 /db02

where /db02 is a VxFS file system containing the Quick I/O files and setting the gio cache enable flag to "0" disables Cached Quick I/O. This command disables caching for all the Quick I/O files on this file system.

Making Cached Quick I/O settings persistent across reboots and mounts

You can make the Cached Quick I/O system setting persistent across reboots and mounts by adding a file system entry in the /etc/vx/tunefstab file.

Note: The tunefstab file is a user-created file. For information on how to create the file and add tuning parameters, see the tunefstab (4) manual page.

To enable a file system after rebooting

Put the file system in the /etc/vx/tunefstab file and set the flag entry:

/dev/vx/dsk/dgname/volname qio cache enable=1

where:

- /dev/vx/dsk/dgname/volname is the name of a block device
- *dgname* is the name of the disk group
- *volname* is the name of the volume

For example:

```
/dev/vx/dsk/PRODdg/db01 gio cache enable=1
/dev/vx/dsk/PRODdg/db02 gio cache enable=1
```

where /dev/vx/dsk/PRODdg/db01 is the block device on which the file system resides.

The tunefstab (4) manual pages contain information on how to add tuning parameters.

See the tunefstab (4) manual page.

Note: vxtunefs can specify a mount point or a block device; tunefstab must always specify a block device only.

Using vxtunefs to obtain tuning information

Check the setting of the qio cache enable flag for each file system using the vxtunefs command.

To obtain information on only the qio_cache_enable flag setting

- Use the grep command with vxtunefs:
 - # /opt/VRTS/bin/vxtunefs /mount_point | grep qio_cache_enable

For example:

```
# /opt/VRTS/bin/vxtunefs /db01 | grep qio_cache_enable
```

where /db01 is the name of the file system. This command displays only the qio cache enable setting as follows:

```
qio cache enable = 0
```

You can also use the vxtunefs command to obtain a more complete list of I/O characteristics and tuning statistics.

See the vxtunefs (1) manual page.

To obtain information on all vxtunefs system parameters

- Use the vxtunefs command without grep:
 - # /opt/VRTS/bin/vxtunefs /mount point

For example:

/opt/VRTS/bin/vxtunefs /db01

The vxtunefs command displays output similar to the following:

```
Filesystem i/o parameters for /db01
read pref io = 65536
read nstream = 1
read unit io = 65536
write pref io = 65536
write nstream = 1
write unit io = 65536
pref strength = 10
buf breakup size = 131072
discovered direct iosz = 262144
max direct iosz = 1048576
default indir size = 8192
qio cache enable = 0
odm cache enable = 0
write throttle = 0
max diskq = 1048576
initial extent size = 1
max segio extent size = 2048
max buf data size = 8192
hsm write prealloc = 0
read ahead = 1
inode aging size = 0
inode aging count = 0
fcl\ maxalloc = 887660544
fcl keeptime = 0
fcl winterval = 3600
fcl ointerval = 600
oltp load = 0
delicache enable = 1
thin friendly alloc = 0
dalloc enable = 1
dalloc limit = 90
```

The vxtunefs(1) manual pages contain a complete description of vxtunefs parameters and the tuning instructions.

See the vxtunefs(1) manual page.

Determining candidates for Cached Quick I/O

Determining which files can benefit from Cached Quick I/O is an iterative process that varies with each application. For this reason, you may need to complete the following steps more than once to determine the best possible candidates for Cached Quick I/O.

Before determining candidate files for Quick I/O, make sure the following conditions have been met:

Prerequisites

■ You must enable Cached Quick I/O for the file systems.

Usage notes

■ See the giostat (1M) manual page for more information.

Collecting I/O statistics

Once you have enabled Cached Quick I/O on a file system, you need to collect statistics to determine and designate the files that can best take advantage of its benefits.

To collect statistics needed to determine files that benefit from Cached Quick I/O

- Reset the qiostat counters by entering:
 - \$ /opt/VRTS/bin/qiostat -r /mount point/filenames
- Run the database under full normal load and through a complete cycle (24 to 48 hours in most cases) to determine your system I/O patterns and database traffic in different usage categories (for example, OLTP, reports, and backups) at different times of the day.
- While the database is running, run giostat -1 to report the caching statistics as follows:
 - \$ /opt/VRTS/bin/qiostat -1 /mount point/filenames

or, use the -i option to see statistic reports at specified intervals:

\$ /opt/VRTS/bin/qiostat -i n /mount point/filenames

where n is time in seconds

For example:

To collect I/O statistics from all database files on file system:

\$ /opt/VRTS/bin/qiostat -1 /db01/*.dbf

About I/O statistics for DB2

The output of the giostat command is the primary source of information to use in deciding whether to enable or disable Cached Quick I/O on specific files. Statistics are printed in two lines per object.

The second line of information is defined as follows:

- CREAD is the number of reads from the VxFS cache (or total number of reads to Quick I/O files with cache advisory on)
- PREAD is the number of reads going to the disk for Quick I/O files with the cache advisory on
- HIT RATIO is displayed as a percentage and is the number of CREADS minus the number of preads times 100 divided by the total number of creads. The formula looks like this:

```
(CREADs - PREADs) * 100/ CREADs
```

The giostat -1 command output looks similar to the following:

```
10.0 0.0
/db01/tbs1 cont001
                           1
                                2.1
       6
/db01/tbs2 cont001 62552 38498 250213 153992 21.9 0.4
62567 49060
              21.6
/db01/tbs2 cont002 62552 38498 250213 153992 21.9 0.4
62567 49060
              21.6
```

Analyze the output to find out where the cache-hit ratio is above a given threshold. A cache-hit ratio above 20 percent on a file for a given application may be sufficient to justify caching on that file. For systems with larger loads, the acceptable ratio may be 30 percent or above. Cache-hit-ratio thresholds vary according to the database type and load.

Using the sample output above as an example, the file /db01/tbs1 cont001 does not benefit from the caching because the cache-hit ratio is zero. In addition, the file receives very little I/O during the sampling duration.

However, the files /db01/tbs2 * have a cache-hit ratio of 21.6 percent. If you have determined that, for your system and load, this figure is above the acceptable threshold, it means the database can benefit from caching. Also, study the numbers reported for the read and write operations. When you compare the number of reads and writes for the /db01/tbs2 * files, you see that the number of reads is roughly twice the number of writes. You can achieve the greatest performance

gains with Cached Quick I/O when using it for files that have higher read than write activity.

Based on these two factors, /db01/tbs2 cont001 and /db01/tbs2 cont002 are prime candidates for Cached Quick I/O.

About I/O statistics for Sybase

The output of the giostat command is the primary source of information to use in deciding whether to enable or disable Cached Quick I/O on specific files. Statistics are printed in two lines per object.

The second line of information is defined as follows:

- CREAD is the number of reads from the VxFS cache (or total number of reads to Quick I/O files with cache advisory on)
- PREAD is the number of reads going to the disk for Quick I/O files with the cache advisory on
- HIT RATIO is displayed as a percentage and is the number of CREADS minus the number of preads times 100 divided by the total number of creads. The formula looks like this:

```
(CREADs - PREADs) * 100/ CREADs
```

The giostat -1 command output looks similar to the following:

```
/db01/sysprocs.dbf 17128 9634 68509 38536 24.8 0.4
17124 15728 8.2
/db1/master.dbf 6 1 21 4 10.0 0.0
 6 6 0.0
/db01/user.dbf 62552 38498 250213 153992 21.9 0.4
62567 49060 21.6
```

Analyze the output to find out where the cache-hit ratio is above a given threshold. A cache-hit ratio above 20 percent on a file for a given application may be sufficient to justify caching on that file. For systems with larger loads, the acceptable ratio may be 30 percent or above. Cache-hit-ratio thresholds vary according to the database type and load.

Using the sample output above as an example, the file /db01/master.dbf does not benefit from the caching because the cache-hit ratio is zero. In addition, the file receives very little I/O during the sampling duration.

However, the file /db01/user.dbf has a cache-hit ratio of 21.6 percent. If you have determined that, for your system and load, this figure is above the acceptable threshold, it means the database can benefit from caching. Also, study the numbers reported for the read and write operations. When you compare the number of reads and writes for the /db01/user.dbf file, you see that the number of reads is roughly twice the number of writes. You can achieve the greatest performance gains with Cached Quick I/O when using it for files that have higher read than write activity.

Based on these two factors, /db01/user.dbf is a prime candidate for Cached Quick I/O.

Effects of read-aheads on I/O statistics

The number of CREADs in the giostat output is the total number of reads performed, including Cached Quick I/O, and the number of PREADS is the number of physical reads. The difference between CREADS and PREADS (CREADS - PREADS) is the number of reads satisfied from the data in the file system cache. Thus, you expect that the number of PREADS would always be equal to or lower than the number of CREADS.

However, the PREADS counter also increases when the file system performs read-aheads. These read-aheads occur when the file system detects sequential reads. In isolated cases where cache hits are extremely low, the output from giostat could show that the number of CREADS is lower than the number of PREADS. The cache-hit ratio calculated against these CREAD/PREAD values is misleading when used to determine whether Cached Quick I/O should be enabled or disabled.

For DB2, you can make a more accurate decision based on a collective set of statistics by gathering multiple sets of data points. Consequently, you might want to enable Cached Quick I/O for all the container files that contain a particular table, across multiple tablespaces used by a given database, even if the containers in just one of the tablespaces exhibited a high cache hit ratio. In general, we expect all containers in a tablespace to have approximately the same cache hit ratio.

For Sybase, you can make a more accurate decision based on a collective set of statistics by gathering multiple sets of data points. Consequently, you might want to enable Cached Quick I/O for all the data files in a given tablespace, even if just one of the files exhibited a high cache-hit ratio.

Other tools for analysis

While the output of the qiostat command is the primary source of information to use in deciding whether to enable Cached Quick I/O on specific files, we also recommend using other tools in conjunction with giostat. For example, benchmarking software that measures database throughput is also helpful. If a benchmark test in which Cached Quick I/O was enabled for a certain set of data

files resulted in improved performance, you can also use those results as the basis for enabling Cached Quick I/O.

Enabling and disabling Cached Quick I/O for individual files

After using qiostat or other analysis tools to determine the appropriate files for Cached Quick I/O, you need to disable Cached Quick I/O for those individual files that do not benefit from caching using the qioadmin command.

Prerequisites

■ Enable Cached Quick I/O for the file system before enabling or disabling Cached Quick I/O at the individual file level.

Usage notes

- You can enable or disable Cached Quick I/O for individual files while the database is online.
- You should monitor files regularly using giostat to ensure that a file's cache-hit ratio has not changed enough to reconsider enabling or disabling Cached Quick I/O for the file.
- Enabling or disabling Cached Quick I/O for an individual file is also referred to as setting the cache advisory on or off.
- See the gloadmin (1) manual page.

Setting cache advisories for individual files

You can enable and disable Cached Quick I/O for individual files by changing the cache advisory settings for those files.

To disable Cached Quick I/O for an individual file

- Use the gloadmin command to set the cache advisory to OFF as follows:
 - \$ /opt/VRTS/bin/qioadmin -S filename=OFF /mount point

For example for DB2, to disable Cached Quick I/O for the file /db01/dbfile, set the cache advisory to OFF:

\$ /opt/VRTS/bin/qioadmin -S dbfile=OFF /db01

For example for Sybase, to disable Cached Quick I/O for the file /db01/master.dbf, set the cache advisory to OFF:

\$ /opt/VRTS/bin/qioadmin -S master.dbf=OFF /db01

To enable Cached Quick I/O for an individual file

- Use the gloadmin command to set the cache advisory to on as follows:
 - \$ /opt/VRTS/bin/qioadmin -S filename=ON /mount point

For example for DB2, running giostatshows the cache hit ratio for the file /db01/dbfilereaches a level that would benefit from caching. To enable Cached Quick I/O for the file /db01/dbfile, set the cache advisory to ON:

\$ /opt/VRTS/bin/qioadmin -S dbfile=ON /db01

For example for Sybase, running qiostatshows the cache hit ratio for the file /db01/master.dbfreaches a level that would benefit from caching. To enable Cached Quick I/O for the file /db01/master.dbf, set the cache advisory to on:

\$ /opt/VRTS/bin/qioadmin -S master/dbf=ON /db01

Making individual file settings for Cached Quick I/O persistent

You can make the enable or disable individual file settings for Cached Quick I/O persistent across reboots and mounts by adding cache advisory entries in the /etc/vx/gioadmin file.

Cache advisories set using the qioadmin command are stored as extended attributes of the file in the inode. These settings persist across file system remounts and system reboots, but these attributes are not backed up by the usual backup methods, so they cannot be restored. Therefore, always be sure to reset cache advisories after each file restore. This is not necessary if you maintain the cache advisories for Quick I/O files in the /etc/vx/qioadmin file.

To enable or disable individual file settings for Cached Quick I/O automatically after a reboot or mount

Add cache advisory entries in the /etc/vx/gioadmin file as follows:

```
device=/dev/vx/dsk/<diskgroup>/<volume>
filename, OFF
filename, OFF
filename, OFF
filename, ON
```

For example, to make the Cached Quick I/O settings for individual files in the /db01 file system persistent, edit the /etc/vx/gioadmin file similar to the following:

```
# List of files to cache in /db01 file system
device=/dev/vx/dsk/PRODdg/db01
```

For DB2

```
dbfile01,0FF
dbfile02,OFF
dbfile03,0FF
```

For Sybase

```
user.dbf,ON
sysprocs.dbf,OFF
master.dbf,OFF
```

Determining individual file settings for Cached Quick I/O using qioadmin

You can determine whether Cached Quick I/O is enabled or disabled for individual files by displaying the file's cache advisory setting using the gloadmin command.

Note: To verify caching, always check the setting of the flag gio cache enable using vxtunefs, along with the individual cache advisories for each file.

To display the current cache advisory settings for a file

- ◆ Use the qioadmin command with the -P option as follows:
 - \$ /opt/VRTS/bin/qioadmin -P filename /mount point

For example for DB2, to display the current cache advisory setting for the file dbfilein the /db01file system:

\$ /opt/VRTS/bin/qioadmin -P dbfile /db01

dbfile,OFF

For example for Sybase, to display the current cache advisory setting for the file sysprocs.dbfin the /db01file system:

\$ /opt/VRTS/bin/qioadmin -P sysprocs.dbf /db01

sysprocs.dbf,OFF

Chapter 5

Improving database performance with Veritas Concurrent I/O

This chapter includes the following topics:

- About Concurrent I/O
- Tasks for enabling and disabling Concurrent I/O

About Concurrent I/O

Veritas Concurrent I/O improves the performance of regular files on a VxFS file system without the need for extending namespaces and presenting the files as devices. This simplifies administrative tasks and allows databases, which do not have a sequential read/write requirement, to access files concurrently. This chapter describes how to use the Concurrent I/O feature.

Quick I/O is an alternative solution for DMS tablespaces.

In some cases (for example, if the system has extra memory), Cached Quick I/O may further enhance performance.

See "About Cached Quick I/O" on page 53.

How Concurrent I/O works

Traditionally, UNIX semantics require that read and write operations on a file occur in a serialized order. Because of this, a file system must enforce strict ordering of overlapping read and write operations. However, databases do not

usually require this level of control and implement concurrency control internally, without using a file system for order enforcement.

The Veritas Concurrent I/O feature removes these semantics from the read and write operations for databases and other applications that do not require serialization.

The benefits of using Concurrent I/O are:

- Concurrency between a single writer and multiple readers
- Concurrency among multiple writers
- Minimalization of serialization for extending writes
- All I/Os are direct and do not use file system caching
- I/O requests are sent directly to file systems
- Inode locking is avoided

Tasks for enabling and disabling Concurrent I/O

Concurrent I/O is not turned on by default and must be enabled manually. You will also have to manually disable Concurrent I/O if you choose not to use it in the future.

You can perform the following tasks:

- Enable Concurrent I/O
- Disable Concurrent I/O

Enabling Concurrent I/O for DB2

Because you do not need to extend name spaces and present the files as devices, you can enable Concurrent I/O on regular files.

For DB2, you can enable an entire file system to use Concurrent I/O or you can enable specific SMS containers to use Concurrent I/O. If you enable a specific SMS container, the rest of the file system will use the regular buffer I/O.

Warning: For DB2, If you use the -o cio option with the mount command to mount your primary database file systems, the Concurrent I/O settings will not be preserved when using Database FlashSnap commands or the command.

Before enabling Concurrent I/O, review the following:

Prerequisites

- To use the Concurrent I/O feature, the file system must be a VxFS
- Make sure the mount point on which you plan to mount the file system exists.
- Make sure the DBA can access the mount point.

Usage notes

- When a file system is mounted with the Concurrent I/O option, do not enable Quick I/O. DB2 will not be able to open the Quick I/O files and the instance start up will fail.
- Do not use any Quick I/O tools if the database is using Concurrent
- See the mount vxfs(1M) manual page for more information about mount settings.

For DB2, */mount point* is the directory in which you can put data containers of the SMS tablespaces using the Concurrent I/O feature.

Note: This applies to both creating a new tablespace to use Concurrent I/O or enabling an existing tablespace to use Concurrent I/O.

For example for DB2 to mount a file system named /datavol on a mount point named /db2data:

/usr/sbin/mount -F vxfs -o cio /dev/vx/dsk/db2dg/datavol \ /db2data

To enable Concurrent I/O on a new SMS container using the namefs -o cio option

- Using the mount command, mount the directory in which you want to put data containers of the SMS tablespaces using the Concurrent I/O feature.
 - # /usr/sbin/mount -Vt namefs -o cio /path name /new mount point where:
 - /path name is the directory in which the files that will be using Concurrent I/O reside
 - /new mount point is the new target directory that will use the Concurrent I/O feature

The following is an example of mounting a directory (where the new SMS containers are located) to use Concurrent I/O.

To mount an SMS container named /container1 on a mount point named /mysms:

/usr/sbin/mount -Vt namefs -o cio /datavol/mysms/container1 /mysms

To enable Concurrent I/O on an existing SMS container using the namefs -o cio option

- 1 Stop the DB2 instance using the db2stop command.
- Make the directory that will have Concurrent I/O turned on available using the my command.
 - # mv /mydb/mysmsdir /mydb/mysmsdir2
- Remount /mydb/mysmsdir2 on /mydb/mysmsdir using the mount command with the -o cio option.
 - # mount -Vt namefs -o cio /mydb/mysmsdir2 /mydb/mysmsdir
- Start the DB2 instance using the db2start command.

```
# db2stop
```

- # mv /mydb/mysmsdir /mydb/mysmsdir2
- # mount -Vt namefs -o cio /mydb/mysmsdir2 /mydb/mysmsdir
- # db2start

This example shows how to mount a directory for an existing SMS container to use Concurrent I/O.

To enable Concurrent I/O on a DB2 tablespace when creating the tablespace

- Use the db2 -v "create regular tablespace..." command with the no file system caching option.
- Set all other parameters according to your system requirements.

To enable Concurrent I/O on an existing DB2 tablespace

Use the DB2 no file system caching option as follows:

```
# db2 -v "alter tablespace tablespace name no file system caching"
```

where tablespace name is the name of the tablespace for which you are enabling Concurrent I/O.

To verify that Concurrent I/O has been set for a particular DB2 tablespace

Use the DB2 get snapshot option to check for Concurrent I/O.

db2 -v "get snapshot for tablespaces on dbname"

where dbname is the database name.

Find the tablespace you want to check and look for the File system caching attribute. If you see File system caching = No, then Concurrent I/O is enabled.

Disabling Concurrent I/O for DB2

If you need to disable Concurrent I/O, use the DB2 file system caching option.

Note: If you used the namefs -o cio option with the mount command to mount a directory to enable Concurrent I/O, make sure you remount without that option as well. Also, if you follow the directions for enabling Concurrent I/O on an existing SMS container, rename the directory back to the original name.

To disable Concurrent I/O on a DB2 tablespace

Use the DB2 file system caching option as follows:

db2 -v "alter tablespace tablespace name file system caching"

where *tablespace name* is the name of the tablespace for which you are disabling Concurrent I/O.

Enabling Concurrent I/O for Sybase

Because you do not need to extend name spaces and present the files as devices, you can enable Concurrent I/O on regular files.

Before enabling Concurrent I/O, review the following:

Prerequisites

- To use the Concurrent I/O feature, the file system must be a VxFS file system.
- Make sure the mount point on which you plan to mount the file system exists.
- Make sure the DBA can access the mount point.

To enable Concurrent I/O on a file system using mount with the -o cio option

Mount the file system using the mount command as follows:

/usr/sbin/mount -F vxfs -o cio special /mount point

where:

- *special* is a block special device.
- */mount point* is the directory where the file system will be mounted.

For example for Sybase, to mount a file system named /datavolon a mount point named /sybasedata:

/usr/sbin/mount -F vxfs -o cio /dev/vx/dsk/sybasedq/datavol \ /sybasedata

The following is an example of mounting a directory (where the new SMS containers are located) to use Concurrent I/O.

To mount an SMS container named /container1 on a mount point named /mysms:

/usr/sbin/mount -Vt namefs -o cio /datavol/mysms/container1 /mysms

Disabling Concurrent I/O for Sybase

If you need to disable Concurrent I/O, unmount the VxFS file system and mount it again without the mount option.

To disable Concurrent I/O on a file system using the mount command

- 1 Shutdown the DB instance.
- Unmount the file sytem using the umount command. 2
- 3 Mount the file system again using the mount command without using the -o cio option.

Section 3

Using point-in-time copies

- Chapter 6. Understanding point-in-time copy methods
- Chapter 7. Backing up and recovering
- Chapter 8. Backing up and recovering in a NetBackup environment
- Chapter 9. Off-host processing
- Chapter 10. Creating and refreshing test environments
- Chapter 11. Creating point-in-time copies of files

Chapter 6

Understanding point-in-time copy methods

This chapter includes the following topics:

- About point-in-time copies
- When to use point-in-time copies
- About Storage Foundation point-in-time copy technologies

About point-in-time copies

Veritas Storage Foundation offers a flexible and efficient means of managing business-critical data. Storage Foundation lets you capture an online image of an actively changing database at a given instant, called a point-in-time copy.


More and more, the expectation is that the data must be continuously available (24x7) for transaction processing, decision making, intellectual property creation, and so forth. Protecting the data from loss or destruction is also increasingly important. Formerly, data was taken out of service so that the data did not change while data backups occured; however, this option does not meet the need for minimal down time.

A point-in-time copy enables you to maximize the online availability of the data. You can perform system backup, upgrade, or perform other maintenance tasks on the point-in-time copies. The point-in-time copies can be processed on the same host as the active data, or a different host. If required, you can offload processing of the point-in-time copies onto another host to avoid contention for system resources on your production server. This method is called off-host processing. If implemented correctly, off-host processing solutions have almost no impact on the performance of the primary production system.

Implementing point-in time copy solutions on a primary host

Figure 6-1 illustrates the steps that are needed to set up the processing solution on the primary host.

Figure 6-1 Using snapshots and FastResync to implement point-in-time copy solutions on a primary host



Note: The Disk Group Split/Join functionality is not used. As all processing takes place in the same disk group, synchronization of the contents of the snapshots from the original volumes is not usually required unless you want to prevent disk contention. Snapshot creation and updating are practically instantaneous.

Figure 6-2 shows the suggested arrangement for implementing solutions where the primary host is used and disk contention is to be avoided.




Figure 6-2 Example point-in-time copy solution on a primary host

In this setup, it is recommended that separate paths (shown as 1 and 2) from separate controllers be configured to the disks containing the primary volumes and the snapshot volumes. This avoids contention for disk access, but the primary host's CPU, memory and I/O resources are more heavily utilized when the processing application is run.

Note: For space-optimized or unsynchronized full-sized instant snapshots, it is not possible to isolate the I/O pathways in this way. This is because such snapshots only contain the contents of changed regions from the original volume. If applications access data that remains in unchanged regions, this is read from the original volume.

Implementing off-host point-in-time copy solutions

Figure 6-3 illustrates that, by accessing snapshot volumes from a lightly loaded host (shown here as the OHP host), CPU- and I/O-intensive operations for online backup and decision support are prevented from degrading the performance of the primary host that is performing the main production activity (such as running a database).


Primary Host OHP host Network 2 SCSI or Fibre Channel connectivity Disks containing primary Disks containing snapshot volumes used to hold volumes production databases or file systems

Figure 6-3 Example implementation of an off-host point-in-time copy solution

Also, if you place the snapshot volumes on disks that are attached to host controllers other than those for the disks in the primary volumes, it is possible to avoid contending with the primary host for I/O resources. To implement this, paths 1 and 2 shown in the Figure 6-3 should be connected to different controllers.

Figure 6-4 shows an example of how you might achieve such connectivity using Fibre Channel technology with 4 Fibre Channel controllers in the primary host.

Figure 6-4 Example connectivity for off-host solution using redundant-loop access



This layout uses redundant-loop access to deal with the potential failure of any single component in the path between a system and a disk array.

Note: On some operating systems, controller names may differ from what is shown here.

Figure 6-5 shows how off-host processing might be implemented in a cluster by configuring one of the cluster nodes as the OHP node.

Figure 6-5 Example implementation of an off-host point-in-time copy solution using a cluster node





Figure 6-6 shows an alternative arrangement, where the OHP node could be a separate system that has a network connection to the cluster, but which is not a cluster node and is not connected to the cluster's private network.

Example implementation of an off-host point-in-time copy solution Figure 6-6 using a separate OHP host




Note: For off-host processing, the example scenarios in this document assume that a separate OHP host is dedicated to the backup or decision support role. For clusters, it may be simpler, and more efficient, to configure an OHP host that is not a member of the cluster.

Figure 6-7 illustrates the steps that are needed to set up the processing solution on the primary host.

Implementing off-host processing solutions Figure 6-7

volumes with the original volumes'

disk group.



through 9 as required

Disk Group Split/Join is used to split off snapshot volumes into a separate disk group that is imported on the OHP host.

Note: As the snapshot volumes are to be moved into another disk group and then imported on another host, their contents must first be synchronized with the parent volumes. On reimporting the snapshot volumes, refreshing their contents from the original volume is speeded by using FastResync.

When to use point-in-time copies

The following typical activities are suitable for point-in-time copy solutions implemented using Veritas FlashSnap:

- Data backup —Many enterprises require 24 x 7 data availability. They cannot afford the downtime involved in backing up critical data offline. By taking snapshots of your data, and backing up from these snapshots, your business-critical applications can continue to run without extended downtime or impacted performance.
- Providing data continuity —To provide continuity of service in the event of primary storage failure, you can use point-in-time copy solutions to recover application data. In the event of server failure, you can use point-in-time copy solutions in conjunction with the high availability cluster functionality of Veritas Storage Foundation™ for Cluster File System HA or Veritas Storage Foundation HA.
- Decision support analysis and reporting—Operations such as decision support analysis and business reporting may not require access to real-time information. You can direct such operations to use a replica database that you have created from snapshots, rather than allow them to compete for access to the primary database. When required, you can quickly resynchronize the database copy with the data in the primary database.
- Testing and training—Development or service groups can use snapshots as test data for new applications. Snapshot data provides developers, system testers and QA groups with a realistic basis for testing the robustness, integrity and performance of new applications.
- Database error recovery—Logic errors caused by an administrator or an application program can compromise the integrity of a database. You can recover a database more quickly by restoring the database files by using Storage Checkpoints or a snapshot copy than by full restoration from tape or other backup media.

Use Storage Checkpoints to quickly roll back a database instance to an earlier point in time.

■ Cloning data—You can clone your file system or application data. This functionality enable you to quickly and efficiently provision virtual desktops.

All of the snapshot solutions mentioned above are also available on the disaster recovery site, in conjunction with Veritas Volume Replicator.

For more information about snapshots with replication, see the Veritas Storage Foundation and High Availability Solutions Replication Administrator's Guide.

Veritas Storage Foundation provides several point-in-time copy solutions that support your needs, including the following use cases:

- Creating a replica database for decision support. See "Using a replica database for decision support" on page 144.
- Backing up and recovering a database with snapshots. See "Online database backups" on page 97.
- Backing up and recovering an off-host cluster file system See "Backing up on an off-host cluster file system" on page 120.
- Backing up and recovering an online database. See "Database recovery using Storage Checkpoints" on page 129.

About Storage Foundation point-in-time copy technologies

This topic introduces the point-in-time copy solutions that you can implement using the Veritas FlashSnap™ technology. Veritas FlashSnap technology requires an enterprise product license.

Veritas FlashSnap offers a flexible and efficient means of managing business critical data. It allows you to capture an online image of actively changing data at a given instant: a point-in-time copy. You can perform system backup, upgrade and other maintenance tasks on point-in-time copies while providing continuous availability of your critical data. If required, you can offload processing of the point-in-time copies onto another host to avoid contention for system resources on your production server.

The following kinds of point-in-time copy solution are supported with an enterprise license:

■ Volume-level solutions. There are several types of volume-level snapshots. These features are suitable for solutions where separate storage is desirable to create the snapshot. For example, lower-tier storage. Some of these techniques provided exceptional offhost processing capabilities. See "Volume-level snapshots" on page 87.

- File system-level solutions use the Storage Checkpoint feature of Veritas File System. Storage Checkpoints are suitable for implementing solutions where storage space is critical for:
 - File systems that contain a small number of mostly large files.
 - Application workloads that change a relatively small proportion of file system data blocks (for example, web server content and some databases).
 - Applications where multiple writable copies of a file system are required for testing or versioning.

See "Storage Checkpoints" on page 88.

■ File level snapshots. The FileSnap feature provides snapshots at the level of individual files. See "About FileSnaps" on page 89.

Volume-level snapshots

A volume snapshot is an image of a Veritas Volume Manager (VxVM) volume at a given point in time. You can also take a snapshot of a volume set.

Volume snapshots allow you to make backup copies of your volumes online with minimal interruption to users. You can then use the backup copies to restore data that has been lost due to disk failure, software errors or human mistakes, or to create replica volumes for the purposes of report generation, application development, or testing.

Volume snapshots can also be used to implement off-host online backup.

Physically, a snapshot may be a full (complete bit-for-bit) copy of the data set, or it may contain only those elements of the data set that have been updated since snapshot creation. The latter are sometimes referred to as allocate-on-first-write snapshots, because space for data elements is added to the snapshot image only when the elements are updated (overwritten) for the first time in the original data set. Storage Foundation allocate-on-first-write snapshots are called space-optimized snapshots.

Persistent FastResync of volume snapshots

If persistent FastResync is enabled on a volume, VxVM uses a FastResync map to keep track of which blocks are updated in the volume and in the snapshot.

When snapshot volumes are reattached to their original volumes, persistent FastResync allows the snapshot data to be quickly refreshed and re-used. Persistent FastResync uses disk storage to ensure that FastResync maps survive both system and cluster crashes. If persistent FastResync is enabled on a volume in a private disk group, incremental resynchronization can take place even if the host is rebooted.

Persistent FastResync can track the association between volumes and their snapshot volumes after they are moved into different disk groups. After the disk groups are rejoined, persistent FastResync allows the snapshot plexes to be quickly resynchronized.

Data integrity in volume snapshots

A volume snapshot captures the data that exists in a volume at a given point in time. As such, VxVM does not have any knowledge of data that is cached in memory by the overlying file system, or by applications such as databases that have files open in the file system. Snapshots are always crash consistent, that is, the snapshot can be put to use by letting the application perform its recovery. This is similar to how the application recovery occurs after a server crash. If the fsqen volume usage type is set on a volume that contains a mounted Veritas File System (VxFS). VxVM coordinates with VxFS to flush data that is in the cache to the volume. Therefore, these snapshots are always VxFS consistent and require no VxFS recovery while mounting.

For databases, a suitable mechanism must additionally be used to ensure the integrity of tablespace data when the volume snapshot is taken. The facility to temporarily suspend file system I/O is provided by most modern database software. The examples provided in this document illustrate how to perform this operation. For ordinary files in a file system, which may be open to a wide variety of different applications, there may be no way to ensure the complete integrity of the file data other than by shutting down the applications and temporarily unmounting the file system. In many cases, it may only be important to ensure the integrity of file data that is not in active use at the time that you take the snapshot. However, in all scenarios where application coordinate, snapshots are crash-recoverable.

Storage Checkpoints

A Storage Checkpoint is a persistent image of a file system at a given instance in time. Storage Checkpoints use a copy-on-write technique to reduce I/O overhead by identifying and maintaining only those file system blocks that have changed since a previous Storage Checkpoint was taken. Storage Checkpoints have the following important features:

■ Storage Checkpoints persist across system reboots and crashes.

- A Storage Checkpoint can preserve not only file system metadata and the directory hierarchy of the file system, but also user data as it existed when the Storage Checkpoint was taken.
- After creating a Storage Checkpoint of a mounted file system, you can continue to create, remove, and update files on the file system without affecting the image of the Storage Checkpoint.
- Unlike file system snapshots, Storage Checkpoints are writable.
- To minimize disk space usage, Storage Checkpoints use free space in the file system.

Storage Checkpoints and the Storage Rollback feature of Veritas Storage Foundation for Databases enable rapid recovery of databases from logical errors such as database corruption, missing files and dropped table spaces. You can mount successive Storage Checkpoints of a database to locate the error, and then roll back the database to a Storage Checkpoint before the problem occurred.

See "Database recovery using Storage Checkpoints" on page 129.

Symantec NetBackup for Oracle Advanced BLI Agent uses Storage Checkpoints to enhance the speed of backing up Oracle databases.

See the Symantec NetBackup for Oracle Advanced BLI Agent System Administrator's Guide.

About FileSnaps

A FileSnap is an atomic space-optimized copy of a file in the same name space, stored in the same file system. Veritas File System (VxFS) supports snapshots on file system disk layout Version 8 and later.

FileSnaps provide an ability to snapshot objects that are smaller in granularity than a file system or a volume. The ability to snapshot parts of a file system name space is required for application-based or user-based management of data stored in a file system. This is useful when a file system is shared by a set of users or applications or the data is classified into different levels of importance in the same file system.

All regular file operations are supported on the FileSnap, and VxFS does not distinguish the FileSnap in any way.

90 Understanding point-in-time copy methods
About Storage Foundation point-in-time copy technologies

Chapter

Backing up and recovering

This chapter includes the following topics:

- About Storage Foundation and High Availability Solutions backup and recovery use cases
- Creating and maintaining a full image snapshot and incremental point-in-time copies
- Online database backups
- Backing up on an off-host cluster file system
- Database recovery using Storage Checkpoints

About Storage Foundation and High Availability Solutions backup and recovery use cases

Storage Foundation and High Availability Solutions (SFHA Solutions) provide point-in-time copy methods which can be applied to multiple database backup use cases.

Example procedures are provided for the following use cases:

- Creating and maintaining a full image snapshot and incremental point-in-time copies
 - See "Creating and maintaining a full image snapshot and incremental point-in-time copies" on page 92.
- Backing up and recovering a database with snapshots.See "Online database backups" on page 97.
- Backing up and recovering an off-host cluster file system

 See "Backing up on an off-host cluster file system" on page 120.

- Backing up and recovering an online database. See "Database recovery using Storage Checkpoints" on page 129.
- Recovering a database with Storage Checkpoints See "Database recovery using Storage Checkpoints" on page 129.
- Backing up and recovering a database in a NetBackup environment.

For basic backup and recovery configuration information, see the Veritas Storage Foundation Administrator's Guide.

Creating and maintaining a full image snapshot and incremental point-in-time copies

On-disk snapshots are efficient when it comes to recovering a logically corrupted data. Storage Foundation and High Availability Solutions (SFHA Solutions) provide a cost effective and very efficient mechanism to manage multiple copies of production data at different points in time. With Flashsnap, you can create a solution to preserve and manage the whole lifecycle of snapshots for recovery from logical data corruption. You can also use the preserved snapshot image itself for business continuity in case of primary storage failure or for off-host processing.

The following example procedures illustrate how to create a full image snapshot and periodic point-in-time copies for recovery. With mulitple point-in-time copies to choose from, you can select the point-in-time to which you want to recover with relative precision.

Setting up a full image snapshot and incremental point-in-time copies

To set up the initial configuration for a full image snapshot and incremental point-in-time copies, set up storage for the point-in-time copies that will be configured over time.

In the example procedures, disk1, disk2, ..., diskN are the LUNs configured on tier 1 storage for application data. A subset of these LUNs logdisk1, logdisk2, ..., logdiskN, will be used to configure DCO. Disks sdisk1, sdisk2, ..., sdiskN are disks from tier 2 storage.

Note: If you have an enclosure or disk array with storage that is backed by write cache, Symantec recommends that you use the same set of LUNS for DCO and for data volume.

If no logdisks are specified by default, Veritas Volume Manager tries to allocate the DCO from the same LUNs used for the data volumes.

See Figure 6-4 on page 81.

You will need to make sure your cache is big enough for the multiple copies with multiple changes. The following guidelines may be useful for estimating your requirements.

To determine your storage requirements, use the following:

Table 7-1 Storage requirements

Represents the storage requirement for the primary volume S_{n}

Represents the storage requirement for the primary break-off snapshot. S_b

 N_c Represents the number of point-in-time copies to be maintained.

Represents the average size of the changes that occur in an interval before the S_c snapshot is taken.

 S_t Represents the total storage requirement.

The total storage requirement for management of multiple point-in-time copies can be roughly calculated as:

$$S_b = S_p$$

$$S_t = S_b + N_c * S_c$$

To determine the size of the cache volume, use the following:

Table 7-2 Cache volume requirements

Represents the number of point-in-time copies to be maintained. N_c

 S_c Represents the average size of the changes that occur in an interval.

Represents the region-size for cache-object. R

Represents the total storage requirement. S_{t}

The size of cache-volume to be configured can be calculated as:

This equation assumes that the application IO size granularity is smaller than cache-object region-size by factor of at most R_c

To configure the initial setup for a full image snapshot and incremental point-in-time copies

1 If the primary application storage is already configured for snapshots, that is, the DCO is already attached for the primary volume, go to step 2.

If not, configure the primary volumes and prepare them for snapshots.

For example:

```
# vxassist -g appdg make appvol 10T <disk1 disk2 ... diskN >
# vxsnap -g appdg prepare appvol
```

- 2 Configure your storage for a full image snapshot and the point-in-time copies to be created periodically, in a similar manner to the way you configured your primary volumes. Veritas Storage Foundation does not need allocation from the same (tier 1) storage to configure point-in-time copies. For instance, the allocation could come from tier 2 storage.
- 3 Configure a snapshot volume from tier 2 storage to use as primary snapshot of the primary volume.

```
# vxassist -g appdg make snap-appvol 10T <sdisk1 sdisk2 ... sdiskN >
# vxsnap -q appdq prepare snap-appvol \
<alloc=slogdisk1, slogdisk2, ...slogdiskN>
```

4 Establish the relationship between primary and snapshot volumes and wait for synchronization of the snapshot to complete.

```
# vxsnap -q appdq make source=appvol/snapvol=snap-appvol/sync=yes
# vxsnap -g appdg syncwait snap-appvol
```

5 Create a volume to use for the cache volume.

```
# vxassist -q appdq make cachevol 1G layout=mirror \
init=active disk16 disk17
```

6 Configure a shared cache object in the disk group from tier 2 storage to use for point-in-time copies created at regular intervals.

```
# vxmake -g appdg cache snapcache cachevolname=cachevol
```

Start the cache object.

```
# vxcache -g appdg start snapcache
```

You now have an initial setup in place to create regular point-in-time copies.

Refreshing point-in-time copies

After configuring your volumes for snapshots, you can periodically invoke a script with steps similar to following to create point-in-time copies at regular intervals.

To identify snapshot age

- To find the oldest and the most recent snapshots, use the creation time of the snapshots. You can use either of the following commands:
 - Use the following command and find the SNAPDATE of snapshot volume.

```
# vxsnap -g appdg list appvol
```

■ Use the following command:

```
# vxprint -g appdg -m snapobject name| grep creation time
```

Where the *snapobject-name* is *appvol-snp*, *appvol-snp1* *appvol-snpN*.

To refresh the primary snapshot

Refresh the primary snapshot from the primary volume.

```
# vxsnap -g appdg refresh snap-appvol source=appvol
```

To create cascaded snapshot of the refreshed snapshot volume

Create a cascaded snapshot of the refreshed snapshot volume.

```
# vxsnap -g appdg make source=snap-appvol/new=sosnap-\
appvol${NEW SNAP IDX}/cache=snapcache/infrontof=snap-appvol
```

To remove the oldest point-in-time copy

If the limit on number of point-in-time copies is reached, remove the oldest point-in-time copy.

```
# vxedit -g appdg -rf rm sosnap-appvol${ OLDEST SNAP IDX }
```

Recovering from logical corruption

You can use the preserved snapshot image in case of primary storage corruption. You must identify the most recent snapshot which is not affected by the logical corruption.

To identify the most recent valid snapshot

For each snapshot, starting from the most recent to the oldest, verify the snapshot image. Create a space-optimized snapshot of the point-in-time copy to generate a synthetic replica of the point-in-time image.

```
# vxsnap -q appdq make source=sosnapappvol${
CURIDX}/new=syn-appvol/cache=snapcache/sync=no
```

2 Mount the synthetic replica and verify the data.

If a synthetic replica is corrupted, proceed to 3.

When you identify a synthetic replica that is not corrupted, you can proceed to the recovery steps.

See "To recover from logical corruption" on page 96.

Unmount the synthetic replica, remove it and go back to verify the next most recent point-in-time copy. Use the following command to dissociate the synthetic replica and remove it:

```
# vxsnap -g appdg dis syn-appvol
# vxedit -q appdq -rf rm syn-appvol
```

When you find the most recent uncorrupted snapshot, use it to restore the primary volume.

To recover from logical corruption

- If the application is running on the primary volume, stop the application.
- 2 Unmount the application volume.
- 3 Restore the primary volume from the synthetic replica.

```
# vxsnap -q appdg restore appvol source=syn-appvol
```

- Resume the application:
 - Mount the primary volume.
 - Verify the content of the primary volume.
 - Restart the application.

Off-host processing using refreshed snapshot images

Preserved point-in-time images can also be used to perform off-host processing. Using preserved point-in-time images for this purpose requires that the storage used for creating the snapshots must be:

- Accessible from the application host
- Accessible from the off-host processing host
- Split into a separate diskgroup

To split the snapshot storage into a separate disk group

Split the snapshot storage into a separate disk group.

```
# vxdg split appdg snapdg snap-appvol
```

The *snapdg* disk group can optionally be deported from the application host using the vxdq deport command and imported on another host using the vxdq import command to continue to perform off-host processing.

To refresh snapshot images for off-host processing

Deport the *snapdg* disk group from the off-host processing host.

```
# vxdq deport snapdq
```

Import the *snapdg* disk group on the application host.

```
# vxdq import snapdq
```

On the application host, join the *snapdg* disk group to *appdg*.

```
# vxdq join snapdq appdq
```

After this step, you can proceed with the steps for managing point-in-time copies.

See "Refreshing point-in-time copies" on page 95.

Online database backups

Online backup of a database can be implemented by configuring either the primary host or a dedicated separate host to perform the backup operation on snapshot mirrors of the primary host's database.

Two backup methods are described in the following sections:

■ See "Making a backup of an online database on the same host" on page 98.

■ See "Making an off-host backup of an online database" on page 109.

Note: All commands require superuser (root) or equivalent privileges, except where it is explicitly stated that a command must be run by the database administrator.

For more information about using snapshots to back up Oracle databases, see the Veritas Storage Foundation™: Storage and Availability Management for Oracle Databases.

Note: The sample database scripts in the following procedures are not supported by Symantec, and are provided for informational use only. You can purchase customization of the environment through Veritas Vpro Consulting Services.

Making a backup of an online database on the same host

Figure 7-1 shows an example with two primary database volumes to be backed up, database vol and dbase logs, which are configured on disks attached to controllers *c1* and *c2*, and the snapshots to be created on disks attached to controllers c3 and c4.

primary host

Figure 7-1 Example system configuration for database backup on the primary

Primary host for database Controllers c1 c2 с3 c4 Database volumes Snapshot volumes are are created on these created on these disks disks Disk arrays Backup to disk, tape or other media by

Note: It is assumed that you have already prepared the volumes containing the file systems for the datafiles to be backed up as described in the example.

To make an online database backup

■ Prepare the snapshot, either full-sized or space-optimized. Depending on the application, space-optimized snapshots typically require 10% of the disk space that is required for full-sized instant snapshots. See "Preparing a full-sized instant snapshot for a backup" on page 100. See "Preparing a space-optimized snapshot for a database backup" on page 102.

- Create snapshot mirrors for volumes containing VxFS file systems for database files to be backed up.
- Make the online database backup. See "Backing up a DB2 database on the same host" on page 104. See "Backing up a Sybase database on the same host" on page 106.
- Resynchronize a volume if required. See "Resynchronizing a volume" on page 108.

Some scenarios where full-instant snapshot works better are:

- Off host processing is planned for a databases backup.
- If a space-optimized snapshot is taken for longer duration and modified frequently then it is not much different than the full-snapshot. So, for performance reason full-snapshot will be preferred,

Preparing a full-sized instant snapshot for a backup

You can use a full-sized instant snapshot for your online or off-host database backup.

Warning: To avoid data inconsistencies, do not use the same snapshot with different point-in-time copy applications. If you require snapshot mirrors for more than one application, configure at least one snapshot mirror that is dedicated to each application.

To make a full-sized instant snapshot for a backup of an online database on the same host

Use the following commands to add one or more snapshot plexes to the volume, and to make a full-sized break-off snapshot, snapvol, of the tablespace volume by breaking off these plexes:

```
# vxsnap -g database_dg addmir database vol [nmirror=N] \
 [alloc=storage_attributes]
# vxsnap -q database dg make \
 source=database vol/newvol=snapvol[/nmirror=N]\
  [alloc=storage attributes]
```

By default, one snapshot plex is added unless you specify a number using the nmirror attribute. For a backup, you should usually only require one plex. You can specify storage attributes (such as a list of disks) to determine where the plexes are created.

You can specify at least N number of disks if the specified number of mirrors is N.

If the volume layout does not support plex break-off, prepare an empty volume for the snapshot. Create a full-sized instant snapshot for an original volume that does not contain any spare plexes, you can use an empty volume with the required degree of redundancy, and with the same size and same region size as the original volume.

Use the vxprint command on the original volume to find the required size for the snapshot volume.

```
# LEN='vxprint [-g diskgroup] -F%len database vol'
```

Note: The command shown in this and subsequent steps assumes that you are using a Bourne-type shell such as sh, ksh or bash. You may need to modify the command for other shells such as csh or tcsh. These steps are valid only for instant snap DCOs.

- Use the vxprint command on the original volume to discover the name of its DCO:
 - # DCONAME='vxprint [-g diskgroup] -F%dco name database vol'
- Use the vxprint command on the DCO to discover its region size (in blocks):
 - # RSZ='vxprint [-g diskgroup] -F%regionsz \$DCONAME'
- Use the vxassist command to create a volume, *snapvol*, of the required size and redundancy, together with a instant snap DCO volume with the correct region size:

```
# vxassist [-q diskgroup] make snapvol $LEN \
  [layout=mirror nmirror=number] logtype=dco drl=no \
 dcoversion=20 [ndcomirror=number] regionsz=$RSZ \
 init=active [storage attributes]
```

It is recommended that you specify the same number of DCO mirrors (ndcomirror) as the number of mirrors in the volume (nmirror). The init=active attribute is used to make the volume available immediately. You can use storage attributes to specify which disks should be used for the volume.

As an alternative to creating the snapshot volume and its DCO volume in a single step, you can first create the volume, and then prepare it for instant snapshot operations as shown here:

```
# vxassist [-g diskgroup] make snapvol $LEN \
  [layout=mirror nmirror=number] init=active \
  [storage attributes]
# vxsnap [-g diskgroup] prepare snapvol [ndcomirs=number] \
 regionsz=$RSZ [storage attributes]
```

Use the following command to create the snapshot:

```
# vxsnap -g database_dg make source=database_vol/snapvol=snapvol
```

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database dg make source=database vol1/snapvol=snapvol1 \
source=database vol2/newvol=snapvol2 \
source=database vol3/snapvol=snapvol3
```

When you are ready to make a backup, proceed to make a backup of an online database on the same host.

Preparing a space-optimized snapshot for a database backup

If a snapshot volume is to be used on the same host, and will not be moved to another host, you can use space-optimized instant snapshots rather than full-sized instant snapshots. Depending on the application, space-optimized snapshots typically require 10% of the disk space that is required for full-sized instant snapshots.

To prepare a space-optimized snapshot for a backup of an online database

To save disk space, use the following command to create a space-optimized snapshot:

```
# vxsnap -g database dg make \
 source=database vol/newvol=snapvol/cache=snapcache
```

The argument snapcache is the name of a pre-existing cache that you have created in the disk group for use with space-optimized snapshots.

2 Decide on the following characteristics that you want to allocate to the cache volume that underlies the cache object:

- The size of the cache volume should be sufficient to record changes to the parent volumes during the interval between snapshot refreshes. A suggested value is 10% of the total size of the parent volumes for a refresh interval of 24 hours.
- If redundancy is a desired characteristic of the cache volume, it should be mirrored. This increases the space that is required for the cache volume in proportion to the number of mirrors that it has.
- If the cache volume is mirrored, space is required on at least as many disks as it has mirrors. These disks should not be shared with the disks used for the parent volumes. The disks should also be chosen to avoid impacting I/O performance for critical volumes, or hindering disk group split and join operations.
- Having decided on its characteristics, use the vxassist command to create the volume that is to be used for the cache volume. The following example creates a mirrored cache volume, *cachevol*, with size 1GB in the disk group, database dg, on the disks disk16 and disk17:

```
# vxassist -g database dg make cachevol 1g layout=mirror \
 init=active disk16 disk17
```

The attribute init=active is specified to make the cache volume immediately available for use.

4 Use the vxmake cache command to create a cache object on top of the cache volume that you created in the previous step:

```
# vxmake [-g diskgroup] cache cache_object \
 cachevolname=cachevol [regionsize=size] [autogrow=on] \
  [highwatermark=hwmk] [autogrowby=agbvalue] \
  [maxautogrow=maxagbvalue]]
```

If you specify the region size, it must be a power of 2, and be greater than or equal to 16KB (16k). If not specified, the region size of the cache is set to 64KB.

Note: All space-optimized snapshots that share the cache must have a region size that is equal to or an integer multiple of the region size set on the cache. Snapshot creation also fails if the original volume's region size is smaller than the cache's region size.

If the cache is not allowed to grow in size as required, specify autogrow=off. By default, the ability to automatically grow the cache is turned on.

In the following example, the cache object, cache object, is created over the cache volume, cachevol, the region size of the cache is set to 32KB, and the autogrow feature is enabled:

- # vxmake -g database dg cache cache object cachevolname=cachevol \ regionsize=32k autogrow=on
- Having created the cache object, use the following command to enable it:

```
vxcache [-g diskgroup] start cache object
```

For example, start the cache object cache object:

- # vxcache -g database_dg start cache_object
- 6 Create a space-optimized snapshot with your cache object.

```
# vxsnap -g database dg make \
source=database vol1/newvol=snapvol1/cache=cache object
```

If several space-optimized snapshots are to be created at the same time, these can all specify the same cache object as shown in this example:

```
# vxsnap -g database dg make \
 source=database vol1/newvol=snapvol1/cache=cache object \
 source=database vol2/newvol=snapvol2/cache=cache object \
 source=database vol3/newvol=snapvol3/cache=cache object
```

Note: This step sets up the snapshot volumes, prepares for the backup cycle, and starts tracking changes to the original volumes.

When you are ready to make a backup, proceed to make a backup of an online database on the same host

Backing up a DB2 database on the same host

You can make an online backup of your DB2 database.

To make a backup of an online DB2 database on the same host

If the volumes to be backed up contain database tables in file systems, suspend updates to the volumes. DB2 provides the write suspend command to temporarily suspend I/O activity for a database. As the DB2 database administrator, use a script such as that shown in the example to suspend I/O for a DB2 database.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to suspend I/O for a DB2 database.
# Note: To recover a database using backups of snapshots, the database
# must be in LOGRETAIN mode.
db2 <<!
connect to database
set write suspend for database
quit
```

Note that to allow recovery from any backups taken from snapshots, the database must be in LOGRETAIN RECOVERY mode.

Refresh the contents of the snapshot volumes from the original volume using the following command:

```
# vxsnap -g database_dg refresh snapvol1 source=database_vol1 \
  [snapvol2 source=database vol2]...
```

For example, to refresh the snapshots *snapvol1*, *snapvol2* and *snapvol3*:

```
# vxsnap -g database_dg refresh snapvol1 source=database_vol1 \
 snapvol2 source=database vol2 snapvol3 source=database vol3
```

If you have temporarily suspended updates to volumes, release all the tablespaces or databases from suspend mode. As the DB2 database administrator, use a script such as that shown in the example to resume I/O for a DB2 database.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to resume I/O for a DB2 database.
db2 <<!
connect to database
set write resume for database
```

```
quit
!
```

Back up the snapshot volume. If you need to remount the file system in the volume to back it up, first run fsck on the volume. The following are sample commands for checking and mounting a file system:

```
# fsck -F vxfs /dev/vx/rdsk/database dg/snapvol
# mount -F vxfs /dev/vx/dsk/database dg/snapvol
    mount point
```

Back up the file system at this point using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.

```
# umount mount point
```

5 Repeat steps in this procedure each time that you need to back up the volume.

Backing up a Sybase database on the same host

You can make an online backup of your Sybase database.

To make a backup of an online Sybase database on the same host

If the volumes to be backed up contain database tables in file systems, suspend updates to the volumes. Sybase ASE from version 12.0 onward provides the Quiesce feature to allow temporary suspension of writes to a database. As the Sybase database administrator, put the database in quiesce mode by using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to quiesce example Sybase ASE database.
# Note: The "for external dump" clause was introduced in Sybase
# ASE 12.5 to allow a snapshot database to be rolled forward.
# See the Sybase ASE 12.5 documentation for more information.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag hold database1[, database2]... [for external dump]
αo
quit
```

Refresh the contents of the snapshot volumes from the original volume using the following command:

```
# vxsnap -g database dg refresh snapvol source=database vol \
  [snapvol2 source=database vol2]...
```

For example, to refresh the snapshots snapvol1, snapvol2 and snapvol3:

```
# vxsnap -g database dg refresh snapvol1 source=database vol1 \
 snapvol2 source=database vol2 snapvol3 source=database vol3
```

If you have temporarily suspended updates to volumes, release all the tablespaces or databases from quiesce mode.

As the Sybase database administrator, release the database from quiesce mode using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to release example Sybase ASE database from
# quiesce mode.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag release
αo
quit
!
```

Back up the snapshot volume. If you need to remount the file system in the volume to back it up, first run fsck on the volume. The following are sample commands for checking and mounting a file system:

```
# fsck -F vxfs /dev/vx/rdsk/database dg/snapvol
# mount -F vxfs /dev/vx/dsk/database dg/snapvol
    mount point
```

Back up the file system at this point using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.

```
# umount mount_point
```

5 Repeat steps in this procedure each time that you need to back up the volume.

Resynchronizing a volume

In some instances, such as recovering the contents of a corrupted volume, it may be useful to resynchronize a volume from its snapshot volume (which is used as a hot standby).

To resynchronize a volume from its snapshot volume

Enter:

```
# vxsnap -g diskgroup restore database vol source=snapvol \
   destroy=ves|no
```

The destroy attribute specifies whether the plexes of the snapshot volume are to be reattached to the original volume. For example, to resynchronize the volume database vol from its snapshot volume snapvol without removing the snapshot volume:

```
# vxsnap -g database dg restore database vol \
  source=snapvol destroy=no
```

Note: You must shut down the database and unmount the file system that is configured on the original volume before attempting to resynchronize its contents from a snapshot.

Making an off-host backup of an online database

Figure 7-2 shows an example of two primary database volumes to be backed up, database_vol and dbase_logs, which are configured on disks attached to controllers c1 and c2, and the snapshots to be created on disks attached to controllers c3 and c4.

There is no requirement for the off-host processing host to have access to the disks that contain the primary database volumes.

Network Primary host for database OHP host disks disks Controllers Controllers c2 с4 c1 с3 с4 с3 Volumes created on these Snapshot volumes created on these disks are accessed by both hosts disks are accessed by the Disk primary host arrays Backup to disk, tape or other media by OHP host

Figure 7-2 Example system configuration for off-host database backup

If the database is configured on volumes in a cluster-shareable disk group, it is assumed that the primary host for the database is the master node for the cluster. However, if the primary host is not also the master node, most VxVM operations on shared disk groups are best performed on the master node.

The procedure in this section is designed to minimize copy-on-write operations that can impact system performance. You can also implement this procedure on a single host by omitting steps 5 through To make an off-host backup of an online Sybase database and 10 through 13 that split, deport, reimport and rejoin the snapshot disk group.

To make an off-host database backup of an online database:

- Prepare the full-sized snapshot for backing up.
- Make the off-host database backup using the steps for DB2 or Sybase. See "Making an off-host backup of an online DB2 database" on page 112. See "Making an off-host backup of an online Sybase database" on page 117.
- Resynchronize a volume if required. See "Resynchronizing a volume" on page 115.

Making an off-host backup of an online DB2 database

To start an off-host backup of an online DB2 database

On the primary host, add one or more snapshot plexes to the volume using this command:

```
# vxsnap -g database dg addmir database vol [nmirror=N] \
[alloc=storage attributes]
```

By default, one snapshot plex is added unless you specify a number using the nmirror attribute. For a backup, you should usually only require one plex. You can specify storage attributes (such as a list of disks) to determine where the plexes are created.

Suspend updates to the volumes. DB2 provides the write suspend command to temporarily suspend I/O activity for a database. As the DB2 database administrator, use a script such as that shown in the example to suspend I/O for a DB2 database.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to suspend I/O for a DB2 database.
# Note: To recover a database using backups of snapshots,
# the database must be in LOGRETAIN mode.
db2 <<!
connect to database
set write suspend for database
quit
!
```

Note that to allow recovery from any backups taken from snapshots, the database must be in LOGRETAIN RECOVERY mode.

Make a full-sized snapshot, *snapvol*, of the tablespace volume by breaking off the plexes that you added in step 1 from the original volume:

```
# vxsnap -q database dq make \
   source=database_vol/newvol=snapvol/nmirror=N \
   [alloc=storage attributes]
```

The nmirror attribute specifies the number of mirrors, N, in the snapshot volume.

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database_dg \
   make source=database vol1/snapvol=snapvol1 \
   source=database vol/snapvol=snapvol2 \
   source=database vol/snapvol=snapvol3 alloc=ctlr:c3,ctlr:c4
```

- This step sets up the snapshot volumes ready for the backup cycle, and starts tracking changes to the original volumes.
- Release all the tablespaces or databases from suspend mode. As the DB2 database administrator, use a script such as that shown in the example. to resume I/O for a DB2 database.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to resume I/O for a DB2 database.
db2 <<!
connect to database
set write resume for database
quit
!
```

6 On the primary host, split the disks containing the snapshot volumes into a separate disk group, snapvoldg, from the original disk group, database_dg using the following command:

```
# vxdg split database dg snapvoldg snapvol ...
```

- 7 On the primary host, deport the snapshot volume's disk group using the following command:
 - # vxdg deport snapvoldg
- 8 On the OHP host where the backup is to be performed, use the following command to import the snapshot volume's disk group:
 - # vxdg import snapvoldg
- **9** VxVM recovers the volumes automatically after the disk group import unless it is set to not recover automatically. Check if the snapshot volume is initially disabled and not recovered following the split.

If a volume is in the DISABLED state, use the following command on the off-host processing host to recover and restart the snapshot volume:

- # vxrecover -g snapvoldg -m snapvol ...
- 10 On the off-host processing host, back up the snapshot volumes. If you need to remount the file system in the volume to back it up, first run fsck on the volumes. The following are sample commands for checking and mounting a file system:
 - # fsck -F vxfs /dev/vx/rdsk/snapvoldg/snapvol
 # mount -F vxfs /dev/vx/dsk/snapvoldg/snapvol mount point

Back up the file system using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.

- # umount mount point
- 11 On the OHP host, use the following command to deport the snapshot volume's disk group:
 - # vxdq deport snapvoldq
- **12** On the primary host, re-import the snapshot volume's disk group using the following command:
 - # vxdg [-s] import snapvoldg

Note: Specify the -s option if you are reimporting the disk group to be rejoined with a shared disk group in a cluster.

13 On the primary host, use the following command to rejoin the snapshot volume's disk group with the original volume's disk group:

```
# vxdq join snapvoldq database dq
```

14 VxVM will recover the volumes automatically after the join unless it is set not to recover automatically. Check if the snapshot volumes are initially disabled and not recovered following the join.

If a volume is in the DISABLED state, use the following command on the primary host to recover and restart the snapshot volume:

```
# vxrecover -g database_dg -m snapvol
```

15 On the primary host, reattach the snapshot volumes to their original volume. Reattach of multiple volumes in a single command is not supported. Split it into multiple invocations:

```
# vxsnap -g database dg reattach snapvol1 source=database vol1
# vxsnap -g database dg reattach snapvol2 source=database vol2
# vxsnap -g database dg reattach snapvol3 source=database vol3
```

Use the following commands to wait for synchronization to complete:

```
# vxsnap -g database dg snapwait database vol1
# vxsnap -g database dg snapwait database vol2
# vxsnap -g database dg snapwait database vol3
```

For example, to reattach the snapshot volumes snapvol1, snapvol2 and snapvol3:

```
# vxsnap -g database dg reattach snapvol1 source=database vol1 \
  snapvol2 source=database vol2 snapvol3 source=database vol3
```

While the reattached plexes are being resynchronized from the data in the parent volume, they remain in the SNAPTMP state. After resynchronization is complete, the plexes are placed in the SNAPDONE state. You can use the vxsnap print command to check on the progress of synchronization.

Repeat steps 2 through 15 each time that you need to back up the volume.

Resynchronizing a volume

In some instances, such as recovering the contents of a corrupted volume, it may be useful to resynchronize a volume from its snapshot volume (which is used as a hot standby).

To resynchronize a volume

Use the following command syntax:

```
\verb|vxsnap -g| database | dg| restore | database\_vol | source=snapvol | |
   destroy=yes|no
```

The destroy attribute specifies whether the plexes of the snapshot volume are to be reattached to the original volume.

For example, to resynchronize the volume *database vol* from its snapshot volume snapvol without removing the snapshot volume:

```
# vxsnap -g database dg restore database vol \
  source=snapvol destroy=no
```

Note: You must shut down the database and unmount the file system that is configured on the original volume before attempting to resynchronize its contents from a snapshot.

Making an off-host backup of an online Sybase database

To make an off-host backup of an online Sybase database

On the primary host, add one or more snapshot plexes to the volume using this command:

```
# vxsnap -g database dg addmir database vol [nmirror=N] \
 [alloc=storage attributes]
```

By default, one snapshot plex is added unless you specify a number using the nmirror attribute. For a backup, you should usually only require one plex. You can specify storage attributes (such as a list of disks) to determine where the plexes are created.

Suspend updates to the volumes. As the Sybase database administrator, put the database in quiesce mode by using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to quiesce example Sybase ASE database.
# Note: The "for external dump" clause was introduced in Sybase
# ASE 12.5 to allow a snapshot database to be rolled forward.
# See the Sybase ASE 12.5 documentation for more information.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag hold database1[, database2]... [for
external dump]
go
quit
!
```

Use the following command to make a full-sized snapshot, *snapvol*, of the tablespace volume by breaking off the plexes that you added in step 1 from the original volume:

```
# vxsnap -g database dg make \
  source=database_vol/newvol=snapvol/nmirror=N \
   [alloc=storage attributes]
```

The nmirror attribute specifies the number of mirrors, *N*, in the snapshot volume.

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database dg make source=database vol1/snapvol=snapvol1 \
  source=database vol/snapvol=snapvol2 \
  source=database vol3/snapvol=snapvol3 alloc=ctlr:c3,ctlr:c4
```

This step sets up the snapshot volumes ready for the backup cycle, and starts tracking changes to the original volumes.

Release all the tablespaces or databases from quiesce mode. As the Sybase database administrator, release the database from quiesce mode using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to release example Sybase ASE database from quiesce
# mode.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag release
go
quit
!
```

On the primary host, split the disks containing the snapshot volumes into a separate disk group, snapvoldg, from the original disk group, database dg using the following command:

```
# vxdg split database dg snapvoldg snapvol ...
```

- 6 On the primary host, deport the snapshot volume's disk group using the following command:
 - # vxdq deport snapvoldq
- On the OHP host where the backup is to be performed, use the following command to import the snapshot volume's disk group:
 - # vxdg import snapvoldg
- VxVM will recover the volumes automatically after the disk group import unless it is set to not recover automatically. Check if the snapshot volume is initially disabled and not recovered following the split.
 - If a volume is in the DISABLED state, use the following command on the OHP host to recover and restart the snapshot volume:
 - # vxrecover -g snapvoldg -m snapvol ...
- On the OHP host, back up the snapshot volumes. If you need to remount the file system in the volume to back it up, first run fsck on the volumes. The following are sample commands for checking and mounting a file system:
 - # fsck -F vxfs /dev/vx/rdsk/snapvoldg/snapvol
 - # mount -F vxfs /dev/vx/dsk/snapvoldg/snapvol mount point

Back up the file system using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.

- # umount mount point
- 10 On the OHP host, use the following command to deport the snapshot volume's disk group:
 - # vxdq deport snapvoldq
- 11 On the primary host, re-import the snapshot volume's disk group using the following command:
 - # vxdg [-s] import snapvoldg

Note: Specify the -s option if you are reimporting the disk group to be rejoined with a shared disk group in a cluster.

- 12 On the primary host, use the following command to rejoin the snapshot volume's disk group with the original volume's disk group:
 - # vxdq join snapvoldq database dq
- 13 VxVM will recover the volumes automatically after the join unless it is set not to recover automatically. Check if the snapshot volumes are initially disabled and not recovered following the join.

If a volume is in the DISABLED state, use the following command on the primary host to recover and restart the snapshot volume:

- # vxrecover -g database dg -m snapvol
- 14 On the primary host, reattach the snapshot volumes to their original volume using the following command:
 - # vxsnap -g database dg reattach snapvol source=database vol \ [snapvol2 source=database vol2]...

For example, to reattach the snapshot volumes *snapvol1*, *snapvol2* and snapvol3:

vxsnap -g database dg reattach snapvol1 source=database vol1 \ snapvol2 source=database vol2 snapvol3 source=database vol3

While the reattached plexes are being resynchronized from the data in the parent volume, they remain in the SNAPTMP state. After resynchronization is complete, the plexes are placed in the SNAPDONE state. You can use the vxsnap print command to check on the progress of synchronization.

Repeat steps 2 through 14 each time that you need to back up the volume.

Backing up on an off-host cluster file system

Storage Foundation Cluster File System High Availability (SFCFSHA) allows cluster nodes to share access to the same file system. SFCFSHA is especially useful for sharing read-intensive data between cluster nodes.

Off-host backup of cluster file systems may be implemented by taking a snapshot of the volume containing the file system and performing the backup operation on a separate host.

Figure 7-3 shows an example where the primary volume that contains the file system to be backed up is configured on disks attached to controllers c1 and c2, and the snapshots are to be created on disks attached to controllers *c*3 and *c*4.




Figure 7-3 System configuration for off-host file system backup scenarios

To set up an off-host cluster file system backup:

- Mount a VxFS file system for shared access by the nodes of a cluster. See "Mounting a file system for shared access" on page 122.
- Prepare a snapshot of the mounted file system with shared access.
- Back up a snapshot of a mounted file system with shared access See "Backing up a snapshot of a mounted file system with shared access" on page 124.
- All commands require superuser (root) or equivalent privileges.

Mounting a file system for shared access

To mount a VxFS file system for shared access, use the following command on each cluster node where required:

```
# mount -F vxfs -o cluster /dev/vx/dsk/database dg/database vol
  mount point
```

For example, to mount the volume *database_vol* in the disk group *database_dg* for shared access on the mount point, /mnt pnt:

```
# mount -F vxfs -o cluster /dev/vx/dsk/database dg/database vol /mnt pnt
```

Preparing a snapshot of a mounted file system with shared access

You must use a full-sized snapshot for your off-host backup.

Warning: To avoid data inconsistencies, do not use the same snapshot with different point-in-time copy applications. If you require snapshot mirrors for more than one application, configure at least one snapshot mirror that is dedicated to each application.

To prepare to back up a snapshot of a mounted file system which has shared access

On the master node, use the following command to make a full-sized snapshot, snapvol, of the volume containing the file system by breaking off plexes from the original volume:

```
# vxsnap -g database dg make \
 source=database vol/newvol=snapvol/nmirror=N
```

The nmirror attribute specifies the number of mirrors, N, in the snapshot volume.

For example, to take a snapshot of the volume *database vol* in the shared disk group exampledg:

```
# vxsnap -q database dq make source=database vol/newvol=snapvol
/nmirror=1
```

If the volume does not have any available plexes, or its layout does not support plex break-off, prepare an empty volume for the snapshot.

Use the vxprint command on the original volume to find the required size for the snapshot volume.

```
# LEN='vxprint [-g database dg] -F%len database vol'
```

Note: The command shown in this and subsequent steps assumes that you are using a Bourne-type shell such as sh, ksh or bash. You may need to modify the command for other shells such as csh or tcsh. These steps are valid only for instant snap DCOs.

- Use the vxprint command on the original volume to discover the name of its DCO:
 - # DCONAME='vxprint [-g database dg] -F%dco name database vol'
- Use the vxprint command on the DCO to discover its region size (in blocks):
 - # RSZ='vxprint [-g database dg] -F%regionsz \$DCONAME'
- Use the vxassist command to create a volume, snapvol, of the required size and redundancy, together with an instant snap DCO volume with the correct region size:
 - # vxassist [-g database_dg] make snapvol \$LEN \ [layout=mirror nmirror=number] logtype=dco drl=no \ dcoversion=20 [ndcomirror=number] regionsz=\$RSZ \ init=active [storage attributes]

It is recommended that you specify the same number of DCO mirrors (ndcomirror) as the number of mirrors in the volume (nmirror). The init=active attribute is used to make the volume available immediately. You can use storage attributes to specify which disks should be used for the volume.

As an alternative to creating the snapshot volume and its DCO volume in a single step, you can first create the volume, and then prepare it for instant snapshot operations as shown here:

```
# vxassist [-g database_dg] make snapvol $LEN \
  [layout=mirror nmirror=number] init=active \
  [storage attributes]
# vxsnap [-g database dg] prepare snapvol [ndcomirs=number] \
 regionsz=$RSZ [storage attributes]
```

- Then use the following command to create the snapshot:
 - # vxsnap -g database_dg make source=database_dg/snapvol=snapvol

Note: This step actually takes the snapshot and sets up the snapshot volumes ready for the backup cycle, and starts tracking changes to the original volumes.

When you are ready to make a backup, proceed to step 1.

Backing up a snapshot of a mounted file system with shared access

While you can run the commands in the following steps from any node, Symantec recommends running them from the master node.

To back up a snapshot of a mounted file system which has shared access

- On any node, refresh the contents of the snapshot volumes from the original volume using the following command:
 - # vxsnap -g database dg refresh snapvol source=database vol \ [snapvol2 source=database vol2]... syncing=yes

The syncing=yes attribute starts a synchronization of the snapshot in the background.

For example, to refresh the snapshot *snapvol*:

vxsnap -g database dg refresh snapvol source=database vol \ syncing=yes

This command can be run every time you want to back up the data. The vxsnap refresh command will resync only those regions which have been modified since the last refresh.

- On any node of the cluster, use the following command to wait for the contents of the snapshot to be fully synchronous with the contents of the original volume:
 - # vxsnap -g database dg syncwait snapvol

For example, to wait for synchronization to finish for the snapshots *snapvol*:

vxsnap -g database_dg syncwait snapvol

Note: You cannot move a snapshot volume into a different disk group until synchronization of its contents is complete. You can use the vxsnap print command to check on the progress of synchronization.

On the master node, use the following command to split the snapshot volume into a separate disk group, snapvoldg, from the original disk group, database dg:

```
# vxdg split volumedg
      snapvoldg
      snapvol
```

For example, to place the snapshot of the volume *database vol* into the shared disk group splitdg:

```
# vxdg split database dg splitdg snapvol
```

On the master node, deport the snapshot volume's disk group using the following command:

```
# vxdg deport snapvoldg
```

For example, to deport the disk group splitdg:

```
# vxdg deport splitdg
```

5 On the OHP host where the backup is to be performed, use the following command to import the snapshot volume's disk group:

```
# vxdg import snapvoldg
```

For example, to import the disk group splitdg:

```
# vxdg import splitdg
```

VxVM will recover the volumes automatically after the disk group import unless it is set not to recover automatically. Check if the snapshot volume is initially disabled and not recovered following the split.

If a volume is in the DISABLED state, use the following command on the OHP host to recover and restart the snapshot volume:

```
# vxrecover -g snapvoldg -m snapvol
```

For example, to start the volume *snapvol*:

```
# vxrecover -g splitdg -m snapvol
```

- On the OHP host, use the following commands to check and locally mount the snapshot volume:
 - # fsck -F vxfs /dev/vx/rdsk/database dg/database vol
 - # mount -F vxfs /dev/vx/dsk/database dg/database vol mount point

For example, to check and mount the volume *snapvol* in the disk group snapvoldg for shared access on the mount point, /bak/mnt pnt:

- Back up the file system at this point using a command such as bpbackup in Symantec NetBackup. After the backup is complete, use the following command to unmount the file system.
 - # umount mount point
- On the off-host processing host, use the following command to deport the snapshot volume's disk group:
 - # vxdg deport snapvoldg

For example, to deport *snapvoldg*:

- # vxdq deport snapvoldq
- 10 On the master node, re-import the snapshot volume's disk group as a shared disk group using the following command:
 - # vxdg -s import snapvoldg

For example, to import *snapvoldg*:

- # vxdg -s import snapvoldg
- 11 On the master node, use the following command to rejoin the snapshot volume's disk group with the original volume's disk group:
 - # vxdg join snapvoldg database_dg

For example, to join disk group *snapvoldg* with *database dg*:

vxdg join snapvoldg database dg

12 VxVM will recover the volumes automatically after the join unless it is set not to recover automatically. Check if the snapshot volumes are initially disabled and not recovered following the join.

If a volume is in the DISABLED state, use the following command on the primary host to recover and restart the snapshot volume:

- # vxrecover -g database dg -m snapvol
- 13 When the backup is complete, use the following command to unmount the snapshot volume, and make it ready for its contents to be refreshed from the primary volume:
 - # umount mount point

When synchronization is complete, the snapshot is ready to be re-used for backup.

Warning: Before attempting to unmount the snapshot, shut down all applications that access a file system in the snapshot volume, and also unmount any such file system.

Repeat the entire procedure each time that you need to back up the volume.

Resynchronizing a volume from its snapshot volume

In some instances, such as recovering the contents of a corrupted volume, it may be useful to resynchronize a volume from its snapshot volume (which is used as a hot standby).

To resynchronize a volume from its snapshot volume

Enter:

```
vxsnap -q database dg restore database vol source=snapvol \
   destroy=yes|no
```

The destroy attribute specifies whether the plexes of the snapshot volume are to be reattached to the original volume. For example, to resynchronize the volume database vol from its snapshot volume snapvol without removing the snapshot volume:

vxsnap -g database dg restore database vol source=snapvol destroy=no

Note: You must unmount the file system that is configured on the original volume before attempting to resynchronize its contents from a snapshot.

Reattaching snapshot plexes

Some or all plexes of an instant snapshot may be reattached to the specified original volume, or to a source volume in the snapshot hierarchy above the snapshot volume.

Note: This operation is not supported for space-optimized instant snapshots.

By default, all the plexes are reattached, which results in the removal of the snapshot. If required, the number of plexes to be reattached may be specified as the value assigned to the nmirror attribute.

Note: The snapshot being reattached must not be open to any application. For example, any file system configured on the snapshot volume must first be unmounted.

To reattach a snapshot

Use the following command to reattach an instant snapshot to the specified original volume, or to a source volume in the snapshot hierarchy above the snapshot volume:

```
vxsnap [-q database dq] reattach snapvol source=database vol \
  [nmirror=number]
```

For example the following command reattaches 1 plex from the snapshot volume, snapvol, to the volume, database vol:

```
# vxsnap -g database dg reattach snapvol source=database vol nmirror=1
```

While the reattached plexes are being resynchronized from the data in the parent volume, they remain in the SNAPTMP state. After resynchronization is complete, the plexes are placed in the SNAPDONE state.

The vxsnap refresh and vxsnap reattach commands have slightly different behaviors.

The vxsnap reattach command reattaches a snapshot volume to its source volume and begins copying the volume data to the snapshot volume.

The vxsnap refresh commands updates the snapshot volumes contents view. The updated snapshot is available immediately with the new contents while synchronization occurs in the background.

Database recovery using Storage Checkpoints

You can use Storage Checkpoints to implement efficient backup and recovery of databases that have been laid out on VxFS file systems. A Storage Checkpoint allows you to roll back an entire database, a tablespace, or a single database file to the time that the Storage Checkpoint was taken. Rolling back to or restoring from any Storage Checkpoint is generally very fast because only the changed data blocks need to be restored.

Storage Checkpoints can also be mounted, allowing regular file system operations to be performed or secondary databases to be started.

For information on how to administer Storage Checkpoints, see Veritas Storage Foundation™ Administrator's Guide.

For information on how to administer Database Storage Checkpoints for an Oracle database, see *Veritas Storage Foundation™*: Storage and High Availability Mangement for Oracle Databases.

Note: Storage Checkpoints can only be used to restore from logical errors such as human mistakes or software faults. You cannot use them to restore files after a disk failure because all the data blocks are on the same physical device. Disk failure requires restoration of a database from a backup copy of the database files kept on a separate medium. Combining data redundancy (for example, disk mirroring) with Storage Checkpoints is recommended for highly critical data to protect against both physical media failure and logical errors.

Storage Checkpoints require space in the file systems where they are created, and the space required grows over time as copies of changed file system blocks are made. If a file system runs out of space, and there is no disk space into which the file system and any underlying volume can expand, VxFS automatically removes the oldest Storage Checkpoints if they were created with the removable attribute.

Creating Storage Checkpoints

To create Storage Checkpoints, select 3 Storage Checkpoint Administration > Create New Storage Checkpoints in the VxDBA utility. This can be done with a database either online or offline.

Note: To create a Storage Checkpoint while the database is online, ARCHIVELOG mode must be enabled in Oracle. During the creation of the Storage Checkpoint, the tablespaces are placed in backup mode. Because it only takes a few seconds to take a Storage Checkpoint, the extra redo logs generated while the tablespaces are in online backup mode are very small. To optimize recovery, it is recommended that you keep ARCHIVELOG mode enabled.

Warning: Changes to the structure of a database, such as the addition or removal of datafiles, make Storage Rollback impossible if they are made after a Storage Checkpoint was taken. A backup copy of the control file for the database is saved under the /etc/vx/vxdba/ORACLE SID/checkpoint dir directory immediately after a Storage Checkpoint is created. If necessary, you can use this file to assist with database recovery. If possible, both an ASCII and binary copy of the control file are made, with the binary version being compressed to conserve space. Use extreme caution if you attempt to recover your database using these control files. It is recommended that you remove old Storage Checkpoints and create new ones whenever you restructure a database.

Rolling back a database

The procedure in this section describes how to roll back a database using a Storage Checkpoint, for example, after a logical error has occurred.

To roll back a database

- Ensure that the database is offline. You can use the VxDBA utility to display the status of the database and its tablespaces, and to shut down the database:
 - Select 2 Display Database/VxDBA Information to access the menus that display status information.
 - Select 1 Database Administration > Shutdown Database Instance to shut down a database.
- Select 4 Storage Rollback Administration > Roll Back the Database to a Storage Checkpoint in the VxDBA utility, and choose the appropriate Storage Checkpoint. This restores all data files used by the database, except redo logs and control files, to their state at the time that the Storage Checkpoint was made.
- Start up, but do not open, the database instance by selecting 1 Database Administration > Startup Database Instance in the VxDBA utility.
- Use one of the following commands to perform an incomplete media recovery of the database:
 - Recover the database until you stop the recovery:

```
recover database until cancel;
alter database [database] recover cancel;
```

■ Recover the database to the point just before a specified system change number, scn:

```
recover database until change scn;
```

■ Recover the database to the specified time:

```
recover database until time 'yyyy-mm-dd:hh:mm:ss';
```

■ Recover the database to the specified time using a backup control file:

```
recover database until time 'yyyy-mm-dd:hh:mm:ss' \
using backup controlfile;
```

Note: To find out when an error occurred, check the ../bdump/alert*.log file.

See the Oracle documentation for complete and detailed information on database recovery.

To open the database after an incomplete media recovery, use the following command:

alter database open resetlogs;

Note: The resetlogs option is required after an incomplete media recovery to reset the log sequence. Remember to perform a full database backup and create another Storage Checkpoint after log reset.

Perform a full database backup, and use the VxDBA utility to remove any existing Storage Checkpoints that were taken before the one to which you just rolled back the database. These Storage Checkpoints can no longer be used for Storage Rollback. If required, use the VxDBA utility to delete the old Storage Checkpoints and to create new ones.

Chapter 8

Backing up and recovering in a NetBackup environment

This chapter includes the following topics:

- About Veritas NetBackup
- About using Veritas NetBackup for backup and restore for DB2
- About using NetBackup for backup and restore for Sybase
- About using Veritas NetBackup to backup and restore Quick I/O files for DB2
- About using Veritas NetBackup to backup and restore Quick I/O files for Sybase
- Using NetBackup in an SFHA Solutions product environment

About Veritas NetBackup

Veritas NetBackup provides backup, archive, and restore capabilities for database files and directories contained on client systems in a client-server network. NetBackup server software resides on platforms that manage physical backup storage devices. The NetBackup server provides robotic control, media management, error handling, scheduling, and a repository of all client backup images.

Administrators can set up schedules for automatic, unattended full and incremental backups. These backups are managed entirely by the NetBackup server. The administrator can also manually back up clients. Client users can

perform backups, archives, and restores from their client system, and once started, these operations also run under the control of the NetBackup server.

Veritas NetBackup can be configured for DB2 in an Extended Edition (EE) or Extended-Enterprise Edition (EEE) environment. For detailed information and instructions on configuring DB2 for EEE, see "Configuring for a DB2 EEE (DPF) Environment" in the Veritas NetBackup for DB2 System Administrator's Guide for UNIX.

Veritas NetBackup, while not a shipped component of Veritas Storage Foundation Enterprise products, can be purchased separately.

About using Veritas NetBackup for backup and restore for DB2

With Veritas NetBackup, you can perform high performance, online (hot) backups of databases that must be available on a 24x7 basis. NetBackup supports the Extended Edition (EE) and the Enterprise Extended Edition (EEE) environments. NetBackup also supports Database Partitioning Feature (DPF) for DB2 8.1 and higher.

Veritas NetBackup enables you to back up and restore database files and directories. You can set up schedules for automatic, unattended database backup, as well as full or incremental backup. These backups are managed entirely by the NetBackup server. You can also manually back up database files from any of the NetBackup clients. Client users can perform database backups and restores from their client systems on demand.

Veritas NetBackup can be configured for DB2 in an Extended Edition (EE), Extended-Enterprise Edition (EEE), or Database Partitioning Feature (DPF) environment. Two types of DB2 backup policies are required. One is used to backup the catalog nodes and the other is used to backup all the nodes, including the catalog node. Detailed information and instructions on configuring DB2 for EEE is available in the system administrator's guide.

See the Veritas NetBackup for DB2 System Administrator's Guide for UNIX.

Veritas NetBackup for DB2 has the following features:

- Media and device management
- Scheduling facilities
- Multiplexed backups and restores
- Transparent execution of both DB2 and regular file system backup and restore operations

- Shared devices and tapes used during other file backups
- Centralized and networked backup operations
- Parallel backup and restore operations
- Incremental backups of DB2 databases

Table 8-1 Options for backing up DB2 with NetBackup

	Automatically	Manually	DB2 BACKUP DATABASE command
DB2 database log backups	Supported	Supported	Supported
DB2 archive log backups	Supported	Supported	Supported
DB2 policy backups	Supported	Supported	

Setting up schedules for automatic backups is the most convenient way to back up your database.

See 'Performing a Backup' in the Veritas NetBackup for DB2 System Administrator's Guide for UNIX.

The procedure for restoring a DB2 database depends on the database involved and the problems that you have on your system. You can browse the backups using the db2 list history command or using the NetBackup bplist command before restoring.

See the DB2 UDB Administration Guide Data Recovery and High Availability Guide.

About using NetBackup for backup and restore for **Sybase**

Veritas NetBackup for Sybase is not included in the standard Veritas Database Edition. The information included here is for reference only.

Veritas NetBackup for Sybase integrates the database backup and recovery capabilities of Sybase Backup Server with the backup and recovery management capabilities of NetBackup.

Veritas NetBackup works with Sybase APIs to provide high-performance backup and restore for Sybase dataservers. With Veritas NetBackup, you can set up schedules for automatic, unattended backups for Sybase ASE dataservers (NetBackup clients) across the network. These backups can be full database dumps or incremental backups (transaction logs) and are managed by the NetBackup

server. You can also manually backup dataservers. The Sybase dump and load commands are used to perform backups and restores.

Veritas NetBackup has both graphical and menu driven user interfaces to suit your needs.

For details, refer to Veritas NetBackup System Administrator's Guide for UNIX.

About using Veritas NetBackup to backup and restore Quick I/O files for DB2

Veritas NetBackup does not follow symbolic links when backing up files. Typical backup management applications are designed this way to avoid backing up the same data twice. This would happen if both the link and the file it points to were included in the list of files to be backed up.

A Quick I/O file consists of two components: a hidden file with the space allocated for it, and a link that points to the Quick I/O interface of the hidden file. Because NetBackup does not follow symbolic links, you must specify both the Quick I/O link and its hidden file in the list of files to be backed up.

To view all files and their attributes in the db01 directory:

```
$ ls -la /db01
total 2192
drwxr-xr-x 2 root root 96 Oct 20 17:39
drwxr-xr-x 9 root root 8192 Oct 20 17:39 ...
-rw-r--r 1 db2 dba 1048576 Oct 20 17:39 .dbfile
lrwxrwxrwx 1 db2 dba 22 Oct 20 17:39 dbfile ->\
.dbfile::cdev:vxfs:
```

In the example above, you must include both the symbolic link dbfile and the hidden file .dbfile in the file list of the backup class.

If you want to back up all Quick I/O files in a directory, you can simplify the process by just specifying the directory to be backed up. In this case, both components of each Quick I/O file will be properly backed up. In general, you should specify directories to be backed up unless you only want to back up some, but not all files, in those directories.

Because NetBackup is tightly integrated with the Veritas Database Edition for DB2, NetBackup backs up extent attributes of a Quick I/O file and restores them

accordingly. Quick I/O files can then be backed up and restored as regular files using NetBackup, while preserving the Quick I/O file's extent reservation. Without this feature, restoring the file could cause the loss of contiguous reservation, which can degrade performance.

When restoring a Quick I/O file, if both the symbolic link and the hidden file already exist, NetBackup will restore both components from the backup image. If either one of or both of the two components are missing, NetBackup creates or overwrites as needed.

About using Veritas NetBackup to backup and restore Quick I/O files for Sybase

Veritas NetBackup does not follow symbolic links when backing up files. Typical backup management applications are designed this way to avoid backing up the same data twice. This would happen if both the link and the file it points to were included in the list of files to be backed up.

A Quick I/O file consists of two components; a hidden file with the space allocated for it, and a link that points to the Quick I/O interface of the hidden file. Because NetBackup does not follow symbolic links, you must specify both the Quick I/O link and its hidden file in the list of files to be backed up.

To view all files and their attributes in the db01 directory:

```
$ ls -la /db01
total 2192
drwxr-xr-x 2 root root 96 Oct 20 17:39
           9 root root 8192 Oct 20 17:39
drwxr-xr-x
-rw-r--r- 1 db2 dba 1048576 Oct 20 17:39 .dbfile
           1 db2
                  dba 22 Oct 20 17:39 dbfile ->\
lrwxrwxrwx
.dbfile::cdev:vxfs:
```

In the example above, you must include both the symbolic link dbfile and the hidden file .dbfile in the file list of the backup class.

If you want to back up all Quick I/O files in a directory, you can simplify the process by just specifying the directory to be backed up. In this case, both components of each Quick I/O file will be properly backed up. In general, you should specify directories to be backed up unless you only want to back up some, but not all files, in those directories.

When restoring a Quick I/O file, if both the symbolic link and the hidden file already exist, NetBackup will restore both components from the backup image. If either one of or both of the two components are missing, NetBackup creates or overwrites as needed.

Using NetBackup in an SFHA Solutions product environment

You can enhance the ease of use and efficiency of your SFHA Solutions product and NetBackup by integrating them as follows:

- Clustering a NetBackup Master Server
- Backing up and recovering a VxVM volume using NetBackup

Clustering a NetBackup Master Server

To enable your NetBackup Master Server to be highly available in a cluster environment, use the following procedure.

To make a NetBackup Master Server, media, and processes highly available

- Verify that your versions of NetBackup and Veritas Cluster Server are compatible. Detailed combination information is included in the NetBackup cluster compatibility list:
 - For NetBackup 7.x cluster compatibility: http://www.symantec.com/business/support/index?page=content&id=TECH126902
 - For NetBackup 6.x cluster compatibility: See http://www.symantec.com/business/support/index?page=content&id=TECH43619
 - For NetBackup 5.x cluster compatibility: http://www.symantec.com/business/support/index?page=content&id=TECH29272
 - For more on NetBackup compatibility, see http://www.symantec.com/business/support/index?page=landing&key=15145
- The steps to cluster a Master Server are different for different versions of NetBackup. See the applicable NetBackup guide for directions.
 - For NetBackup 7.x: See Symantec NetBackup Clustered Master Server Administrator's Guide See http://www.symantec.com/docs/DOC3679

■ For NetBackup 7.0.1:

See Symantec NetBackup Clustered Master Server Administrator's Guide 7.0.1

See http://www.symantec.com/docs/DOC135520

- For NetBackup 7.0:
 - See NetBackup High Availability Guide 7.0 See http://www.symantec.com/docs/DOC127045
- For NetBackup 6.5: See NetBackup High Availability Guide 6.5 See http://www.symantec.com/docs/DOC52835
- For more on NetBackup documentation, see http://www.symantec.com/business/support/index?page=landing&key=15145

To verify the robustness of the VCS resources and NetBackup processes

- Verify that you can online the Netbackup master.
- 2 Verify that you can offline the Netbackup master.
- 3 Verify that you can monitor all the NetBackup resources.

Backing up and recovering a VxVM volume using NetBackup

To enable NetBackup to backup objects on a VxVM volume, use the following procedure. This procedure enables an Instant Recovery (IR) using a VxVM volume.

To back up objects in a VxVM volume using NetBackup

Create a VxVM disk group with six disks. The number of disks may vary depending on the volume size, disk size, volume layout, and snapshot method.

If the system this test is running on is a clustered system, create a shared disk group using the -s option.

```
# vxdg -s init database dg disk1 disk2 disk3 \
disk4 disk5 disk6
```

2 Create a "mirror-striped" VxVM volume with a size of 10 Gbytes or the maximum size of the disk, whichever is larger.

```
# vxassist -g database dg make vol name 10G \
layout=mirror-stripe init=active
# vxvol -g database dg set fastresync=on vol name
# vxassist -g database dg snapstart nmirror=1 vol name
```

Note: There are three types of snapshot: mirror, full-size instant, and space-optimized instant shanpshots. The example uses an Instant Recovery (IR) snapshot. For snapshot creation details:

See pages 104-107 of the NetBackup Snapshot Client Administrator's Guide for 7.1.

See http://www.symantec.com/docs/DOC3661

- 3 Make the file system on the volume.
- Mount a VxFS file system on the volume.

If the VxVM volume is a clustered volume, mount the VxFS file system with the "-o cluster" option.

- Fill up the VxFS file system up to the desired level. For example, you can fill to 95% full, or to whatever level is appropriate for your file system.
- Store the cksum(1) for these files.
- 7 Un-mount the VxFS file system.
- 8 Enable the following Advanced Client option:
 - Perform Snapshot Backup.
 - Set Advanced Snapshot Options to vxvm.

- **■** Enable **Retain snapshots for instant recovery**.
- Back up the VxVM volume with the NetBackup policy.

See pages 98-101 of the NetBackup Snapshot Client Administrator's Guide for 7.1.

See http://www.symantec.com/docs/DOC3661

Recovering a VxVM volume using NetBackup

To enable NetBackup to recover objects on a VxVM volume, use the following procedure. This procedure performs an Instant Recovery (IR) using a VxVM volume.

To recover objects in a VxVM volume using NetBackup

- Initialize the VxVM volume to zeros.
- 2 Recover the VxVM volume to the newly initialized VxVM volume.
- 3 Mount the VxFS file system on the empty VxVM volume.
- Verify the cksum(1) values against the files recovered.

142 | Backing up and recovering in a NetBackup environment Using NetBackup in an SFHA Solutions product environment

Chapter 9

Off-host processing

This chapter includes the following topics:

- Storage Foundation off-host processing methods
- Using a replica database for decision support
- What is off-host processing?
- About using VVR for off-host processing

Storage Foundation off-host processing methods

While backup and recovery is an important use case for Storage Foundation point-in-time copy methods, they can also be used for:

- Periodic analysis (mining) of production data
- Predictive what-if analysis
- Software testing against real data
- Application or database problem diagnosis and resolution

Off-host processing use cases are similar to the backup use case in that they generally require consistent images of production data sets. They differ from backup in the three important respects:

- Access mode Whereas backup is a read-only activity, most off-host processing activities update the data they process. Thus, Snapshot File Systems are of limited utility for off-host processing uses.
- Multiple uses

 Backup uses each source data image once, after which the snapshot can be discarded. With other use cases, it is often useful to perform several experiments on the same data set. It is possible to take snapshots of both

Storage Checkpoints and Space-Optimized Instant Snapshots of production data. This facility provides multiple identical data images for exploratory applications at almost no incremental overhead. Rather than testing destructively against a snapshot containing the data set state of interest, tests can be run against snapshots of that snapshot. After each test, the snapshot used can be deleted, leaving the original snapshot containing the starting state intact. Any number of tests or analyses can start with the same data, providing comparable alternatives for evaluation. All such tests can be run while production applications simultaneously process live data.

■ Scheduling

Whereas backup is typically a regularly scheduled activity, allowing storage and I/O capacity needs to be planned, other applications of snapshots must run with little or no notice. Full-sized and space-optimized instant snapshots and Storage Checkpoints provide instantly accessible snapshots, and are therefore more suitable for these applications.

Storage Foundation examples for data analysis and off-host processing use cases:

- Decision support
- Active secondary use-case with VVR

Using a replica database for decision support

You can use snapshots of a primary database to create a replica of the database at a given moment in time. You can then implement decision support analysis and report generation operations that take their data from the database copy rather than from the primary database. The FastResync functionality of Veritas Volume Manager (VxVM) allows you to quickly refresh the database copy with up-to-date information from the primary database. Reducing the time taken to update decision support data also lets you generate analysis reports more frequently.

Two methods are described for setting up a replica database for decision support:

- See "Creating a replica database on the same host" on page 145.
- See "Creating an off-host replica database" on page 155.


Note: All commands require superuser (root) or equivalent privileges, except where it is explicitly stated that a command must be run by the database administrator.

Creating a replica database on the same host

Figure 9-1 shows an example where the primary database volumes to be backed up, dbase vol and dbase logs, are configured on disks attached to controllers c1 and c2, and the snapshots are to be created on disks attached to controllers c3 and c4.

Figure 9-1 Example system configuration for decision support on the primary host

Primary host for database



To set up a replica database to be used for decision support on the primary host

- Prepare the snapshot, either full-sized or space-optimized. See "Preparing a full-sized instant snapshot for a backup" on page 100.
- Create snapshot mirrors for volumes containing VxFS file systems for database files to be backed up.
- Make the database replica.
- All commands require superuser (root) or equivalent privileges.

Preparing for the replica database

To prepare a snapshot for a replica database on the primary host

- If you have not already done so, prepare the host to use the snapshot volume that contains the copy of the database tables. Set up any new database logs and configuration files that are required to initialize the database.
- Use the following command to make a full-sized snapshot, *snapvol*, of the tablespace volume by breaking off plexes from the original volume:

```
# vxsnap -g database dg make \
 source=volume/newvol=snapvol/nmirror=N
```

The nmirror attribute specifies the number of mirrors, N, in the snapshot volume.

If the volume does not have any available plexes, or its layout does not support plex break-off, prepare an empty volume for the snapshot.

Use the vxprint command on the original volume to find the required size for the snapshot volume.

```
# LEN='vxprint [-q diskgroup] -F%len volume'
```

Note: The command shown in this and subsequent steps assumes that you are using a Bourne-type shell such as sh, ksh or bash. You may need to modify the command for other shells such as csh or tcsh. These steps are valid only for an instant snap DCO.

Use the vxprint command on the original volume to discover the name of its DCO:

```
DCONAME='vxprint [-g diskgroup] -F%dco name volume'
```

Use the vxprint command on the DCO to discover its region size (in blocks):

```
# RSZ='vxprint [-g diskgroup] -F%regionsz $DCONAME'
```

Use the vxassist command to create a volume, snapvol, of the required size and redundancy, together with an instant snap DCO volume with the correct region size:

```
# vxassist [-g diskgroup] make snapvol $LEN \
  [layout=mirror nmirror=number] logtype=dco drl=no \
 dcoversion=20 [ndcomirror=number] regionsz=$RSZ \
 init=active [storage attributes]
```

It is recommended that you specify the same number of DCO mirrors (ndcomirror) as the number of mirrors in the volume (nmirror). The init=active attribute is used to make the volume available immediately. You can use storage attributes to specify which disks should be used for the volume.

As an alternative to creating the snapshot volume and its DCO volume in a single step, you can first create the volume, and then prepare it for instant snapshot operations as shown here:

```
# vxassist [-q diskgroup] make snapvol $LEN \
  [layout=mirror nmirror=number] init=active \
  [storage attributes]
# vxsnap [-g diskgroup] prepare snapvol [ndcomirs=number] \
 regionsz=$RSZ [storage attributes]
```

To create the snapshot, use the following command:

```
# vxsnap -g database dg make source=volume/snapvol=snapvol
```

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -q database dg make \
source=vol1/snapvol=svol1/nmirror=2 \
source=vol2/snapvol=svol2/nmirror=2 \
source=vol3/snapvol=svol3/nmirror=2
```

If you want to save disk space, you can use the following command to create a space-optimized snapshot instead:

```
# vxsnap -g database dg make \
 source=volume/newvol=snapvol/cache=cacheobject
```

The argument cacheobject is the name of a pre-existing cache that you have created in the disk group for use with space-optimized snapshots.

If several space-optimized snapshots are to be created at the same time, these can all specify the same cache object as shown in this example:

```
# vxsnap -g database dg make \
 source=vol1/newvol=svol1/cache=dbaseco \
 source=vol2/newvol=svol2/cache=dbaseco \
 source=vol3/newvol=svol3/cache=dbaseco
```

- Decide on the following characteristics that you want to allocate to the cache volume that underlies the cache object:
 - The size of the cache volume should be sufficient to record changes to the parent volumes during the interval between snapshot refreshes. A suggested value is 10% of the total size of the parent volumes for a refresh interval of 24 hours.
 - If redundancy is a desired characteristic of the cache volume, it should be mirrored. This increases the space that is required for the cache volume in proportion to the number of mirrors that it has.
 - If the cache volume is mirrored, space is required on at least as many disks as it has mirrors. These disks should not be shared with the disks used for the parent volumes. The disks should also be chosen to avoid impacting I/O performance for critical volumes, or hindering disk group split and join operations.

- ${f 9}$ Having decided on its characteristics, use the <code>vxassist</code> command to create the volume that is to be used for the cache volume. The following example creates a mirrored cache volume, cachevol, with size 1GB in the disk group, mydg, on the disks disk16 and disk17:
 - # vxassist -g mydg make cachevol 1g layout=mirror \ init=active disk16 disk17

The attribute init-active is specified to make the cache volume immediately available for use.

- 10 Use the vxmake cache command to create a cache object on top of the cache volume that you created in the previous step:
 - # vxmake [-g diskgroup] cache cache object \ cachevolname=volume [regionsize=size] [autogrow=on] \ [highwatermark=hwmk] [autogrowby=agbvalue] \ [maxautogrow=maxagbvalue]]

If you specify the region size, it must be a power of 2, and be greater than or equal to 16KB (16k). If not specified, the region size of the cache is set to 64KB.

Note: All space-optimized snapshots that share the cache must have a region size that is equal to or an integer multiple of the region size set on the cache. Snapshot creation also fails if the original volume's region size is smaller than the cache's region size.

If the cache is not allowed to grow in size as required, specify autogrow=off. By default, the ability to automatically grow the cache is turned on.

In the following example, the cache object, cobjmydg, is created over the cache volume, cachevol, the region size of the cache is set to 32KB, and the autogrow feature is enabled:

- # vxmake -g mydg cache cobjmydg cachevolname=cachevol \ regionsize=32k autogrow=on
- 11 Having created the cache object, use the following command to enable it:

```
# vxcache [-g diskgroup] start cache_object
```

For example to start the cache object, cobjmydg:

```
# vxcache -g mydg start cobjmydg
```

Note: This step sets up the snapshot volumes, and starts tracking changes to the original volumes.

Creating a replica database

After you prepare the snapshot, you are ready to create a replica of the database.

To create the replica database

- If the volumes to be backed up contain database tables in file systems, suspend updates to the volumes:
 - DB2 provides the write suspend command to temporarily suspend I/O activity for a database. As the DB2 database administrator, use a script such as that shown in the example. Note that to allow recovery from any backups taken from snapshots, the database must be in LOGRETAIN RECOVERY mode.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to suspend I/O for a DB2 database.
# Note: To recover a database using backups of snapshots,
# the database must be in LOGRETAIN mode.
db2 <<!
connect to database
set write suspend for database
quit
!
```

■ Sybase ASE from version 12.0 onward provides the Quiesce feature to allow temporary suspension of writes to a database. As the Sybase database administrator, put the database in quiesce mode by using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to quiesce example Sybase ASE database.
# Note: The "for external dump" clause was introduced in Sybase
# ASE 12.5 to allow a snapshot database to be rolled forward.
# See the Sybase ASE 12.5 documentation for more information.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag hold database1[, database2]... [for
external dump]
go
```

```
quit
```

If you are using Sybase ASE 12.5, you can specify the for external dump clause to the guiesce command. This warm standby method allows you to update a replica database using transaction logs dumped from the primary database.

See "Updating a warm standby Sybase ASE 12.5 database" on page 165.

Refresh the contents of the snapshot volumes from the original volume using the following command:

```
# vxsnap -g database_dg refresh snapvol source=vol \
  [snapvol2 source=vol2]...
For example, to refresh the snapshots svol1, svol2 and svol3:
# vxsnap -g database dg refresh svol1 source=vol1 \
```

svol2 source=vol2 svol3 source=vol3

If you temporarily suspended updates to volumes in step 1, perform the following steps.

Release all the tablespaces or databases from suspend, hot backup or quiesce mode:

■ As the DB2 database administrator, use a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to resume I/O for a DB2 database.
db2 <<!
connect to database
set write resume for database
quit
!
```

■ As the Sybase database administrator, release the database from quiesce mode using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup_end.sh
# Sample script to release example Sybase ASE database from
# quiesce mode.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag release
αo
quit
```

If you are using Sybase ASE 12.5, you can specify the for external dump clause to the guiesce command. This warm standby method allows you to update a replica database using transaction logs dumped from the primary database.

See "Updating a warm standby Sybase ASE 12.5 database" on page 165.

For each snapshot volume containing tablespaces, check the file system that it contains, and mount the volume using the following commands:

```
# fsck -F vxfs /dev/vx/rdsk/diskgroup/snapvol
# mount -F vxfs /dev/vx/dsk/diskgroup/snapvol
  mount point
```

For example, to check the file system in the snapshot volume snap1 dbase vol, and mount it on /rep dbase vol:

```
# fsck -F vxfs /dev/vx/rdsk/database dg/snap1 dbase vol
# mount -F vxfs /dev/vx/dsk/database dg/snap1 dbase vol \
 /rep dbase vol
```

Copy any required log files from the primary database to the replica database.

For a Sybase ASE database, if you specified the for external dump clause when you quiesced the database, use the following isql command as the database administrator to dump the transaction log for the database:

```
dump transaction to dump device with standby access
```

Then copy the dumped transaction log to the appropriate replica database directory.

- As the database administrator, start the new database:
 - For a Sybase ASE database, use a script such as that shown in the example.

```
#!/bin/ksh
# script: startdb.sh <list of database volumes>
# Sample script to recover and start replica Sybase ASE
# database.
# Import the snapshot volume disk group.
vxdg import $snapvoldg
# Mount the snapshot volumes (the mount points must already
# exist).
for i in $*
do
  fsck -F vxfs /dev/vx/rdsk/$snapvoldg/snap $i
  mount -F vxfs /dev/vx/dsk/$snapvoldg/snap $i \
${rep mnt point}/$i
done
# Start the replica database.
# Specify the -q option if you specified the "for external
# dump" clause when you quiesced the primary database.
# See the Sybase ASE 12.5 documentation for more information.
/sybase/ASE-12 5/bin/dataserver \
[-q] \
-sdatabase name \
-d /sybevm/master \
-e /sybase/ASE-12 5/install/dbasename.log \
-M /sybase
# Online the database. Load the transaction log dump and
# specify "for standby access" if you used the -q option
# with the dataserver command.
isql -Usa -Ppassword -SFMR <<!
[load transaction from dump device with standby access
online database database name [for standby access]
```

```
quit
```

If you are using the warm standby method, specify the -q option to the dataserver command. Use the following isgl commands to load the dump of the transaction log and put the database online:

load transaction from dump device with standby access online database database_name for standby_access

If you are not using the warm standby method, use the following isql command to recover the database, roll back any uncommitted transactions to the time that the quiesce command was issued, and put the database online:

online database database name

When you want to resynchronize a snapshot with the primary database, shut down the replica database, unmount the snapshot volume, and go back to step 1 to refresh the contents of the snapshot from the original volume.

Creating an off-host replica database

Figure 9-2 shows an example where the primary database volumes to be backed up, dbase vol and dbase logs, are configured on disks attached to controllers c1 and c2, and the snapshots are to be created on disks attached to controllers c3 and c4.

There is no requirement for the off-host processing host to have access to the disks that contain the primary database volumes.

Note: If the database is configured on volumes in a cluster-shareable disk group, it is assumed that the primary host for the database is the master node for the cluster. If the primary host is not also the master node, all VxVM operations on shared disk groups must be performed on the master node.

Network Primary host for database OHP host Volumes created on local disks of OHP host are used for the replica database's logs and ≥ Local : configuration files disks disks Controllers Controllers c2 с3 c2 с3 с4 c1 c4 c1 Volumes created on these Snapshot volumes created on disks are accessed by the Disk these disks are accessed by both hosts primary host arrays

Figure 9-2 Example system configuration for off-host decision support

To set up a replica database to be used for decision support on another host

- Prepare the full-sized snapshot. See "Preparing a space-optimized snapshot for a database backup" on page 102.
- Create snapshot mirrors for volumes containing VxFS file systems for database files to be backed up.
- Make the database replica.
- All commands require superuser (root) or equivalent privileges.

Setting up a replica database for off-host decision support

To set up a replica database for off-host decision support

- If you have not already done so, prepare the off-host processing host to use the snapshot volume that contains the copy of the database tables. Set up any new database logs and configuration files that are required to initialize the database.
- On the primary host, use the following command to make a full-sized snapshot, snapvol, of the tablespace volume by breaking off plexes from the original volume:

```
# vxsnap -g database dg make \
 source=volume/newvol=snapvol/nmirror=N
```

The nmirror attribute specifies the number of mirrors, N, in the snapshot volume.

If the volume does not have any available plexes, or its layout does not support plex break-off, prepare an empty volume for the snapshot.

Then use the following command to create the snapshot:

```
# vxsnap -q database dq make source=volume/snapvol=snapvol
```

If a database spans more than one volume, specify all the volumes and their snapshot volumes as separate tuples on the same line, for example:

```
# vxsnap -g database dg make source=vol1/snapvol=svol1 \
source=vol2/snapvol=svol2 source=vol3/snapvol=svol3
```

Note: This step sets up the snapshot volumes, and starts tracking changes to the original volumes.

When you are ready to create the replica database, proceed to step 3.

- If the volumes to be backed up contain database tables in file systems, suspend updates to the volumes:
 - DB2 provides the write suspend command to temporarily suspend I/O activity for a database. As the DB2 database administrator, use a script such as that shown in the example. Note that if the replica database must be able to be rolled forward (for example, if it is to be used as a standby database), the primary database must be in LOGRETAIN RECOVERY mode.

```
#!/bin/ksh
```

```
# script: backup start.sh
# Sample script to suspend I/O for a DB2 database.
# Note: To recover a database using backups of snapshots, the database
# must be in LOGRETAIN mode.
db2 <<!
connect to database
set write suspend for database
quit
```

■ Sybase ASE from version 12.0 onward provides the Quiesce feature to allow temporary suspension of writes to a database. As the Sybase database administrator, put the database in quiesce mode by using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup start.sh
# Sample script to quiesce example Sybase ASE database.
# Note: The "for external dump" clause was introduced in Sybase
# ASE 12.5 to allow a snapshot database to be rolled forward.
# See the Sybase ASE 12.5 documentation for more information.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag hold database1[, database2]... [for external dump]
go
quit
!
```

If you are using Sybase ASE 12.5, you can specify the for external dump clause to the quiesce command. This warm standby method allows you to update a replica database using transaction logs dumped from the primary database.

See "Updating a warm standby Sybase ASE 12.5 database" on page 165.

4 On the primary host, refresh the contents of the snapshot volumes from the original volume using the following command:

```
# vxsnap -q database dq refresh snapvol source=vol \
  [snapvol2 source=vol2]... syncing=yes
```

The syncing=yes attribute starts a synchronization of the snapshot in the background.

For example, to refresh the snapshots svol1, svol2 and svol3:

```
# vxsnap -g database dg refresh svol1 source=vol1 \
   svol2 source=vol2 svol3 source=vol3
```

- If you temporarily suspended updates to volumes in step 3, release all the tablespaces or databases from suspend, hot backup or quiesce mode:
 - As the DB2 database administrator, use a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to resume I/O for a DB2 database.
db2 <<!
connect to database
set write resume for database
quit
!
```

■ As the Sybase database administrator, release the database from quiesce mode using a script such as that shown in the example.

```
#!/bin/ksh
# script: backup end.sh
# Sample script to release example Sybase ASE database from
  quiesce mode.
isql -Usa -Ppassword -SFMR <<!
quiesce database tag release
```

```
go
quit
!
```

Use the following command to wait for the contents of the snapshot to be fully synchronous with the contents of the original volume:

```
# vxsnap -g database dg syncwait snapvol
```

For example, to wait for synchronization to finish for all the snapshots svol1, svol2 and svol3, you would issue three separate commands:

```
# vxsnap -g database dg syncwait svol1
# vxsnap -g database dg syncwait svol2
# vxsnap -g database dg syncwait svol3
```

Note: You cannot move a snapshot volume into a different disk group until synchronization of its contents is complete. You can use the vxsnap print command to check on the progress of synchronization.

On the primary host, use the following command to split the disks containing the snapshot volumes into a separate disk group, snapvoldg, from the original disk group, database dg:

```
# vxdg split database dg snapvoldgsnapvol ...
```

For example to split the snap volumes from *database dg*:

```
# vxdg split database dg snapvoldg svol1 svol2 svol3
```

8 On the primary host, deport the snapshot volume's disk group using the following command:

```
# vxdq deport snapvoldq
```

On the off-host processing host where the replica database is to be set up, use the following command to import the snapshot volume's disk group:

```
# vxdg import snapvoldg
```

10 VxVM will recover the volumes automatically after the disk group import unless it is set to not recover automatically. Check if the snapshot volume is initially disabled and not recovered following the split.

If a volume is in the DISABLED state, use the following command on the off-host processing host to recover and restart the snapshot volume:

```
# vxrecover -q snapvoldg -m snapvol ...
```

11 On the off-host processing host, for each snapshot volume containing tablespaces, check the file system that it contains, and mount the volume using the following commands:

```
# fsck -F vxfs /dev/vx/rdsk/diskgroup/snapvol
# mount -F vxfs /dev/vx/dsk/diskgroup/snapvol
   mount point
```

For example, to check the file system in the snapshot volume snap1 dbase vol, and mount it on /rep/dbase vol:

```
# fsck -F vxfs /dev/vx/rdsk/snapvoldg/snap1 dbase vol
# mount -F vxfs /dev/vx/dsk/snapvoldg/snap1 dbase vol \
 /rep/dbase vol
```

Note: For a replica DB2 database, the database volume must be mounted in the same location as on the primary host.

12 Copy any required log files from the primary host to the off-host processing host.

For a Sybase ASE database on the primary host, if you specified the for external dump clause when you quiesced the database, use the following isql command as the database administrator to dump the transaction log for the database:

```
dump transaction to dump device with standby access
```

Then copy the dumped transaction log to the appropriate database directory on the off-host processing host.

- **13** As the database administrator, start the new database:
 - If the replica DB2 database is not to be rolled forward, use the following commands to start and recover it:

db2start

db2inidb database as snapshot

If the replica DB2 database is to be rolled forward (the primary must have been placed in LOGRETAIN RECOVERY mode before the snapshot was taken), use the following commands to start it, and put it in roll-forward pending state:

db2start

```
db2inidb database as standby
```

Obtain the latest log files from the primary database, and use the following command to roll the replica database forward to the end of the logs:

db2 rollforward db database to end of logs

■ For a Sybase ASE database, use a script such as that shown in the example.

```
#!/bin/ksh
# script: startdb.sh <list of database volumes>
# Sample script to recover and start replica Sybase ASE
# database.
# Import the snapshot volume disk group.
vxdq import $snapvoldq
# Mount the snapshot volumes (the mount points must already
# exist).
for i in $*
   fsck -F vxfs /dev/vx/rdsk/$snapvoldg/snap $i
   mount -F vxfs /dev/vx/dsk/$snapvoldg/snap $i \
${rep mnt point}/$i
done
# Start the replica database.
# Specify the -q option if you specified the "for external
# dump" clause when you quiesced the primary database.
# See the Sybase ASE 12.5 documentation for more information.
```

```
/sybase/ASE-12 5/bin/dataserver \
[-q] \
-sdatabase name \
-d /sybevm/master \
-e /sybase/ASE-12 5/install/dbasename.log \
-M /sybase
# Online the database. Load the transaction log dump and
\# specify "for standby access" if you used the -q option
# with the dataserver command.
isql -Usa -Ppassword -SFMR <<!
[load transaction from dump device with standby access
online database database name [for standby access]
quit
!
```

If you are using the warm standby method, specify the -g option to the dataserver command. Use the following isgl commands to load the dump of the transaction log and put the database online:

```
load transaction from dump device with standby access
online database database name for standby access
```

If you are not using the warm standby method, use the following isql command to recover the database, roll back any uncommitted transactions to the time that the quiesce command was issued, and put the database online:

```
online database database name
```

Resynchronizing the data with the primary host

This procedure describes how to resynchronize the data in a snapshot with the primary host.

To resynchronize a snapshot with the primary database

- On the off-host processing host, shut down the replica database, and use the following command to unmount each of the snapshot volumes:
 - # umount mount point
- On the off-host processing host, use the following command to deport the snapshot volume's disk group:
 - # vxdg deport snapvoldg
- On the primary host, re-import the snapshot volume's disk group using the following command:
 - # vxdg [-s] import snapvoldg

Note: Specify the -s option if you are reimporting the disk group to be rejoined with a shared disk group in a cluster.

- On the primary host, use the following command to rejoin the snapshot volume's disk group with the original volume's disk group:
 - # vxdg join snapvoldg database dg
- VxVM will recover the volumes automatically after the join unless it is set to not recover automatically. Check if the snapshot volumes are initially disabled and not recovered following the join.

If a volume is in the DISABLED state, use the following command on the primary host to recover and restart the snapshot volume:

- # vxrecover -g database dg -m snapvol
- Use the steps in Creating an off-host replica database to to resynchronize the snapshot and make the snapshot available at off-host processing host again.
 - The snapshots are now ready to be re-used for backup or for other decision support applications.

Updating a warm standby Sybase ASE 12.5 database

If you specified the for external dump clause when you quiesced the primary database, and you started the replica database by specifying the -q option to the dataserver command, you can use transaction logs to update the replica database.

To update the replica database

On the primary host, use the following isql command to dump the transaction log for the database:

```
dump transaction to dump device with standby access
```

- Copy the transaction log dump to the appropriate database directory on the off-host processing host.
- On the off-host processing host, use the following isql command to load the new transaction log:

```
load transaction from dump device with standby access
```

On the off-host processing host, use the following isql command to put the database online:

```
online database database name for standby access
```

Reattaching snapshot plexes

Some or all plexes of an instant snapshot may be reattached to the specified original volume, or to a source volume in the snapshot hierarchy above the snapshot volume.

Note: This operation is not supported for space-optimized instant snapshots.

By default, all the plexes are reattached, which results in the removal of the snapshot. If required, the number of plexes to be reattached may be specified as the value assigned to the nmirror attribute.

Note: The snapshot being reattached must not be open to any application. For example, any file system configured on the snapshot volume must first be unmounted.

To reattach a snapshot

- Use the following command, to reattach some or all plexes of an instant snapshot to the specified original volume, or to a source volume in the snapshot hierarchy above the snapshot volume:
 - # vxsnap [-q diskgroup] reattach snapvol source=vol \ [nmirror=number]

For example the following command reattaches 1 plex from the snapshot volume, snapmyvol, to the volume, myvol:

vxsnap -q mydq reattach snapmyvol source=myvol nmirror=1

While the reattached plexes are being resynchronized from the data in the parent volume, they remain in the SNAPTMP state. After resynchronization is complete, the plexes are placed in the SNAPDONE state.

What is off-host processing?

Off-host processing consists of performing operations on application data on a host other than the one where the application is running. Typical operations include Decision Support Systems (DSS) and backup. In a VVR environment, off-host processing operations can be performed on the Secondary of the Replicated Data Set. This reduces the load on the application server, the Primary.

The model for data access on the Secondary is that you break off a mirror from each data volume in the RVG, perform the operation on the mirror, and then reattach the mirror while replication is in progress.

About using VVR for off-host processing

This chapter explains how to use Veritas Volume Replicator (VVR) for off-host processing on the Secondary host. You can use the In-Band Control (IBC) Messaging feature with the FastResync (FMR) feature of Veritas Volume Manager (VxVM) and its integration with VVR to take application-consistent snapshots at the replicated volume group (RVG) level. This lets you perform off-host processing on the Secondary host.

This chapter explains how to perform off-host processing operations using the vradmin ibc command. You can also use the vxibc commands to perform off-host processing operations.

Creating and refreshing test environments

This chapter includes the following topics:

- About test environments
- Creating a test environment
- Refreshing a test environment

About test environments

Sometimes, there is a need to do some testing or development on a copy of production data. In such scenarios, it is essential to provide isolation of these environments from the production environment. This is required so that there is no interference of testing or development environments with production environment. Veritas Storage Foundation can provide a very efficient and cost effective mechanism to create multiple test setups at the same time from a copy of production data. This is done without affecting performance of the production application, at the same time providing complete isolation.

Creating a test environment

Before you set up a test or development environment, you must have a production application volume already created in the application disk group.

To prepare for a test environment

◆ Prepare the application data volume(s) for snapshot operation

```
# vxsnap -g appdg prepare appvol
```

To create a test environment

- Identify disks to create break-off snapshots. These disks need not be from the same array as the application volume. These disks must be visible to the host that will run test/dev environment.
- Use these disks to create a mirror breakoff snapshot:
 - Add the mirror to create a breakoff snapshot. This step copies application volume data into the new mirror added to create the snapshot.
 - # vxsnap -g appdg addmir appvol alloc=<sdisk1,sdisk2,...>
 - Create a snapshot.
 - # vxsnap -g appdg make src=appvol/nmirror=1/new=snapvol
- Split the diskgroup containing the mirror breakoff snapshot.
 - # vxdg split appdg testdevdg snapvol
- Deport the diskgroup from the production application host
 - # vxdq deport testdevdq
- Import the *testdev* disk group on the host that will run the test environment.
 - # vxdq import testdevdq

Once this step is done, the *snapvol* present in the *testdevdg* disk group is ready to be used for testing or development purposes. If required, it is also possible to create multiple copies of *snapvol* using Veritas Storage Foundation's Flashsnap feature by creating a snapshot of snapvol using method described above.

Refreshing a test environment

Periodically, it may be required to resynchronize the test or development environment with current production data. This can be efficiently achieved using the Flashsnap feature of Storage Foundation and High Availability Solutions products.

To refresh a test environment

- Deport the *testdevdg* disk group from the test environment. This step requires stopping the usage of *snapvol* in the test environment.
 - # vxdq deport testdevdq
- 2 Import *testdevdg* into the production environment.
 - # vxdg import testdevdg
- Reattach the *snapvol* to *appvol* in order to synchronize current production data. Note that this synchronization is very efficient since it copies only the changed data.
 - # vxsnap -g appdg snapvol source=appvol
- When you need to setup the *testdevdg* environment again, recreate the break-off snapshot.
 - # vxsnap -q appdq make src=appvol/nmirror=1/new=snapvol
- Split the diskgroup containing the mirror breakoff snapshot.
 - # vxdg split appdg testdevdg snapvol
- Deport the diskgroup from the production application host
 - # vxdq deport testdevdq
- Import the *testdev* disk group on the host that will run the test environment.
 - # vxdg import testdevdg

Once this step is done, the *snapvol* present in *testdevdg* is ready to be used for testing or development purposes.

You can also create further snapshots of *snapvol* in order to create more test or development environments using the same snapshot. For this purpose, the following mechanisms can be used:

- Mirror breakoff snapshots See "Preparing a full-sized instant snapshot for a backup" on page 100.
- Space-optimized snapshot See "Preparing a space-optimized snapshot for a database backup" on page 102.
- Veritas File System level checkpoints

See "Creating Storage Checkpoints" on page 130.

For more detailed information, see the $Veritas\ Storage\ Foundation^{\text{\tiny TM}}$ $Administrator's\ Guide$

Creating point-in-time copies of files

This chapter includes the following topics:

■ Using FileSnaps to create point-in-time copies of files

Using FileSnaps to create point-in-time copies of files

The key to obtaining maximum performance with FileSnaps is to minimize the copy-on-write overhead. You can achieved this by enabling lazy copy-on-write. Lazy copy-on-write is easy to enable and usually results in significantly better performance. If lazy copy-on-write is not a viable option for the use case under consideration, an efficient allocation of the source file can reduce the need of copy-on-write.

Using FileSnaps to provision virtual desktops

Virtual desktop infrastructure (VDI) operating system boot images are a good use case for FileSnaps. The parts of the boot images that can change are user profile, page files (or swap for UNIX/Linux) and application data. You should separate such data from boot images to minimize unsharing. You should allocate a single extent to the master boot image file.

Example of using FileSnaps to provision a virtual desktop

The following example uses a 4 GB master boot image that has a single extent that will be shared by all snapshots.

- # touch /vdi images/master image
- # /opt/VRTS/bin/setext -r 4g -f chgsize /vdi_images/master_image

The master image file can be presented as a disk device to the virtual machine for installing the operating system. Once the operating system is installed and configured, the file is ready for snapshots.

Using FileSnaps to optimize write intensive applications for virtual machines

When virtual machines are spawned to perform certain tasks that are write intensive, a significant amount of unsharing can take place. Symantec recommends that you optimize performance by enabling lazy copy-on-write. If the use case does not allow enabling lazy copy-on-write, with careful planning, you can reduce the occurrence of unsharing. The easiest way to reduce unsharing is to separate the application data to a file other than the boot image. If you cannot do this due to the nature of your applications, then you can take actions similar to the following example.

Example of using FileSnaps to optimize write intensive applications

Assume that the disk space required for a boot image and the application data is 20 GB. Out of this, only 4 GB is used by the operating system and the remaining 16 GB is the space for applications to write. Any data or binaries that are required by each instance of the virtual machine can still be part of the first 4 GB of the shared extent. Since most of the writes are expected to take place on the 16 GB portion, you should allocate the master image in such a way that the 16 GB of space is not shared, as shown in the following commands:

```
# touch /vdi_images/master_image
# /opt/VRTS/bin/setext -r 4g -f chqsize /vdi images/master image
# dd if=/dev/zero of=/vdi images/master image seek=16777215 \
bs=1024 count=1
```

The last command creates a 16 GB hole at the end of the file. Since holes do not have any extents allocated, the writes to hole do not need to be unshared.

Using FileSnaps to create multiple copies of data instantly

It is common to create one or more copies of production data for the purpose of generating reports, mining, and testing. These cases frequently update the copies of the data with the most current data, and one or more copies of the data always exists. FileSnaps can be used to create multiple copies instantly. The application that uses the original data can see a slight performance hit due to the unsharing of data that can take place during updates. This slight impact on performance

can still be present even when all FileSnaps have been deleted. However, you rarely see all FileSnaps being deleted since these use cases usually have one or more copies at any given time.

174 | Creating point-in-time copies of files Using FileSnaps to create point-in-time copies of files Section

Maximizing storage utilization

■ Chapter 12. Optimizing storage tiering with SmartTier

Optimizing storage tiering with SmartTier

This chapter includes the following topics:

- About SmartTier
- SmartTier building blocks
- SmartTier use cases for DB2 or Sybase
- Setting up a filesystem for storage tiering with SmartTier
- Relocating old archive logs to tier two storage using SmartTier
- Relocating inactive tablespaces or segments to tier two storage
- Relocating active indexes to premium storage
- Relocating all indexes to premium storage

About SmartTier

SmartTier matches data storage with data usage requirements. After data matching, the data can then be relocated based upon data usage and other requirements determined by the storage or database administrator (DBA).

As more and more data is retained over a period of time, eventually, some of that data is needed less frequently. The data that is needed less frequently still requires a large amount of disk space. SmartTier enables the database administrator to manage data so that less frequently used data can be moved to slower, less expensive disks. This also permits the frequently accessed data to be stored on faster disks for quicker retrieval.

Tiered storage is the assignment of different types of data to different storage types to improve performance and reduce costs. With SmartTier, storage classes are used to designate which disks make up a particular tier. There are two common ways of defining storage classes:

Note: SmartTier is the expanded and renamed feature previously known as Dynamic Storage Tiering (DST).

- Performance, or storage, cost class: The most-used class consists of fast, expensive disks. When data is no longer needed on a regular basis, the data can be moved to a different class that is made up of slower, less expensive disks.
- Resilience class: Each class consists of non-mirrored volumes, mirrored volumes, and n-way mirrored volumes.
 - For example, a database is usually made up of data, an index, and logs. The data could be set up with a three-way mirror because data is critical. The index could be set up with a two-way mirror because the index is important, but can be recreated. The redo and archive logs are not required on a daily basis but are vital to database recovery and should also be mirrored.

SmartTier policies control initial file location and the circumstances under which existing files are relocated. These policies cause the files to which they apply to be created and extended on specific subsets of a file systems's volume set, known as placement classes. The files are relocated to volumes in other placement classes when they meet specified naming, timing, access rate, and storage capacity-related conditions.

In addition to preset policies, you can manually move files to faster or slower storage with SmartTier, when necessary. You can also run reports that list active policies, display file activity, display volume usage, or show file statistics.

To use SmartTier, your storage must be managed using the following features:

- VxFS multi-volume file system
- VxVM volume set
- Volume tags
- SmartTier management at the file level
- SmartTier management at the sub-file level

SmartTier building blocks

To use SmartTier, your storage must be managed using the following features:

- VxFS multi-volume file system
- VxVM volume set
- Volume tags
- SmartTier management at the file level
- SmartTier management at the sub-file level

About VxFS multi-volume file systems

Multi-volume file systems are file systems that occupy two or more virtual volumes. The collection of volumes is known as a volume set, and is made up of disks or disk array LUNs belonging to a single Veritas Volume Manager (VxVM) disk group. A multi-volume file system presents a single name space, making the existence of multiple volumes transparent to users and applications. Each volume retains a separate identity for administrative purposes, making it possible to control the locations to which individual files are directed.

This feature is available only on file systems meeting the following requirements:

- The minimum disk group version is 140.
- The minimum file system layout version is 7 for file level SmartTier.
- The minimum file system layout version is 8 for sub-file level SmartTier.

To convert your existing VxFS system to a VxFS multi-volume file system, you must convert a single volume to a volume set.

The VxFS volume administration utility (fsvoladm utility) can be used to administer VxFS volumes. The fsvoladm utility performs administrative tasks, such as adding, removing, resizing, encapsulating volumes, and setting, clearing, or querying flags on volumes in a specified Veritas File System.

See the fsvoladm (1M) manual page for additional information about using this utility.

About VxVM volume sets

Volume sets allow several volumes to be represented by a single logical object. Volume sets cannot be empty. All I/O from and to the underlying volumes is directed via the I/O interfaces of the volume set. The volume set feature supports the multi-volume enhancement to Veritas File System (VxFS). This feature allows file systems to make best use of the different performance and availability characteristics of the underlying volumes. For example, file system metadata could be stored on volumes with higher redundancy, and user data on volumes with better performance.

About volume tags

You make a VxVM volume part of a placement class by associating a volume tag with it. For file placement purposes, VxFS treats all of the volumes in a placement class as equivalent, and balances space allocation across them. A volume may have more than one tag associated with it. If a volume has multiple tags, the volume belongs to multiple placement classes and is subject to allocation and relocation policies that relate to any of the placement classes.

Warning: Multiple tagging should be used carefully.

A placement class is a SmartTier attribute of a given volume in a volume set of a multi-volume file system. This attribute is a character string, and is known as a volume tag.

SmartTier use cases for DB2 or Sybase

Storage Foundation High Availability Solutions include SmartTier, a storage tiering feature which enables you to tier your data to achieve optimal use of your storage.

Example procedures illustrate the following use cases:

- Relocating archive logs older than 2 days to Tier-2 storage
- Relocating inactive tablespaces or segments to Tier-2 storage
- Relocating active indexes to Tier-0 storage
- Relocating all indexes to Tier-0 storage

Setting up a filesystem for storage tiering with **SmartTier**

In the use case examples, the following circumstances apply:

- The database containers are in the file system /DBdata
- The database archived logs are in the file system /DBarch

To create required filesystems for SmartTier

1 List the disks:

vxdisk list

DEVICE	TYPE	DISK	GROUP	STATUS
fas30700_0	auto:cdsdisk	fas30700_0		online thin
fas30700_1	auto:cdsdisk	fas30700 <u></u> 1		online thin
fas30700_2	auto:cdsdisk	fas30700_2		online thin
fas30700_3	auto:cdsdisk	fas30700_3		online thin
fas30700_4	auto:cdsdisk	fas30700 <u>4</u>		online thin
fas30700_5	auto:cdsdisk	fas30700_5		online thin
fas30700_6	auto:cdsdisk	fas30700_6		online thin
fas30700_7	auto:cdsdisk	fas30700_7		online thin
fas30700_8	auto:cdsdisk	fas30700_8		online thin

Assume there are 3 LUNs on each tier.

2 Create the disk group.

```
# Vxdg init DBdg fas30700 0 fas30700 1 fas30700 2 \
fas30700 3 fas30700 4 fas30700 5 fas30700 6 fas30700 7 \
fas30700 8
```

3 Create the volumes *datavol* and *archvol*.

```
# vxassist -g DBdg make datavol 200G alloc=fas30700 3,\
fas30700 4,fas30700 5
# vxassist -q DBdq make archvol 50G alloc= fas30700 3,\
fas30700_4,fas30700_5
```

Tag datavol and archvol as tier-1.

```
# vxassist -g DBdg settag datavol vxfs.placement_class.tier1
# vxassist -g DBdg settag archvol vxfs.placement class.tier1
```

4 Create the Tier-0 volumes.

```
# vxassist -g DBdg make tier0 vol1 50G alloc= fas30700 0,\
fas30700_1,fas30700_2
# vxassist -g DBdg make tier0 vol2 50G alloc= fas30700 0,\
fas30700 1,fas30700 2
# vxassist -g DBdg settag tier0 vol1 vxfs.placement class.tier0
# vxassist -g DBdg settag tier0_vol2 vxfs.placement_class.tier0
```

5 Create the Tier-2 volumes.

```
# vxassist -g DBdg make tier2 vol1 50G alloc= fas30700 6,\
fas30700 7,fas30700 8
# vxassist -g DBdg make tier2 vol2 50G alloc= fas30700 6,\
fas30700 7,fas30700 8
# vxassist -g DBdg settag tier2 vol1 vxfs.placement class.tier2
# vxassist -g DBdg settag tier2 vol2 vxfs.placement class.tier2
```

6 Convert *datavol* and *archvol* to a volume set.

```
# vxvset -g DBdg make datavol mvfs datavol
# vxvset -g DBdg make archvol mvfs archvol
```

Add the volumes *Tier-0* and *Tier-2* to *datavol mvfs*.

```
# vxvset -g DBdg addvol datavol mvfs tier0 vol1
# vxvset -g DBdg addvol datavol mvfs tier2 vol1
```

8 Add the volume *Tier-2* to *archvol mvfs*

```
# vxvset -g DBdg archvol_mvfs tier2_vol2
```

Make the file system and mount *datavol mvfs* and *archvol mvfs*.

```
# mkfs -F vxfs /dev/vx/rdsk/DBdg/datavol mvfs
```

10 Mount the *DBdata* file system

```
# mount -F vxfs /dev/vx/rdsk/DBdg/datavol mvfs /DBdata
```

11 Mount the *DBarch filesystem*

```
# mount -F vxfs /dev/vx/rdsk/DBdg/datavol mvfs /DBarch
```

12 Migrate the database into the newly created, SmartTier-ready file system. You can migrate the database either by restoring from backup or copying appropriate files into respective filesystems.

See the database documentation for more information.

Relocating old archive logs to tier two storage using **SmartTier**

A busy database can generate few hundred gigabytes of archivelogs per day. Restoring these archive logs from tape backup is not ideal because it increases database recovery time. Regulatory requirements could mandate that these archive logs be preserved for several weeks.

To save storage costs, you can relocate archive logs older than two days (for example) into tier two storage. To achieve this you must create a policy file, for example, archive policy.xml.

Note: The relocaing archive logs use case applies for both DB2 and Sybase environments.

To relocate archive logs that are more than two days old to Tier-2

Create a policy file. A sample XML policy file is provided below.

```
<?xml version="1.0"?>
<!DOCTYPE PLACEMENT POLICY SYSTEM "/opt/VRTSvxfs/etc\</pre>
   /placement policy.dtd">
<PLACEMENT_POLICY Version="5.0" Name="access_age_based">
    <RULE Flags="data" Name="Key-Files-Rule">
         <COMMENT>
            This rule deals with key files such as archive logs.
         </COMMENT>
    <SELECT Flags="Data">
         <COMMENT>
             You want all files. So choose pattern as '*'
         </COMMENT>
         <PATTERN> * </PATTERN>
     </SELECT>
    <CREATE>
        <0N>
            <DESTINATION>
                <CLASS> tier1 </CLASS>
            </DESTINATION>
        </ON>
    </CREATE>
    <RELOCATE>
    <TO>
          <DESTINATION>
              <CLASS> tier2 </CLASS>
          </DESTINATION>
    </TO>
          <WHEN>
                  <ACCAGE Units="days">
                      <MIN Flags="gt">2</MIN>
                  </ACCAGE>
          </WHEN>
    </RELOCATE>
    </RULE>
</PLACEMENT POLICY>
```

Notice the ACCAGE units in the WHEN clause.

To locate additional sample policy files, go to /opt/VRTSvxfs/etc.

The access age-based policy is appropriate for this use case. Pay attention to the CREATE ON and RELOCATE TO sections of the XML file.

To apply a policy file

- As root, validate archive policy.xml
 - # fsppadm validate /DBarch archive_policy.xml
- If the validation process is not successful, correct the problem. Validate archive policy.xml successfully before proceeding.
- Assign the policy to /DBarch filesystem
 - # fsppadm assign /DBarch archive policy.xml
- Enforce the policy. The relocation of two day old archive logs happens when the enforcement step is performed. The policy enforcements must be done every day to relocate aged archive logs. This enforcement can be performed on demand as needed or by using a cron-like scheduler.
 - # fsppadm enforce /DBarch

Relocating inactive tablespaces or segments to tier two storage

It is general practice to use partitions in databases. Each partition maps to a unique tablespace. For example in a shopping goods database, the orders table can be portioned into orders of each quarter. Q1 orders can be organized into Q1 order tbs tablespace or Q1 order tbs segment, Q2 order can be organized into Q2 order tbs.

As the quarters go by, the activity on older quarter data decreases. By relocating old quarter data into Tier-2, significant storage costs can be saved. The relocation of data can be done when the database is online.

For the following example use case, the steps illustrate how to relocate Q1 order data into Tier-2 in the beginning of Q3. The example steps assume that all the database data is in /DBdata filesystem.

To prepare to relocate Q1 order data into Tier-2 storage for DB2

- Obtain a list of containers belonging to *Q1_order_tbs*.
 - \$ db2inst1\$ db2 list tablespaces
- 2 Find the tablespace-id for the tablespace *Q1* order tbs.
 - \$ db2inst1\$ db2 list tablespace containers for <tablespace-id>
- **3** Find the path names for the containers and store them in file Q1 order files.txt.

```
#cat Q1 order_files.txt
         NODE0000/Q1 order file1.f
         NODE0000/Q1 order file2.f
         NODE0000/Q1 order fileN.f
```

To prepare to relocate Q1 order data into Tier-2 storage for Sybase

Obtain a list of datafiles belonging to segment Q1 order tbs. System Procedures sp helpsegment and *sp_helpdevice* can be used for this purpose.

```
sybsadmin$ sp helpsegment Q1 order tbss
```

Note: In Sybase terminology, a "tablespace" is same as a "segment."

- 2 Note down the device names for the segment *Q1 order tbs*.
- 3 For each device name use the sp helpdevice system procedure to get the physical path name of the datafile.

```
sybsadmin$ sp helpdevice <device name>
```

Save all the datafile path names in Q1 order files.txt

```
# cat Q1 order files.txt
         NODE0000/Q1 order file1.f
         NODE0000/Q1 order file2.f
         NODE0000/Q1 order fileN.f
```

To relocate Q1 order data into Tier-2

Prepare a policy XML file. For the example, the policy file name is Q1 order policy.xml. Below is a sample policy.

This is policy is for unconditional relocation and hence there is no when clause. There are multiple Pattern statements as part of the select clause. Each PATTERN selects a different file.

```
<?xml version="1.0"?>
<!DOCTYPE PLACEMENT POLICY SYSTEM "/opt/VRTSvxfs/etc/\</pre>
placement policy.dtd">
<PLACEMENT POLICY Version="5.0" Name="selected files">
    <RULE Flags="data" Name="Key-Files-Rule">
        <COMMENT>
            This rule deals with key important files.
        </COMMENT>
        <SELECT Flags="Data">
           <DIRECTORY Flags="nonrecursive" > NODE0000/DIRECTORY>
            <PATTERN> Q1 order file1.f </pattern>
           <PATTERN> Q1 order file2.f </pattern>
            <PATTERN> Q1 order fileN.f </PATTERN>
        </SELECT>
        <RELOCATE>
             <COMMENT>
                Note that there is no WHEN clause.
             </COMMENT>
                <DESTINATION>
                   <CLASS> tier2 </CLASS>
                </TO>
         </RELOCATE>
    </RULE>
</PLACEMENT POLICY>
```

- Validate the policy Q1 order policy.xml.
 - # fsppadm validate /DBdata Q1 order policy.xml

- Assign the policy.
 - # fsppadm assign /DBdata Q1 order policy.xml
- Enforce the policy.
 - # fsppadm enforce /DBdata

Relocating active indexes to premium storage

Database transaction rate depends upon how fast indexes can be accessed. If Indexes reside on slow storage, the database transaction rate suffers. Tier-0 storage is generally too expensive to be practical to relocate the entire table data to Tier-0. Indexes are generally much smaller in size and are created to improve the database transaction rate, hence it is more practical to relocate active indexes to Tier-0 storage. Using SmartTier you can move active indexes to Tier-0 storage.

For the following telephone company database example procedure, assume the call details table has an index call idx on the column customer id.

To prepare to relocate call_idx to Tier-0 storage for DB2

Find the tablespace where *call idx* resides.

```
$ db2inst1$ db2 connect to PROD
$ db2inst1$ db2 select index tbspace from syscat.tables \
where tabname='call details'
```

2 In this example, the index is in tablespace *tbs_call_idx*. To get the tablespace id for tbs call idx and the list of containers:

```
$ db2inst1$ db2 list tablespaces
```

Note the tablespace id for the call idx.

List the containers and record the filenames in the tabelspace *tbs call idx*.

```
$ db2inst1$ db2 list tablespace containers for <tablespace-id>
```

Store the files in *index files.txt*.

```
# cat index files.txt
/DB2data/NODE0000/IDX/call1.idx
/DB2data/NODE0000/IDX/call2.idx
/DB2data/NODE0000/IDX/call3.idx
```

To prepare to relocate call_idx to premium storage for Sybase

1 Obtain a list of datafiles for the *call_idx* segment.

```
$ sybsadmin$ sp helpsegment call idx
```

- Note down the device names for the segment *call_idx*. 2
- 3 For each device name use the sp helpdevice system procedure to get the physical pathname of the datafile.

```
sybsadmin$ sp helpdevice <device name>
```

4 Save all the datafile path names in *index_files.txt*.

```
# cat index files.txt
```

```
/DB2data/NODE0000/IDX/call1.idx
/DB2data/NODE0000/IDX/call2.idx
/DB2data/NODE0000/IDX/call3.idx
```

To relocate call_idx to Tier-0 storage

Prepare the policy *index_policy.xml*.

Example policy:

```
<?xml version="1.0"?>
<!DOCTYPE PLACEMENT POLICY SYSTEM "/opt/VRTSvxfs/etc/\</pre>
placement policy.dtd">
<PLACEMENT POLICY Version="5.0" Name="selected files">
    <RULE Flags="data" Name="Key-Files-Rule">
        <COMMENT>
            This rule deals with key important files.
        </COMMENT>
        <SELECT Flags="Data">
            <DIRECTORY Flags="nonrecursive" > NODE0000/DIRECTORY>
            <PATTERN> call*.idx </pattern>
        </select>
        <RELOCATE>
            <COMMENT>
                Note that there is no WHEN clause.
         </COMMENT>
         <TO>
            <DESTINATION>
                <CLASS> tier0 </CLASS>
            </DESTINATION>
         </TO>
         </RELOCATE>
    </RULE>
</PLACEMENT POLICY>
```

Assign and enforce the policy.

```
# fsppadm validate /DBdata index_policy.xml
# fsppadm assign /DBdata index_policy.xml
# fsppadm enforce /DBdata
```

Relocating all indexes to premium storage

It is a common practice for DBAs to name index files with some common extensions. For example, all index files are named with ".inx" extensions. If your Tier-0 storage has enough capacity, you can relocate all indexes of the database to Tier-0 storage. You can also make sure all index containers created with this special extension are automatically created on Tier-0 storage by using the ${\tt CREATE}$ and RELOCATE clause of policy definition.

To relocate all indexes to Tier-0 storage

Create a policy such as the following example:

```
# cat index policy.xml
```

```
<?xml version="1.0"?>
<!DOCTYPE PLACEMENT POLICY SYSTEM "/opt/VRTSvxfs/etc/\</pre>
placement policy.dtd">
<PLACEMENT POLICY Version="5.0" Name="selected files">
    <RULE Flags="data" Name="Key-Files-Rule">
        <COMMENT>
            This rule deals with key important files.
        </comment>
        <SELECT Flags="Data">
            <PATTERN> *.inx </PATTERN>
        </SELECT>
        <CREATE>
            <COMMENT>
               Note that there are two DESTINATION.
            </COMMENT>
            <NO>
               <DESTINATION>
                   <CLASS> tier0 </CLASS>
               </DESTINATION>
               <DESTINATION>
                   <CLASS> tier1</CLASS>
               </ON>
        </CREATE>
             <RELOCATE>
                 <COMMENT>
                    Note that there is no WHEN clause.
                 </COMMENT>
                 <TO>
                    <DESTINATION>
                        <CLASS> tier0 </CLASS>
                    </TO>
            </RELOCATE>
    </RULE>
</PLACEMENT POLICY>
```

- 2 To make sure file creation succeeds even if Tier-0 runs out of space, add two ON clauses as in the example policy in 1.
- Assign and enforce the policy.
 - # fsppadm validate /DBdata index policy.xml
 - # fsppadm assign /DBdata index_policy.xml
 - # fsppadm enforce /DBdata

Section

Migrating data

- Chapter 13. Understanding data migration
- Chapter 14. Offline migration from Solaris Volume Manager to Veritas Volume Manager
- Chapter 15. Online migration of a native file system to the VxFS file system
- Chapter 16. Migrating storage arrays
- Chapter 17. Migrating data between platforms

Understanding data migration

This chapter includes the following topics:

■ Types of data migration

Types of data migration

This section describes the following types of data migration:

- Migrating data from Solaris Volume Manager to Storage Foundation using offline migration
 - When you install Storage Foundation, you may already have some volumes that are controlled by the Solaris Volume Manager. You can preserve your data and convert these volumes to Veritas Volume Manager volumes. See "About migration from Solaris Volume Manager" on page 199.
- Migrating data from a native file system to a Veritas File System (VxFS) file system using online migration
 See "About online migration of a native file system to the VxFS file system" on page 217.
- Migrating data between platforms using Cross-platform Data Sharing (CDS) Storage Foundation lets you create disks and volumes so that the data can be read by systems running different operating systems. CDS disks and volumes cannot be mounted and accessed from different operating systems at the same time. The CDS functionality provides an easy way to migrated data between one system and another system running a different operating system.

 See "Overview of the Cross-Platform Data Sharing (CDS) feature" on page 237.
- Migrating data between arrays

Storage Foundation supports arrays from various vendors. If your storage needs change, you can move your data between arrays. See "Array migration for storage using Linux" on page 225.

Note: The procedures are different if you plan to migrate to a thin array from a thick array.

Offline migration from Solaris Volume Manager to Veritas Volume Manager

This chapter includes the following topics:

- About migration from Solaris Volume Manager
- How Solaris Volume Manager objects are mapped to VxVM objects
- Overview of the conversion process
- Planning the conversion
- Preparing a Solaris Volume Manager configuration for conversion
- Setting up a Solaris Volume Manager configuration for conversion
- Converting from the Solaris Volume Manager software to VxVM
- Post conversion tasks
- Converting a root disk

About migration from Solaris Volume Manager

Note: Migrating from Solaris Volume Manager to VxVM is not supported on Solaris 10 x64.

Veritas Volume Manager (VxVM) provides utilities that you can use to convert objects, file systems, and device partitions controlled by the Oracle Solaris Volume

Manager software (also known as Solstice Disk Suite™) to VxVM control. The tools convert all Solaris Volume Manager objects into VxVM objects amd encapsulate the file systems and swap device partitions used by the Solaris Volume Manager software. The conversion happens in place. You do not need to copy data into temporary storage. After the conversion, the Solaris Volume Manager software is disabled and can be removed.

The conversion utilities have the following characteristics:

- The utilities are provided in the VRTSVXVM package.
- All objects under Solaris Volume Manager control are converted. The conversion commands have no partial conversion option.
- You must use the recommended root disk conversion procedure if you want to move only a root disk from under Solaris Volume Manager control to VxVM. See "Converting a root disk" on page 215.

Warning: You cannot use the conversion utilities in a mixed environment. Even if you move only the root disk from Solaris Volume Manager software to VxVM, you cannot later use the conversion utilities to move other Solaris Volume Manager objects to VxVM.

- The conversion cannot be done in a mixed environment, which is a system that has both Solaris Volume Manager metadevices and VxVM objects (disk groups, un-used plexes, etc).
- All file systems that are on a Solaris Volume Manager metadevice and that are listed in /etc/vfstab are put under VxVM control.
- A conversion retains the on-disk layouts of Solaris Volume Manager volumes and does not improve layouts as supported by VxVM.
- The conversion utilities do not allow a conversion to be reversed. Once the conversion process starts, the best way to return to the Solaris Volume Manager configuration is to restore it from backups.
- After the conversion process starts on RAID-5 volumes, the data in these volumes is reorganized. Returning RAID-5 volumes to Solaris Volume Manager control can be done only by restoring the Solaris Volume Manager configuration and the volume data from backups.
- If you are very familiar with Solaris Volume Manager software and VxVM, you may be able to reverse a conversion without performing a full Solaris Volume Manager restoration from backups. However, RAID-5 volumes must always be restored from backups because the conversion utilities always reorganize RAID-5 parity. To manually reverse a conversion, preserve all Solaris Volume

Manager configuration information that is required for its restoration. This includes output from metastat -p and metadb for every diskset, and prtvtoc output for all disks.


■ Any partition that is on a disk with Solaris Volume Manager metadevices and that is not listed as a file system in /etc/vfstab is lost during the conversion. The partition is considered free space when the disk is converted to VxVM control. Even if the partitions are in use, they are not encapsulated during the conversion. The raw partitions are lost when the disk layout changes. Either encapsulate the partition under Solaris Volume Manager control and allow the conversion to convert the resulting metadevice, or back up the partition, plan to create a new volume for it, and restore the partition after the conversion.

How Solaris Volume Manager objects are mapped to VxVM objects

The following illustrations give examples of how the conversion process maps Solaris Volume Manager concat/stripe objects to VxVM objects. RAID-5 volumes and mirrors come through the conversion intact.

Figure 14-1 shows a single Solaris Volume Manager partition encapsulated in a concat/stripe Solaris Volume Manager object.


Figure 14-1 Single Solaris Volume Manager partition encapsulated in a concat/stripe Solaris Volume Manager object



The partition becomes a simple volume under VxVM.

Figure 14-2 shows a number of one-partition Solaris Volume Manager stripes in a concat/stripe Solaris Volume Manager object.


A number of one-partition Solaris Volume Manager stripes in a Figure 14-2 concat/stripe Solaris Volume Manager object



The stripes become a concat plex under VxVM.


Figure 14-3 shows a single Solaris Volume Manager stripe with an arbitrary number of partitions in a concat/stripe Solaris Volume Manager object.

A single Solaris Volume Manager stripe with any number of Figure 14-3 partitions in a concat/stripe Solaris Volume Manager object



The partitions become a striped plex under VxVM.

Figure 14-4 shows a Solaris Volume Manager concat/stripe object with a mix of stripes.



A Solaris Volume Manager concat/stripe object with a mix of stripes Figure 14-4

Under VxVM, the stripes are concatenated and may require a layered volume.

Conversion of soft partitions

The provided utilities support the conversion of the following soft partition-based layouts:

- A simple soft partition on a disk slice with one or more extents. Figure 14-5 shows the conversion of such a layout. See Figure 14-5 on page 204.
- Concat/Stripe on a soft partition on a disk slice with a single extent. Figure 14-6 shows the conversion of such a layout. See Figure 14-6 on page 204.
- RAID-5 on a soft partition on a disk slice with a single extent.
- Concat/Stripe on a soft partition on a disk slice with multiple extents.

The utilities do not support the conversion of the following soft partition-based layouts:

- RAID-5 on soft partitions on a disk with multiple extents.
- Soft partition on a logical volume.





Figure 14-5 Simple soft partition on a disk slice with two extents

Figure 14-6 Concat/stripe Solaris Volume Manager object on a soft partition on a disk slice with a single extent



More information about soft partitions may be found in the Solaris documentation. See "Check metadevices" on page 208.

Overview of the conversion process

The conversion utilities allow you to do most of the preparation before starting the conversion, and before disrupting your system. To take advantage of this feature, read this entire manual and be familiar with the required tasks before starting the conversion from the Solaris Volume Manager configuration to VxVM.

The conversion utilities perform the following tasks:

- Planning and preparing for conversion. See "Plan and prepare for the conversion" on page 205.
- Set up the conversion. See "Set up the conversion" on page 205.
- Convert the volumes. See "Perform the conversion" on page 206.
- Perform post conversion cleanup tasks. See "Perform post-conversion tasks" on page 206.

Note: For a successful conversion, follow the steps in the given order.

Plan and prepare for the conversion

The tasks in this category can be done well before starting the actual conversion.

Plan the process and collect data for the conversion. The conversion may require changes to some Solaris Volume Manager metadevices.

See "Check metadevices" on page 208.

See "Planning the conversion" on page 206.

See "Preparing a Solaris Volume Manager configuration for conversion" on page 209.

Install the basic Veritas Volume Manager (without creating disk groups or objects and without initializing disks). The conversion utilities complete the VxVM setup with objects converted from Solaris Volume Manager software.

Set up the conversion

The tasks in this category should be done or updated just before starting the conversion. Information from the tasks in this category must be current when the conversion starts.

Use the preconvert utility to analyze the Solaris Volume Manager configuration and build a description for the VxVM conversion. You can run preconvert multiple times as it makes no changes to the Solaris Volume Manager configuration or file systems.

Run the showconvert utility to interpret preconvert output into a readable format. The showconvert output flags where changes must be made in the Solaris Volume Manager configuration for the conversion process to succeed. After making changes, run preconvert and showconvert again before starting the conversion. Make backups of everything needed to restore the Solaris Volume Manager configuration.

See "Setting up a Solaris Volume Manager configuration for conversion" on page 210.

Perform the conversion

The first task in this category starts the conversion from Solaris Volume Manager software to VxVM. You have no easy way to return to a Solaris Volume Manager configuration once the conversion starts.

Run the doconvert utility to make the conversion. The doconvert utility relies on information from the preconvert utility.

Reboot the system. The reboot activates system configuration changes.

Change volume references in applications that use the volumes. VxVM uses volume names that are different than the names used by Solaris Volume Manager software. Every application that uses the Solaris Volume Manager volumes must be updated to use the new names.

See "Converting from the Solaris Volume Manager software to VxVM" on page 213.

Perform post-conversion tasks

After the doconvert utility performs a reboot of the system, the converted volumes and file systems are under the control of Veritas Volume Manager.

Use VxVM tools such as vxassist or the graphical user interface to improve the layout of volumes.

Remove or re-initialize the Solaris Volume Manager software for use on non-VxVM disks. After the conversion, the Solaris Volume Manager software is disabled and does not control any data. You can either remove the Solaris Volume Manager software or initialize the Solaris Volume Manager software with disks that are not used by VxVM. Both VxVM and the Solaris Volume Manager software can run on the same system.

See "Post conversion tasks" on page 214.

Planning the conversion

Before using any of the conversion utilities, you should consider how to schedule the steps in the process.

Scheduling considerations

The following preparation tasks can be done at any time before the conversion:

- Schedule downtime.
- Check and reconfigure Solaris Volume Manager metadevices.
- Identify references from applications to Solaris Volume Manager volumes.
- Install VxVM.

The setup tasks should be done just before starting the conversion. If you make changes to the Solaris Volume Manager configuration after doing the setup tasks, perform the following setup tasks again to update information used during the conversion:

- Run the preconvert utility.
- Run the showconvert utility.
- Make Solaris Volume Manager configuration changes if showconvert shows error messages.
- Re-run preconvert and showconvert if needed.
- Make Solaris Volume Manager backups.

The conversion tasks mark the point where you first make changes that cannot be reversed easily. The previous tasks of gathering information and reconfiguring the Solaris Volume Manager software (if needed) allow you to continue using the Solaris Volume Manager software with no disruption. Do the following conversion tasks as soon as possible one after the other:

- Run the doconvert utility.
- Reboot the system.
- Change volume references in applications.

After the conversion completes successfully, the following post-conversion tasks are optional and can be done at any time:

- Improve volume layouts.
- Remove or reinitialize the Solaris Volume Manager software.

Schedule downtime

A conversion includes downtime for applications using Solaris Volume Manager volumes during the doconvert, reboot, and change volume references tasks and downtime for the system during the reboot. A second reboot happens automatically if a root device hosts Solaris Volume Manager objects or is a Solaris Volume Manager metadevice.

The doconvert utility takes about a minute unless the conversion includes RAID-5 volumes. RAID-5 conversions take about a minute for each megabyte of RAID-5 data. The total downtime to expect for a conversion is the sum of the following times:

- Approximately one minute to run doconvert.
- The time needed for one or two system reboots.
- Approximately one minute for each megabyte of RAID-5 data if RAID-5 volumes are included.
- The time needed for changing volume references in applications.

Check metadevices

Solaris Volume Manager metadevices may need changes before starting the conversion.

■ Extended RAID-5 metadevices cannot be converted. A RAID-5 metadevice becomes extended when you add space after the device is first initialized. To find extended RAID-5 metadevices, use the metastat -p command of the Solaris Volume Manager software for each diskset. Look for RAID-5 devices in the output that have a $-\circ$ option showing more original partitions than current partitions. The following example of output from metastat -p shows an extended metadevice:

```
d100 -r clt65d0s3 clt66d0s3 clt67d0s3 clt99d0s3 -k -i 32b -o 3
```

The example lists four partitions: 65, 66, 67, and 99. The -○ entry shows the number of original partitions, three in this case.

Use either of the following options to deal with extended RAID-5 devices:

- Use the Solaris Volume Manager commands or the Solaris Volume Manager user interface to create a new metadevice large enough to contain all the data. Copy the data to the new metadevice.
- Dump the data from the metadevice to tape and restore it to a VxVM volume after the conversion process finishes.
- Metadevices using a hot spare cannot be converted. Use the metastat command of the Solaris Volume Manager software to identify metadevices that currently use hot spares. The following example of output from metastat shows a metadevice using a hot spare:

```
d3:Submirror of d51
  State: Okay
  Hot spare pool: hsp000
  Size 5922252 blocks
  Stripe 0:
  Device Start Block Dbase
                                  State
                                         Hot Spare
  clt75d0s1 0
                                           clt66d0s6
                          No
                                  Okay
```

With no hot spare in use, the "Hot Spare" column at the far right is empty.

Use either of the following options to deal with hot spares:

- Use the metareplace command of the Solaris Volume Manager software to move data from the hot spare onto the original partition (if there is room).
- Use the metareplace and metahs commands of the Solaris Volume Manager software to move the hot spare partition from the hot spare pool into the metadevice.

Identify references by applications

Find and list all references to Solaris Volume Manager metadevices from applications. The conversion utilities update /etc/vfstab with a new path for each metadevice that is converted to a VxVM volume. However, you must manually change references to Solaris Volume Manager metadevices in every application that uses a Solaris Volume Manager metadevice.

See "Run convertname" on page 211.

Preparing a Solaris Volume Manager configuration for conversion

The following preparation tasks can be done at any time before starting the conversion.

Installing VxVM

You must install Veritas Volume Manager before running the conversion utilities. Obtain the VxVM software and a full VxVM license key.

During the VxVM installation, do not run vxinstall. If required, you can use the vxlicinst command to install any license keys.

After installation, do not initialize any disks, and do not create any disk groups or VxVM objects.

The conversion process completes the VxVM installation and configuration.

Setting up a Solaris Volume Manager configuration for conversion

Do the setup tasks just before converting from the Solaris Volume Manager software to VxVM. If you make any changes between the setup tasks and the actual conversion, update the setup tasks.

Run preconvert

The preconvert utility analyzes the current Solaris Volume Manager configuration and builds a description for the new VxVM configuration. The preconvert utility does not make any changes to the Solaris Volume Manager configuration or to the host system. The description created by the preconvert utility must be current with the state of the Solaris Volume Manager software when the conversion process starts or the process will fail. Always run preconvert again if you make any changes to the Solaris Volume Manager configuration.

The preconvert utility has no options and uses no arguments:

preconvert

Messages from preconvert appear on the screen and in a file that is used by the showconvert utility.

WARNING errors are for your information only and require no changes to the Solaris Volume Manager configuration.

FATAL errors mean that the conversion process will fail unless you make changes to the Solaris Volume Manager configuration. A FATAL error does not stop preconvert from examining the rest of the Solaris Volume Manager configuration. FATAL errors that do not make sense may be related to earlier FATAL errors. Correct the earlier FATAL errors and run preconvert again to see if the later errors still exist.

The following are possible causes of FATAL errors:

- A metadevice is being initialized or resynchronized.
- A disk is offline.
- The /etc/vfstab file contains incorrect entries.

- An extended RAID-5 metadevice exists.
- A metadevice is using a hot spare.

Run showconvert

The showconvert utility displays the preconvert conversion plan in a readable format. The command showconvert help gives a list of command options.

showconvert keyword [arg ...]

The following keywords and arguments are defined for the showconvert command:

Displays error messages generated by the log preconvert utility. All FATAL messages must be resolved and preconvert run again before the conversion process can run successfully. list [diskgroup ...] Lists all the VxVM disk groups that will be created from Solaris Volume Manager disk sets and gives information about each disk group. These VxVM disk groups are not created to be compatible with CDS. Additionally, the disks in these disk groups are set up in slice and not cds format. To make the disk groups compatible with CDS, use the vxcdsconvert command. See the vxcdsconvert(1M) manual page. print diskgroup [vxprint args] Uses standard arguments from the VxVM vxprint utility and displays the VxVM objects that the conversion will create.

The conversion plan displayed by showconvert describes the layouts that the conversion utilities create. The layouts will have the same data on the same disks as the Solaris Volume Manager configuration. If you want different layouts, make changes to the Solaris Volume Manager configuration and run preconvert and showconvert again.

Run convertname

The convertname utility takes Solaris Volume Manager device paths as arguments (metadevice paths or raw disk paths) and returns the VxVM volume path for the device as it will show after the conversion. Use the command to make a list of path names for replacing references in applications. One or more device paths as arguments returns one line for each argument with the proposed VxVM path. Use absolute path names. For example:

convertname /dev/md/dsk/d2 /dev/md/rdsk/d3

Table 14-1 shows examples of how names are translated by the conversion process:

Table 14-1 Examples of the translation of device path names

Metadevice path	VxVM volume path		
/dev/md/dsk/d2	/dev/vx/dsk/rootdg/d2		
/dev/md/rdsk/d3	/dev/vx/rdsk/rootdg/d3		
/dev/md/setname/dsk/d10	/dev/vx/dsk/setname/d10		
/dev/md/setname/rdsk/d12	/dev/vx/rdsk/setname/d12		

The following metadevices do not retain their dN names or are converted from raw partitions that did not have dN names:

- The volume for the root file system is always named rootvol as a VxVM convention.
- A trans metadevice has its data device converted using the master device name. The log device is lost.
- A file system encapsulated from a raw partition is named for the last component of its mount point.
- A swap device on a disk that will include VxVM volumes after the conversion receives a name starting with swapvol.
- The /usr, /opt, and /var file systems when converted from being Solaris Volume Manager metadevices or when encapsulated retain the names /usr, /opt, and /var.

Warning: Any partition that is on a disk with Solaris Volume Manager metadevices and that is not listed as a file system in /etc/vfstab is lost during the conversion. The partition is considered free space when the disk is converted to VxVM control. Even if the partitions are in use, they are not encapsulated during the conversion. The raw partitions are lost when the disk layout changes. Either encapsulate the partition under the Solaris Volume Manager software and allow the conversion to convert the resulting metadevice, or back up the partition, plan to create a new volume for it, and restore the partition after the conversion.

Make backups

Make backups of all Solaris Volume Manager software-related files and information before running the conversion utility. If you need to return to the Solaris Volume Manager configuration, using backups is the recommended way.

Converting from the Solaris Volume Manager software to VxVM

Warning: This is the first step that makes changes, and that is not easily reversed. Be sure that you are ready for the conversion before performing this step. This step also includes downtime for volume management and leads to a reboot for the system.

Run the doconvert utility to start the conversion from the Solaris Volume Manager software to VxVM. A manual reboot of the system completes the conversion by updating configuration changes that were made by doconvert.

doconvert [force]

The doconvert utility checks that the VxVM licenses are correct, makes configuration changes, and then prompts for a system reboot. You must reboot the system immediately to complete the conversion process. If you run doconvert with the force option, the system is automatically rebooted without prompting you.

Warning: Do not make system configuration changes after running doconvert and before rebooting. Such changes can lead to loss of data.

If you choose not to reboot, the location of a script is given that allows you to reverse the changes to the system files made by doconvert. If you run this script, the system files are reinstated and the conversion is prevented from completing at the next reboot.

If doconvert fails, the system remains unchanged. You can then return to the preparation steps to correct the problems. The following situations cause doconvert to fail:

- The output of preconvert does not exist or is stale.
- The preconvert utility terminated with an error.
- VxVM licenses are not sufficient for the planned VxVM configuration.

■ A VxVM configuration already exists.

During the conversion, doconvert displays locations for some system file backups.

Reboot the system

Reboot the system immediately after doconvert finishes. During the reboot:

- If the system root device hosts Solaris Volume Manager objects or is a Solaris Volume Manager metadevice, the root device becomes a VxVM volume during the reboot. The process of making the root device a VxVM volume automatically starts a second reboot.
- If the system goes down, due to a power loss or other problem, the conversion process continues when the system boots again. Messages such as "Already exists..." appear for processes that completed before the system went down. These messages are harmless.

Change volume references

After the reboot, you must manually change references in applications that use Solaris Volume Manager metadevices. The references need to point to the new VxVM volumes.

See "Identify references by applications" on page 209.

See "Run convertname" on page 211.

Post conversion tasks

Do the following tasks at any time after a successful conversion.

Improve volume layouts

Start VxVM and use tools such as vxassist or the VxVM user interface to relayout volumes online. New layouts may require additional disk space.

You may want to create logs for converted RAID-5 volumes. RAID-5 logging from the Solaris Volume Manager configuration is not suitable for conversion to use by VxVM. Logs are not necessary for normal operations, but are useful for recovery. Use the following command to create a log for a RAID-5 volume:

vxassist [-g diskgroup] addlog volume

Remove the Solaris Volume Manager software

After the conversion, the Solaris Volume Manager software controls no data and is disabled. You can safely remove the Solaris Volume Manager software or you can re-initialize the Solaris Volume Manager software for use on disks not controlled by VxVM. The Solaris Volume Manager software and VxVM can run at the same time on the same machine.

Converting a root disk

The following steps allow you to move only a root disk from Solaris Volume Manager control to VxVM control. Use this procedure if you want to move only the root disk from the Solaris Volume Manager software to VxVM.

Warning: You cannot use the conversion utilities in a mixed environment. Even if you move only the root disk from the Solaris Volume Manager software to VxVM, you cannot later use the conversion utilities to move other Solaris Volume Manager objects to Veritas Volume Manager.

To convert a root disk

- Use the Solaris Volume Manager unencapsulation procedure to remove the root disk from Solaris Volume Manager control. See the Solaris Volume Manager documentation for details.
- Create VxVM volumes from the partitions on the root disk by encapsulating the root disk.

Online migration of a native file system to the VxFS file system

This chapter includes the following topics:

- About online migration of a native file system to the VxFS file system
- Administrative interface for online migration of a native file system to the VxFS file system
- Migrating a native file system to the VxFS file system
- Migrating a source file system to the VxFS file system over NFS v3
- Backing out an online migration of a native file system to the VxFS file system
- VxFS features not available during online migration


About online migration of a native file system to the VxFS file system

The online migration feature provides a method to migrate a native file system to the VxFS file system. The native file system is referred to as source file system and the VxFS file system as referred to as the target file system. The migration takes minimum amounts of clearly bounded, easy to schedule downtime. Online migration is not an in-place conversion and requires a separate storage. During online migration the application remains online and the native file system data is copied over to the VxFS file system. Both of the file systems are kept in sync during migration. This makes online migration back-out and recovery seamless.

The online migration tool also provides an option to throttle the background copy operation to speed up or slow down the migration based on your production needs.

Figure 15-1 illustrates the overall migration process.

Migration process Figure 15-1



You can migrate UFS file systems.

Administrative interface for online migration of a native file system to the VxFS file system

Online migration of a native file system to the VxFS file system can be started using the fsmigadm VxFS administrative command.

Table 15-1 describes the fsmigadm keywords.

Table 15-1

Keyword	Usage
analyze	Analyzes the source file system that is to be converted to VxFS and generates an analysis report.
start	Starts the migration.
list	Lists all ongoing migrations.
status	Shows a detailed status of the migration, including the percentage of completion, for the specified file system, or for all file systems under migration.

Keyword	Usage
throttle	Throttles the background copy operation.
pause	Pauses the background copy operation for one or more of migrations.
resume	Resumes the background copy operation if the operation was paused or the background copy operation was killed before the migration completed.
commit	Commits the migration.
abort	Aborts the migration.

Table 15-1 (continued)

See the fsmigadm(1M) manual page.

Migrating a native file system to the VxFS file system

The following procedure migrates a native file system to the VxFS file system.

Note: You cannot unmount the target (VxFS) file system nor the source file system after you start the migration. Only the commit or abort operation can unmount the target file system. Do not force unmount the source file system; use the abort operation to stop the migration and unmount the source file system.

To migrate a native file system to the VxFS file system

- Install Veritas Storage Foundation on the physical application host. See the Veritas Storage Foundation Installation Guide.
- Add new storage to the physical application host on which you will configure Veritas Volume Manager (VxVM).
- Create a VxVM volume according to the your desired configuration on the newly added storage. The volume size cannot be less than source file system size.
- Mount the source file system if the file system is not mounted already.
- 5 Run the fsmigadm analyze command and ensure that all checks pass:
 - # fsmigadm analyze /dev/vx/dsk/dg/vol1 /mnt1
- If the application is online, then shut down the application.
- 7 Start the migration by running fsmigadm start:

fsmigadm start /dev/vx/dsk/vol1 /mnt1

The fsmigadm command performs the following tasks:

- Unmounts the source file system.
- Creates a VxFS file system using the mkfs command on the new storage provided, specifying the same block size (*bsize*) as the source file system. You can use the -b blocksize option with fsmigadm start to specify your desired supported VxFS block size.
- Mounts the target file system.
- Mounts the source file system inside the target file system, as /mnt1/lost+found/srcfs.

You can perform the following operations during the migration on the target VxFS file system:

- You can get the status of the migration using the fsmigadm status command:
 - # fsmigadm status /mnt1
- You can speed up or slow down the migration using the fsmigadm throttle command:
 - # fsmigadm throttle 9g /mnt1
- You can pause the migration using fsmigadm pause command:
 - # fsmigadm pause /mnt1
- You can resume the migration using the fsmigadm resume command:
 - # fsmigadm resume /mnt1

The application can remain online throughout the entire migration operation. When the migration operation completes, you are alerted via the system log.

Both the target and the source file systems are kept up-to-date until the migration is committed.

- While the migration operation proceeds, you can bring the application online.
- Check the log file for any errors during migration. If you find any errors, you must copy the indicated files manually from the source file system after performing the commit operation.

10 After the migration operation completes, if you brought the application online while the migration operation proceeded, then shut down the application again.

11 Commit the migration:

fsmigadm commit /mnt1

The fsmigadm command unmounts the source file system, unmounts the target file system, and then remounts the migrated target VxFS file system on the same mount point.

12 Start the application on the Veritas Storage Foundation stack.

Migrating a source file system to the VxFS file system over NFS v3

When you migrate a file system over NFS v3, the NFS server exports the file system to the server's NFS clients. During the migration, only a single NFS client can mount the exported file system. The application on the host is only available on this NFS client node during migration.

The following procedure migrates a source file system to the VxFS file system over NFS v3.

Note: You cannot unmount the target (VxFS) file system nor the source file system after you start the migration. Only the commit or abort operation can unmount the target file system. Do not force unmount the source file system; use the abort operation to stop the migration and unmount the source file system.

Do not modify the exported file system from the NFS server during the migration.

To migrate a source file system to the VxFS file system over NFS v3

- Install Veritas Storage Foundation on the physical application host. See the Veritas Storage Foundation Installation Guide.
- Add new storage to the physical application host on which you will configure Veritas Volume Manager (VxVM).
- Create a VxVM volume according to the your desired configuration on the newly added storage. The volume size cannot be less than source file system size.

Mount the source file system if the file system is not mounted already.

```
# mount -V nfs3 cpeaixs07:/dump /mnt1
# mount
 node
      mounted mounted over vfs date options
______ _____
     /dev/hd4
                          jfs2 Feb 28 15:05 rw, log=/dev/hd8
```

/mnt1 nfs3 Mar 14 12:07

The source file system to be migrated is exported from NFS server. It is mounted on a single NFS client. The migration runs on this NFS client.

- Run the fsmigadm analyze command and ensure that all checks pass:
 - # fsmigadm analyze /dev/vx/rdsk/s03dg/vol1 /mnt1
- If the application is online, then shut down the application.
- 7 Start the migration by running fsmigadm start:

```
# fsmigadm start /dev/vx/rdsk/s03dg/vol1 /mnt1
```

mount

cpeaixs07 /dump

node	mounted	mounted over	vfs	date		options
	/dev/hd4	/	jfs2	Feb 28 1	5:05	rw,log=/dev/hd8
•••	/dev/vx/dsk/s03d	g/vol1 /mnt1	vxfs	Mar 14 1		migrate,rw,delaylog,suid,
cpeaixs0	7 /dump	/mnt1/lost+found	/srcfs	nfs3 Ma		, ,

- 8 While the migration operation proceeds, you can bring the application online.
- Check the log file for any errors during migration. If you find any errors, you must copy the indicated files manually from the source file system after performing the commit operation.
- **10** After the migration operation completes, shutdown the application.
- **11** Commit the migration:
 - # fsmigadm commit /mnt1

The fsmigadm command unmounts the source file system, unmounts the target file system, then mounts the target file system.

12 Start the application on the Veritas Storage Foundation stack.

Restrictions of NFS v3 migration

The following restrictions apply when you migrate over NFS v3:

- Migration over only NFS v3 is supported.
- The root directory must be exported from the NFS server to the NFS client.
- The source file system exported from the NFS Server to the NFS client must have 'root' and 'rw' permissions.
- The NFS server and the NFS client must be different nodes.

Backing out an online migration of a native file system to the VxFS file system

The following procedure backs out an online migration operation of a native file system to the VxFS file system.

Note: As both source and target file system are kept in sync during migration, the application sometimes experiences performance degradation.

In the case of a system failure, if the migration operation completed before the system crashed, then you are able to use the VxFS file system.

To back out an online migration operation of a native file system to the VxFS file system

- Shut down the application
- 2 Abort the migration:
 - # fsmigadm abort /mnt1

The source file system is mounted again.

Bring the application online.

VxFS features not available during online migration

During the online migration process, the following features are not supported on a file system that you are migrating:

- Block clear (blkclear) mount option
- Cached Quick I/O
- Cross-platform data sharing (portable data containers)

- Data management application programming interface (DMAPI)
- File Change Log (FCL)
- File promotion (undelete)
- **■** Fileset quotas
- **■** Forced unmount
- Online resize
- Quick I/O
- Quotas
- Reverse name lookup
- SmartTier
- Snapshots
- Storage Checkpoints
- Veritas Storage Foundation Cluster File System (SFCFS)

During the online migration process, the following commands are not supported on a file system that you are migrating:

- fiostat
- fsadm
- tar
- vxdump
- vxfreeze
- vxrestore
- vxupgrade

All of the listed features and commands become available after you commit the migration.

Note: Any source file system-specific features are not preserved on the target file system.

You cannot use online migration on a nested source mount point.

You cannot migrate from a VxFS file system to a VxFS file system.

Migrating storage arrays

This chapter includes the following topics:

- Array migration for storage using Linux
- Overview of storage mirroring for migration
- Allocating new storage
- Initializing the new disk
- Checking the current VxVM information
- Adding a new disk to the disk group
- Mirroring
- **■** Monitoring
- Mirror completion
- Removing old storage
- Post-mirroring steps

Array migration for storage using Linux

The array migration example documented for this use case uses a Linux system. The example details would be different for AIX, Solaris, or Windows systems.

Veritas Storage Foundation and High Availability Solutions (SFHA Solutions) products provide enterprise-class software tools which enable companies to achieve data management goals which would otherwise require more expensive hardware or time-consuming consultative solutions.

For many organizations, both large and small, storage arrays tend to serve as useful storage repositories for periods of 3-6 years. Companies are constantly

evaluating new storage solutions in their efforts to drive down costs, improve performance and increase capacity. The flexibility of Storage Foundation and High Availability Solutions enable efficient migration to new storage and improve the overall availability of data.

While there are several methods for accomplishing the migration, the most basic and traditional method is using a volume level mirror. The example procedures:

- Provide system administrators responsible for SFHA Solutions systems within their organization a demonstration of the steps required for performing an online storage array migration from one array to another.
- Illustrate the migration process using a Linux system which is connected to two different storage arrays through a SAN.
- Provide steps for starting with a file system with a single volume, mirroring the volume to a volume to another array, and then detaching the original storage.
- Are performed from the command prompt.
- Use Operating System Based Naming (OSN) for disk devices (sdb, sdc, etc).

There are two user interface options:

- The SFHA Solutions command line interface (CLI).
- The Veritas Operations Manager (VOM) graphical user interface (GUI) has a storage migration wizard.
 - See the Veritas Operations Manager documentation for details: https://sortsymanteccom/public/documents/vom/40u1/windowsandunix/productguides/pdf/vom sp addon userspdf

Note: Symantec's NetBackup PureDisk comes bundled with the Veritas Storage Foundation and High Availability Solutions software for the purpose of enhanced storage management and high availability. Storage arrays used with PureDisk can also be migrated using the SFHA Solutions methodologies.

Overview of storage mirroring for migration

The migration example occurs between a Hitachi 9900 array, 350 GB disk/LUN and a NetApps 3050 Fibre-Attached 199GB disk/LUN.

To migrate storage using storage mirroring

- Connect the new array to the SAN.
- Zone the array controller ports(s) to the server HBA port(s).
- Create or present the new LUN(s) on the array.

- Map the new LUN(s) to the server HBA port(s).
- 5 Stop any processes that are running on this volume or file system.
- 6 Rescan hardware using rescan-scsi-bus.sh and scsidev commands, or reboot (optional).
- Confirm that the operating system has access to the new target storage (Array-B).
- Bring new disks under Veritas Volume Manager (VxVM) control.
- 9 Start the VxVM mirroring process to synchronize the plexes between the source and target array enclosures.
- **10** Monitor the mirroring process.
- **11** After mirroring is complete, logically remove disks from VxVM control.

Note: The example Linux system happens to be running as a Symantec NetBackup Puredisk server which includes the Storage Foundation software. Puredisk also supports this mode of storage array migration.

12 Disconnect the old storage array (enclosure).

Allocating new storage

The first step to migrating array storage is to allocate new storage to the server.

To allocate new storage as in the example

- 1 Create the LUN(s) on the new array.
- 2 Map the new LUN(s) to the server.
- Zone the new LUN(s) to the server.
- Reboot or rescan using a native OS tool such as "fdisk" and the new external disk is now visible.

In the example, the original disk (/dev/sdb) has already been initialized by Veritas Volume Manager (VxVM). Note that it has a partition layout already established. Note also the different disk sizes. It may turn out that you want to use smaller or larger LUNs. This is fine, but if you are going to mirror to a smaller LUN you will need to shrink the original volume so that it can fit onto the physical disk device or LUNs.

```
ot@ny-puredisk:fdisk -1
isk /dev/sda: 80.0 GB, 80026361856 bytes
255 heads, 63 sectors/track, 9729 cylinders
Units - cylinders of 16065 * 512 - 8225280 bytes

        Start
        End
        Blocks
        Id
        System

        1
        13
        104391
        83
        Linux

        14
        1580
        125869271+
        82
        Linux swap / Solaris

        1581
        9729
        65456842+
        83
        Linux

    Device Boot
 dev/sda2
olsk /dev/sdb: 375.) GB, 375813308416 bytes
55 heads, 63 sectors/track, 45690 cylinders
htts - cylinders of 16065 * 512 - 8225280 bytes
                                                                                        Blocks Id System
366948666 5 Extended
1165+ 7f Unknown
366947343 7e Unknown
                                          Start
                                                                         End
    Device Boot
 dev/sdb4
 dev/sdb5
Disk /dev/sdc: 213 v GB, 213676323840 bytes
255 heads, 63 sectors/track, 25978 cylinders
Units - cylinders of 16065 * 512 - 8225280 bytes
                                                                      End
25976
    Device Boot
                                                                                         208652188+
                                                                                                                       5 Extended
dev/sdc4
 oot@ny-puredisk:
```

To shrink the original volume

◆ You can shrink the new volume size to *n* gigabytes:

```
# vxassist -g diskgroup_name shrinkto volume_name ng
```

Then resize the file system:

```
# /opt/VRTS/bin/fsadm -F vxfs -b new_size_in_sectors /Storage
```

Alternately, use the ${\tt vxresize}$ command to resize both the volume and the file system.

To grow the original volume

◆ You can increase the new volume size to *n* gigabytes:

```
# vxassist -g diskgroup name growto volume name ng
```

Then resize the file system:

```
# /opt/VRTS/bin/fsadm -F vxfs -b new size in sectors /Storage
```

Alternately, use the ${\tt vxresize}$ command to resize both the volume and the file system.

Note: SmartMove enables you to migrate from thick array LUNs to thin array LUNs on those enclosures that support Thin Provisioning.

Initializing the new disk

Now that the operating system recognizes the new disk, the next step is to initialize it.

To initialize the disk as in the example

Use the vxdisksetup command to establish the appropriate VxVM-friendly partition layout for Veritas Volume Manager.

Note below that the internal name *OLDDISK* is assigned to the old disk. The new disk is assigned a unique name later for the sake of clarity.

```
GROUP
DEVICE
                              DISK
                                                         STATUS
                                                         online invalid
ıda
             auto:none
                              OLDDISK
ıdb
             auto:sliced
                                                         online
de
                                                         online invalid
oot@ny-puredisk:
coot@ny-puredisk
oot@ny-puredisk:/usr/lib/vxvm/bin/vxdisksetup_sdc
coot@ny-puredisk:vxdisk list
        TYPE
auto:none
auto:sliced
                                            GROUP
                                                         STATUS
od a
                                                         online invalid
                             OLDDISK
                                           PDDG
                                                         online
db
                                                         online invalid
            auto:none
oot@ny-puredisk:
```

The disk is now initialized under VxVM control. Note below, that the disk has a new partition table similar to the existing disk (sdb)and is ready to be joined to the Veritas disk group *PDDG* (name of the example disk group).

```
oot@ny-puredisk:fdisk -1 /dev/sdc
Disk /dev/sdc: 213.6 GB, 213676323840 bytes
255 heads, 63 sectors/track, 25978 cylinders
Units - cylinders of 16065 * 512 - 8225280 bytes
                                                         208652188+ 5 Extended
1165+ 7f Unknown
208650865+ 7e Unknown
dev/sdc6
 oot@ny-puredisk:
```

Checking the current VxVM information

Check the VxVM information after initializing the new disk. The screen shot below illustrates all the disks on the server along with their corresponding partition tables. Note that disks *sdb* and *sdc* are partitioned in the same manner since they were both set up with the vxdisksetup command.

```
ot@ny-puredisk:fdisk -1
isk /dev/sda: 80.0 GB, 80026361856 bytes
55 heads, 63 sectors/track, 9729 cylinders
hits - cylinders of 16065 * 512 - 8225280 bytes
  Device Boot
                                                       Blocks
                                                    104391 83 Linux
12586927+ 82 Linux swap / Solaris
65456842+ 83 Linux
                                         13
1580
dev/sdal
Disk /dev/sdb: 375.8 GB, 375813308416 bytes
255 heads, 63 sectors/track, 45690 cylinders
Units - cylinders of 16065 * 512 - 8225280 bytes
                      Start End

1 45683 36

1 1

1 45683 36
                                                      Blocks
  Device Boot
                                                                   Id System
                                                                   5 Extended
dev/sdb4
                                                   366948666
                                                         1165+ 7£
dev/sdb5
Disk /dev/sdc: 213.6 GB, 213676323840 bytes
255 heads, 63 sectors/track, 25978 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
                       Start
                                          End
                                                      Blocks
                                                                   Id System
                                                                   5 Extended
dev/sdc4
                                                                    0 Empty
  ot@ny-puredisk:
```

The screen shot below shows the VxVM hierarchy for existing storage objects. Remember that we are working with a live and running server. We are using a logical disk group called PDDG which has other storage objects subordinate to it. The most important storage object here is the volume which is called Storage. The volume name can be any arbitrary name that you want, but for this example, the volume name is "Storage". The volume object is denoted by "v" in the output of the vxprint command. Other objects are subdisks (sd) which represents a single contiguous range of blocks on a single LUN. The other object here is a plex ("pl") which represents the virtual object or container to which the OS reads and writes. In vxprint, the length values are expressed in sectors, which in Linux are 512 bytes each. The raw volume size is 377487360 sectors in length, or when multiplied by 512 bytes (512*377487360) is 193273528320 bytes, or about 193 GB(2).

Notice that when the new disk was added it was 213GB yet the original existing Storage volume was 250GB. The Storage volume had to first be shrunk to a size equal the same (or smaller) number of sectors as the disk to which it would be mirrored.

TY NAME PUTILO	ASSOC	KSTATE	LENGTH	PLOFFS	STATE	TUTIL0	
dg PDDG	PDDG	-	-	-	-	-	-
dm OLDDISK	sdb	-	733894672	2 -	-	-	_
dm sdc	adc	-	417301712	2 -	-	-	-
v Storage	fsgen	ENABLED	377487360) -	ACTIVE	-	_
pl Storage-02	Storage	ENABLED	377487360) -	ACTIVE	-	-
ad OLDDISK-01	Storage-02	ENABLED	377487360	0 0	-	-	-

To shrink a volume as in the example Storage volume

Use the vxresize command:

```
# vxresize -f -t my-shrinktask -g PDDG Storage 193g
```

The original physical disk ("dm") that has been grouped into the *PDDG* diskgroup is called *sdb* but we have assigned the internal name *OLDDISK* for the purpose of this example. This can be done with the vxedit command using the rename operand. We also see the new disk (sdc) under VxVM control. It has been initialized but not yet assigned to any disk group.



Adding a new disk to the disk group

The next step is adding the new disk into the PDDG disk group and assigning the name of NEWDISK to the disk.

To add a new disk to the example disk group

- Initialize the disk.
- Add the disk into the *PDDG* disk group


```
root@ny-puredisk:vxdisk init sdc
root@ny-puredisk:vxdg -g PDDG adddisk sdo
root@ny-puredisk:vxprint
v Storage fsgen ENABLED 377487360 - ACTIVE -
pl Storage-02 Storage ENABLED 377487360 - ACTIVE -
sd OLDDISK-01 Storage-02 ENABLED 377487360 0 - -
```

The internal VxVM name of the new disk is changed from the default disk to NEWDISK.

Disk gr	oup: PDD							
TY NAME		ASSOC	KSTATE	LENGTH	PLOFFS	STATE	TUTILO	PUTILO
dg PDDG		PDDG	-	-	-	-	-	-
dn OLDD	ISK	adb	-	733894672	-	-	-	-
dn NEWD	ISK	sdc	-	417301712	-	-	-	-
v Stor	age	fsgen	ENABLED	377487360	-	ACTIVE	-	-
pl Stor	age-02	Storage	ENABLED	377487360	-	ACTIVE	-	-
sd OLDD	ISK-01	Storage-02	ENABLED	377487360		-	-	-

Mirroring

The next step is to start the mirroring process. We used the vxassist command to transform the Storage volume from a simple, concatenated volume into a mirrored volume. Optionally, a DRL (Dirty Region Log) can be added to the volume. If enabled, the DRL speeds recovery of mirrored volumes after a system crash. It requires an additional 1 Megabyte of extra disk space.



To add a DRL as in the example Storage volume

Use:

vxassist -g PDDG addlog Storage logtype=drl

For more information about DRL logging,:

See the Veritas Storage Foundation Administrator's Guide


Monitoring

The mirroring process must complete before you can proceed. During this time there may be a heavy I/O load on the system as the mirroring process reads from one disk and writes to another.

To monitor the mirroring progress

Use the vxtask list command.

Raw I/O statistics can also be monitored with the vxstat command. Mirroring should be done either during times of low demand on the server, or, optionally, to have the services stopped completely. While the initial synchronization is underway, the STATE of the new plex is still TEMPRMSD.



To pause and resume mirroring

Use the vxtask command.

To throttle the mirroring process and free up I/O if needed

Use the vxtask command.


```
oot@ny-puredisk:vxtask list
TASKID PTID TYPE/STATE
                               PROGRESS
                ATCOPY/R 00.12% 0/377487360/449792 PLXATT Storage Storage-01 PDDG
```

The TEMPRMSD plex state is used by wassist when attaching new data plexes to a volume. If the synchronization operation does not complete, the plex and its subdisks are removed.

See http://www.symantec.com/docs/TECH19044

Mirror completion

When the mirroring completes, you can see that the output from vxprint shows the volume now has two active plexes associated with it. This is the mirrored volume comprised of two plexes, each plex residing on separate physical storage arrays.



To confirm completion of the mirror task

Use the vxtask command.

Removing old storage

After the mirroring process completes, you can remove the old storage.

To remove the old storage

- Break the mirror.
- 2 Logically detach the old disk (*OLDDISK*, *sdb*).
- 3 Check the viability of the volume. Services do not need to be stopped during this phase.
- Remove the old storage from the diskgroup.

root@ny-p	uredisk:vxdisk lis	st		
DEVICE	TYPE	DISK	GROUP	STATUS
sda	auto:none	-	-	online invalid
sdb	auto:sliced		-	online
sda	auto:sliced	NEWDISK	PDDG	online

)185	k group: PDI	DG						
Y	NAME	ASSOC	KSTATE	LENGTH	PLOFFS	STATE	TUTIL0	PUTILO
lg	PDDG	PDDG	-	-	-	-	-	-
'n	NEWDISK	adc	-	417301712	- 5	-	-	-
'n	OLDDISK	adb	-	733894672	2 -	-	-	-
	Storage	fagen	ENABLED	377487360	-	ACTIVE	-	-
1	Storage-01	Storage	ENABLED	377487360) -	ACTIVE	-	-
d	NEMDISK-01	Storage-01	ENABLED	377487360	0 0	-	-	-

The use of the backslash is necessary to override the significance of "!" to the bash Shell which is the default shell for root user. Without the "\", the bash (or C Shell) command line interpreter would look for some history of command event.

Post-mirroring steps

The last step is to check on application services by running whatever utilities you have to ensure the applicatio is up. At some point, a reboot should be done at this point to ensure that the system properly starts and can access the disks during a reboot. No additional modifications need to be made to the file system mount table (etc/fstab, for example) since all storage, disk group, and volume object names remain unchanged.

Migrating data between platforms

This chapter includes the following topics:

- Overview of the Cross-Platform Data Sharing (CDS) feature
- CDS disk format and disk groups
- Setting up your system to use Cross-platform Data Sharing (CDS)
- Maintaining your system
- **■** File system considerations
- Alignment value and block size
- Disk group alignment and encapsulated disks
- Disk group import between Linux and non-Linux machines
- Migrating a snapshot volume

Overview of the Cross-Platform Data Sharing (CDS) feature

This section presents an overview of the Cross-Platform Data Sharing (CDS) feature of Symantec's Veritas Storage Foundation™ software. CDS provides you with a foundation for moving data between different systems within a heterogeneous environment. The machines may be running HP-UX, AIX, Linux or the Solaris™ operating system (OS), and they may all have direct access to physical devices holding data. CDS allows Symantec's Veritas products and

applications to access data storage independently of the operating system platform, enabling them to work transparently in heterogeneous environments.

The Cross-Platform Data Sharing feature is also known as Portable Data Containers (PDC). For consistency, this document uses the name Cross-Platform Data Sharing throughout.

The following levels in the device hierarchy, from disk through file system, must provide support for CDS to be used:

End-user applications Application level.

Veritas™ File System (VxFS) File system level.

Veritas[™] Volume Manager (VxVM) Volume level.

Operating system Device level.

CDS is a license-enabled feature that is supported at the disk group level by VxVM and at the file system level by VxFS.

CDS utilizes a new disk type (auto:cdsdisk). To effect data sharing, VxVM supports a new disk group attribute (cds) and also supports different OS block sizes.

Note: CDS allows data volumes and their contents to be easily migrated between heterogeneous systems. It does not enable concurrent access from different types of platform unless such access is supported at all levels that are required.

Shared data across platforms

While volumes can be exported across platforms, the data on the volumes can be shared only if data sharing is supported at the application level. That is, to make data sharing across platforms possible, it must be supported throughout the entire software stack.

For example, if a VxFS file system on a VxVM volume contains files comprising a database, then the following functionality applies:

- Disks can be recognized (as cds disks) across platforms.
- Disk groups can be imported across platforms.
- The file system can be mounted on different platforms.

However, it is very likely that, because of the inherent characteristics of databases, you may not be able to start up and use the database on a platform different from the one on which it was created.

An example is where an executable file, compiled on one platform, can be accessed across platforms (using CDS), but may not be executable on a different platform.

Note: You do not need a file system in the stack if the operating system provides access to raw disks and volumes, and the application can utilize them. Databases and other applications can have their data components built on top of raw volumes without having a file system to store their data files.

Disk drive sector size

Sector size is an attribute of a disk drive (or SCSI LUN for an array-type device), which is set when the drive is formatted. Sectors are the smallest addressable unit of storage on the drive, and are the units in which the device performs I/O. The sector size is significant because it defines the atomic I/O size at the device level. Any multi-sector writes which VxVM submits to the device driver are not guaranteed to be atomic (by the SCSI subsystem) in the case of system failure.

Block size issues

The block size is a platform-dependent value that is greater than or equal to the sector size. Each platform accesses the disk on block boundaries and in quantities that are multiples of the block size.

Data that is created on one platform, and then accessed by a platform of a different block size, can suffer from the following problems:

- Addressing issues

 The data may not have been created on a block boundary compatible with that used by the accessing platform.
 - The accessing platform cannot address the start of the data.

Bleed-over issues

The size of the data written may not be an exact multiple of the block size used by the accessing platform. Therefore the accessing platform cannot constrain its I/O within the boundaries of the data on disk.

Operating system data

Some operating systems (OS) require OS-specific data on disks in order to recognize and control access to the disk.

CDS disk format and disk groups

This section provides additional information about CDS disk format and CDS disk groups.

CDS disk access and format

For a disk to be accessible by multiple platforms, the disk must be consistently recognized by the platforms, and all platforms must be capable of performing I/O on the disk. CDS disks contain specific content at specific locations to identify or control access to the disk on different platforms. The same content and location are used on all CDS disks, independent of the platform on which the disks are initialized.

In order for a disk to be initialized as, or converted to a CDS disk, it must satisfy the following requirements:

- Must be a SCSI disk
- Must be the entire physical disk (LUN)
- Only one volume manager (such as VxVM) can manage a physical disk (LUN)
- There can be no disk partition (slice) which is defined, but which is not configured on the disk
- Cannot contain a volume whose use-type is either root or swap (for example, it cannot be a boot disk)

The CDS conversion utility, vxcdsconvert, is provided to convert non-CDS VM disk formats to CDS disks, and disk groups with a version number less than 110 to disk groups that support CDS disks.

See "Converting non-CDS disks to CDS disks" on page 249.

Note: Disk groups with version numbers less than 110 are not supported for the Solaris OS on the x64 platform.

CDS disk types

The CDS disk format, cdsdisk, is recognized by all VxVM platforms. The cdsdisk disk format is the default for all newly-created VM disks unless overridden in a defaults file. The vxcdsconvert utility is provided to convert other disk formats and types to CDS.

See "Defaults files" on page 253.

Note: Disks with format cdsdisk can only be added to disk groups with version 110 or later.

Private and public regions

A VxVM disk usually has a private and a public region.

The private region is a small area on the disk where VxVM configuration information is stored, such as a disk header label, configuration records for VxVM objects (such as volumes, plexes and subdisks), and an intent log for the configuration database. The default private region size is 32MB, which is large enough to record the details of several thousand VxVM objects in a disk group.

The public region covers the remainder of the disk, and is used for the allocation of storage space to subdisks.

The private and public regions are aligned and sized in multiples of 8K to permit the operation of CDS. The alignment of VxVM objects within the public region is controlled by the disk group alignment attribute. The value of the disk group alignment attribute must also be 8K to permit the operation of CDS.

Note: With other (non-CDS) VxVM disk formats, the private and public regions are aligned to the platform-specific OS block size.

Disk access type auto

The disk access (DA) type auto supports multiple disk formats, including cdsdisk, which is supported across all platforms. It is associated with the DA records created by the VxVM auto-configuration mode. Disk type auto automatically determines which format is on the disk.

Platform block

The platform block resides on disk sector 0, and contains data specific to the operating system for the platforms. It is necessary for proper interaction with each of those platforms. The platform block allows a disk to perform as if it was initialized by each of the specific platforms.

AIX coexistence label

The AIX coexistence label resides on the disk, and identifies the disk to the AIX logical volume manager (LVM) as being controlled by VxVM.

HP-UX coexistence label

The HP-UX coexistence label resides on the disk, and identifies the disk to the HP logical volume manager (LVM) as being controlled by VxVM.

VxVM ID block

The VxVM ID block resides on the disk, and indicates the disk is under VxVM control. It provides dynamic VxVM private region location and other information.

About Cross-platform Data Sharing (CDS) disk groups

A Cross-platform Data Sharing (CDS) disk group allows cross-platform data sharing of Veritas Volume Manager (VxVM) objects, so that data written on one of the supported platforms may be accessed on any other supported platform. A CDS disk group is composed only of CDS disks (VxVM disks with the disk format cdsdisk), and is only available for disk group version 110 and greater.

Starting with disk group version 160, CDS disk groups can support disks of greater than 1 TB.

Note: The CDS conversion utility, vxcdsconvert, is provided to convert non-CDS VxVM disk formats to CDS disks, and disk groups with a version number less than 110 to disk groups that support CDS disks.

See "Converting non-CDS disks to CDS disks" on page 249.

All VxVM objects in a CDS disk group are aligned and sized so that any system can access the object using its own representation of an I/O block. The CDS disk group uses a platform-independent alignment value to support system block sizes of up to 8K.

See "Disk group alignment" on page 243.

CDS disk groups can be used in the following ways:

- Initialized on one system and then used "as-is" by VxVM on a system employing a different type of platform.
- Imported (in a serial fashion) by Linux, Solaris, AIX, and HP-UX systems.
- Imported as private disk groups, or shared disk groups (by CVM).

You cannot include the following disks or volumes in a CDS disk group:

- Volumes of usage type root and swap. You cannot use CDS to share boot devices.
- Encapsulated disks.

Note: On Solaris and Linux systems, the process of disk encapsulation places the slices or partitions on a disk (which may contain data or file systems) under VxVM control. On AIX and HP-UX systems, LVM volumes may similarly be converted to VxVM volumes.

Device quotas

Device quotas limit the number of objects in the disk group which create associated device nodes in the file system. Device quotas are useful for disk groups which to be transferred between Linux with a pre-2.6 kernel and other supported platforms. Prior to the 2.6 kernel, Linux supported only 256 minor devices per major device.

You can limit the number of devices that can be created in a given CDS disk group by setting the device quota.

See "Setting the maximum number of devices for CDS disk groups" on page 261.

When you create a device, an error is returned if the number of devices would exceed the device quota. You then either need to increase the quota, or remove some objects using device numbers, before the device can be created.

See "Displaying the maximum number of devices in a CDS disk group" on page 265.

Minor device numbers

Importing a disk group will fail if it will exceed the maximum devices for that platform.

Note: There is a large disparity between the maximum number of devices allowed for devices on the Linux platform with a pre-2.6 kernel, and that for other supported platforms.

Non-CDS disk groups

Any version 110 (or greater) disk group (DG) can contain both CDS and non-CDS disks. However, only version 110 (or greater) disk groups composed entirely of CDS disks have the ability to be shared across platforms. Whether or not that ability has been enabled is a controlled by the cds attribute of the disk group. Enabling this attribute causes a non-CDS disk group to become a CDS disk group.

Although a non-CDS disk group can contain a mixture of CDS and non-CDS disks having dissimilar private region alignment characteristics, its disk group alignment will still direct how all subdisks are created.

Disk group alignment

One of the attributes of the disk group is the block alignment, which represents the largest block size supported by the disk group.

The alignment constrains the following attributes of the objects within a disk group:

Subdisk offset

- Subdisk length
- Plex offset
- Volume length
- Log length
- Stripe width

The offset value specifies how an object is positioned on a drive.

The disk group alignment is assigned at disk group creation time.

See "Disk group tasks" on page 257.

Alignment values

The disk group block alignment has two values: 1 block or 8k (8 kilobytes).

All CDS disk groups must have an alignment value of 8k.

All disk group versions before version 110 have an alignment value of 1 block, and they retain this value if they are upgraded to version 110 or later.

A disk group that is not a CDS disk group, and which has a version of 110 and later, can have an alignment value of either 1 block or 8k.

The alignment for all newly initialized disk groups in VxVM 4.0 and later releases is 8k. This value, which is used when creating the disk group, cannot be changed. However, the disk group alignment can be subsequently changed.

See "Changing the alignment of a non-CDS disk group" on page 258.

Note: The default usage of vxassist is to set the layout=diskalign attribute on all platforms. The layout attribute is ignored on 8K-aligned disk groups, which means that scripts relying on the default may fail.

Dirty region log alignment

The location and size of each map within a dirty region log (DRL) must not violate the disk group alignment for the disk group (containing the volume to which the DRL is associated). This means that the region size and alignment of each DRL map must be a multiple of the disk group alignment, which for CDS disk groups is 8K. (Features utilizing the region size can impose additional minimums and size increments over and above this restriction, but cannot violate it.)

In a version 110 disk group, a traditional DRL volume has the following region requirements:

■ Minimum region size of 512K

■ Incremental region size of 64K

In a version 110 disk group, an instant snap DCO volume has the following region requirements:

- Minimum region size of 16K
- Incremental region size of 8K

Object alignment during volume creation

For CDS disk groups, VxVM objects that are used in volume creation are automatically aligned to 8K. For non-CDS disk groups, the vxassist attribute, dgalign checking, controls how the command handles attributes that are subject to disk group alignment restrictions. If set to strict, the volume length and values of attributes must be integer multiples of the disk group alignment value, or the command fails and an error message is displayed. If set to round (default), attribute values are rounded up as required. If this attribute is not specified on the command-line or in a defaults file, the default value of round is used.

The diskalign and nodiskalign attributes of vxassist, which control whether subdisks are aligned on cylinder boundaries, is honored only for non-CDS disk groups whose alignment value is set to 1.

Setting up your system to use Cross-platform Data **Sharing (CDS)**

In order to migrate data between platforms using Cross-platform Data Sharing (CDS), set up your system to use CDS disks and CDS disk groups. The CDS license must be enabled. You can use the default files to configure the appropriate settings for CDS disks and disk groups.

Table 17-1 describes the tasks for setting up your system to use CDS.

Task **Procedures** Create the CDS disks. You can create a CDS disk in one of the following ways: Creating CDS disks from uninitialized See "Creating CDS disks from uninitialized disks" on page 246. ■ Creating CDS disks from initialized VxVM disks See "Creating CDS disks from initialized VxVM disks" on page 247. ■ Converting non-CDS disks to CDS disks See "Converting non-CDS disks to CDS disks" on page 249. Create the CDS disk groups. You can create a CDS disk group in one of the following ways: ■ Creating CDS disk groups See "Creating CDS disk groups" on page 248. ■ Converting a non-CDS disk group to a CDS disk group See "Converting a non-CDS disk group to a CDS disk group" on page 251. Verify the CDS license. Verifying licensingSee "Verifying licensing" on page 253.

Table 17-1 Setting up CDS disks and CDS disk groups

Creating CDS disks from uninitialized disks

You can create a CDS disk from an uninitialized disk by using one of the following methods:

Defaults files See "Defaults files" on page 253.

■ Creating CDS disks by using vxdisksetup

Verify the system defaults related to CDS.

Creating CDS disks by using vxdiskadm

Creating CDS disks by using vxdisksetup

To create a CDS disk by using the vxdisksetup command

■ Type the following command:

vxdisksetup -i disk [format=disk format]

The format defaults to cdsdisk unless this is overridden by the /etc/default/vxdisk file, or by specifying the disk format as an argument to the format attribute.

See "Defaults files" on page 253.

See the vxdisksetup(1M) manual page.

Creating CDS disks by using vxdiskadm

To create a CDS disk by using the vxdiskadm command

■ Run the vxdiskadm command, and select the "Add or initialize one or more disks" item from the main menu. You are prompted to specify the format.

Warning: On CDS disks, the CDS information occupies the first sector of that disk, and there is no fdisk partition information. Attempting to create an fdisk partition (for example, by using the fdisk or format commands) erases the CDS information, and can cause data corruption.

Creating CDS disks from initialized VxVM disks

How you create a CDS disk depends on the current state of the disk, as follows:

- Creating a CDS disk from a disk that is not in a disk group
- Creating a CDS disk from a disk that is already in a disk group

Creating a CDS disk from a disk that is not in a disk group

To create a CDS disk from a disk that is not in a disk group

- Run the following command to remove the VM disk format for the disk:
 - # vxdiskunsetup disk

This is necessary as non-auto types cannot be reinitialized by vxdisksetup.

- If the disk is listed in the /etc/vx/darecs file, remove its disk access (DA) record using the command:
 - # vxdisk rm disk

(Disk access records that cannot be configured by scanning the disks are stored in an ordinary file, /etc/vx/darecs, in the root file system. Refer to the vxintro(1M) manual page for more information.)

- **3** Rescan for the disk using this command:
 - # vxdisk scandisks
- Type this command to set up the disk:
 - # vxdisksetup -i disk

Creating a CDS disk from a disk that is already in a disk group

To create a CDS disk from a disk that is already in a disk group

■ Run the vxcdsconvert command. See "Converting non-CDS disks to CDS disks" on page 249.

Creating CDS disk groups

You can create a CDS disk group in the following ways:

- Creating a CDS disk group by using vxdg init
- Creating a CDS disk group by using vxdiskadm

Creating a CDS disk group by using vxdg init

Note: The disk group version must be 110 or greater.

To create a CDS disk group by using the vxdq init command

■ Type the following command:

vxdg init diskgroup disklist [cds={on|off}]

The format defaults to a CDS disk group, unless this is overridden by the /etc/default/vxdg file, or by specifying the cds argument. See the vxdg(1M) manual page for more information.

Creating a CDS disk group by using vxdiskadm

You cannot create a CDS disk group when encapsulating an existing disk, or when converting an LVM volume.

When initializing a disk, if the target disk group is an existing CDS disk group, vxdiskadm will only allow the disk to be initialized as a CDS disk. If the target disk group is a non-CDS disk group, the disk can be initialized as either a CDS disk or a non-CDS disk.

If you use the vxdiskadm command to initialize a disk into an existing CDS disk group, the disk must have be added with the cdsdisk format.

The CDS attribute for the disk group remains unchanged by this procedure.

To create a CDS disk group by using the vxdiskadm command

■ Run the vxdiskadm command, and select the "Add or initialize one or more disks" item from the main menu. Specify that the disk group should be a CDS disk group when prompted.

Converting non-CDS disks to CDS disks

Note: The disks must be of type of auto in order to be re-initialized as CDS disks.

To convert non-CDS disks to CDS disks

- If the conversion is not going to performed on-line (that is, while access to the disk group continues), stop any applications that are accessing the disks.
- Make sure that the disks have free space of at least 256 sectors before doing the conversion.

Add a disk to the disk group for use by the conversion process. The conversion process evacuates objects from the disks, reinitializes the disks, and relocates objects back to the disks.

Note: If the disk does not have sufficient free space, the conversion process will not be able to relocate objects back to the disk. In this case, you may need to add additional disks to the disk group.

Type one of the following forms of the CDS conversion utility (vxcdsconvert) to convert non-CDS disks to CDS disks.

```
# vxcdsconvert -q diskgroup [-A] [-d defaults file] \
 [-o novolstop] disk name [attribute=value] ...
# vxcdsconvert -q diskgroup [-A] [-d defaults file] \
 [-o novolstop] alldisks [attribute=value] ...
```

The alldisks and disk keywords have the following effect

Converts all non-CDS disks in the disk group into CDS disks. alldisks

Specifies a single disk for conversion. You would use this option disk under the following circumstances:

- If a disk in the non-CDS disk group has cross-platform exposure, you may want other VxVM nodes to recognize the disk, but not to assume that it is available for initialization.
- If the native Logical Volume Manager (LVM) that is provided by the operating system needs to recognize CDS disks, but it is not required to initialize or manage these disks.
- Your intention is to move the disk into an existing CDS disk group.

Specify the -o novolstop option to perform the conversion on-line (that is, while access to the disk continues). If the -o novolstop option is not specified, stop any applications that are accessing the disks, and perform the conversion off-line.

Warning: Specifying the -o novolstop option can greatly increase the amount of time that is required to perform conversion.

Before you use the vxcdsconvert command, make sure you understand its options, attributes, and keywords.

See the vxcdsconvert(1M) manual page.

Converting a non-CDS disk group to a CDS disk group

To convert a non-CDS disk group to a CDS disk group

- If the disk group contains one or more disks that you do not want to convert to CDS disks, use the vxdg move or vxdg split command to move the disks out of the disk group.
- The disk group to be converted must have the following characteristics:
 - No dissociated or disabled objects.
 - No sparse plexes.
 - No volumes requiring recovery.
 - No volumes with pending snapshot operations.
 - No objects in an error state.

To verify whether a non-CDS disk group can be converted to a CDS disk group, type the following command:

- # vxcdsconvert -g diskgroup -A group
- If the disk group does not have a CDS-compatible disk group alignment, the objects in the disk group must be relayed out with a CDS-compatible alignment.
- If the conversion is not going to performed on-line (that is, while access to the disk group continues), stop any applications that are accessing the disks.
- Type one of the following forms of the CDS conversion utility (vxcdsconvert) to convert a non-CDS disk group to a CDS disk group.

```
# vxcdsconvert -g diskgroup [-A] [-d defaults file] \
  [-o novolstop] alignment [attribute=value] ...
# vxcdsconvert -g diskgroup [-A] [-d defaults file] \
  [-o novolstop] group [attribute=value] ...
```

The alignment and group keywords have the following effect:

Specifies alignment conversion where disks are not converted, alignment and an object relayout is performed on the disk group. A successful completion results in an 8K-aligned disk group. You might consider this option, rather than converting the entire disk group, if you want to reduce the amount of work to be done for a later full conversion to CDS disk group.

Specifies group conversion of all non-CDS disks in the disk group group

before realying out objects in the disk group.

The conversion involves evacuating objects from the disk, reinitializing the disk, and relocating objects back to disk. You can specify the -o novolstop option to perform the conversion on-line (that is, while access to the disk group continues). If the -o novolstop option is not specified, stop any applications that are accessing the disks, and perform the conversion off-line.

Warning: Specifying the -o novolstop option can greatly increase the amount of time that is required to perform conversion.

Conversion has the following side effects:

- Non-CDS disk group are upgraded by using the vxdg upgrade command. If the disk group was originally created by the conversion of an LVM volume group (VG), rolling back to the original LVM VG is not possible. If you decide to go through with the conversion, the rollback records for the disk group will be removed, so that an accidental rollback to an LVM VG cannot be done.
- Stopped, but startable volumes, are started for the duration of the conversion.
- Any volumes or other objects in the disk group that were created with the layout=diskalign attribute specified can no longer be disk aligned.
- Encapsulated disks may lose the ability to be unencapsulated.
- Performance may be degraded because data may have migrated to different regions of a disk, or to different disks.

In the following example, the disk group, mydq, and all its disks are converted to CDS while keeping its volumes are still online:

```
# vxcdsconvert -g mydg -o novolstop group \
 move_subdisks_ok=yes evac_subdisks_ok=yes \
 evac disk list=disk11,disk12,disk13,disk14
```

The evac disk list attrinute specifies a list of disks (disk11 through disk14) to which subdisks can be evacuated to disks if required.

Before you use the vxcdsconvert command, make sure you understand its options, attributes, and keywords.

See the vxcdsconvert(1M) manual page.

Verifying licensing

The ability to create or import a CDS disk group is controlled by a CDS license. CDS licenses are included as part of the Veritas Storage Foundation license.

To verify the CDS enabling license

■ Type the following command:

vxlicrep

Verify the following line in the output:

Cross-platform Data Sharing = Enabled

Defaults files

The following system defaults files in the /etc/default directory are used to specify the alignment of VxVM objects, the initialization or encapsulation of VM disks, the conversion of LVM disks, and the conversion of disk groups and their disks to the CDS-compatible format

vxassist.

Specifies default values for the following parameters to the vxcdsconvert command that have an effect on the alignment of VxVM objects: dgalign checking, diskalign, and nodiskalign.

See "Object alignment during volume creation" on page 245.

See the vxassist(1M) manual page.

Setting up your system to use Cross-platform Data Sharing (CDS)

vxcdsconvert

Specifies default values for the following parameters to the

vxcdsconvertcommand:evac disk list, evac subdisks ok, min split size, move subdisks ok, privlen, and

split subdisks ok.

The following is a sample vxcdsconvert defaults file:

evac subdisks ok=no min split size=64k move subdisks ok=yes privlen=2048 split subdisks ok=move

An alternate defaults file can be specified by using the -d option with the vxcdsconvert command.

See the vxcdsconvert(1M) manual page.

vxdg

Specifies default values for the cds, default activation mode and enable activation parameters to the vxdg command. The default activation mode and enable activation parameters are only used with shared disk groups in a cluster.

The following is a sample vxdq defaults file:

cds=on

See the vxdg(1M) manual page.

vxdisk

Specifies default values for the format and privlen parameters to the vxdisk and vxdisksetup commands. These commands are used when disks are initialized by VxVM for the first time. They are also called implicitly by the vxdiskadm command and the Veritas Operations Manager (VOM) GUI.

The following is a sample vxdisk defaults file:

format=cdsdisk privlen=2048

See the vxdisk(1M) manual page.

See the vxdisksetup(1M) manual page.

vxencap

Specifies default values for the format, privlen, privoffset and puboffset parameters to the vxencap and vxlvmencap commands. These commands are used when disks with existing partitions or slices are encapsulated, or when LVM disks are converted to VM disks. It is also called implicitly by the vxdiskadm, vxconvert (on AIX) and vxvmconvert (on HP-UX) commands, and by the VOM.

The following is a sample vxencap defaults file:

format=sliced privlen=4096 privoffset=0 puboffset=1

See the vxencap(1M) manual page.

See the vxconvert(1M) manual page.

See the vxvmconvert(1M) manual page.

In the defaults files, a line that is empty, or that begins with a "#" character in the first column, is treated as a comment, and is ignored.

Apart from comment lines, all other lines must define attributes and their values using the format attribute=value. Each line starts in the first column, and is terminated by the value. No white space is allowed around the = sign.

Maintaining your system

You may need to perform maintenance tasks on the CDS disks and CDS disk groups. Refer to the respective section for each type of task.

- Disk tasks See "Disk tasks" on page 256.
- Disk group tasks See "Disk group tasks" on page 257.
- Displaying information See "Displaying information" on page 264.
- Default activation mode of shared disk groups See "Default activation mode of shared disk groups" on page 267.
- Additional considerations when importing CDS disk groups See "Defaults files" on page 253.

Disk tasks

The following disk tasks are supported:

- Changing the default disk format
- Restoring CDS disk labels

Changing the default disk format

When disks are put under VxVM control, they are formatted with the default cdsdisk layout. This happens during the following operations:

- Initialization of disks
- Encapsulation of disks with existing partitions or slices (Linux and Solaris systems)
- Conversion of LVM disks (AIX, HP-UX and Linux systems)

You can override this behavior by changing the settings in the system defaults files. For example, you can change the default format to sliced for disk initialization by modifying the definition of the format attribute in the /etc/default/vxdisk defaults file.

To change the default format for disk encapsulation or LVM disk conversion

■ Edit the /etc/default/vxencap defaults file, and change the definition of the format attribute.

See "Defaults files" on page 253.

Restoring CDS disk labels

CDS disks have the following labels:

- Platform block
- AIX coexistence label
- HP-UX coexistence or VxVM ID block

There are also backup copies of each. If any of the primary labels become corrupted, VxVM will not bring the disk online and user intervention is required.

If two labels are intact, the disk is still recognized as a cdsdisk (though in the error state) and vxdisk flush can be used to restore the CDS disk labels from their backup copies.

Note: For disks larger than 1 TB, cdsdisks use the EFI layout. The procedure to restore disk labels does not apply to cdsdisks with EFI layout.

Primary labels are at sectors 0, 7, and 16; and a normal flush will not flush sectors 7 and 16. Also, the private area is not updated as the disk is not in a disk group. There is no means of finding a "good" private region to flush from. In this case, it is possible to restore the CDS disk labels from the existing backups on disk using the flush operation.

If a corruption happened after the labels were read and the disk is still online and part of a disk group, then a flush operation will also flush the private region.

Warning: Caution and knowledge must be employed because the damage could involve more than the CDS disk labels. If the damage is constrained to the first 128K, the disk flush would fix it. This could happen if another system on the fabric wrote a disk label to a disk that was actually a CDS disk in some disk group.

To rewrite the CDS ID information on a specific disk

■ Type the following command:

```
# vxdisk flush disk access name
```

This rewrites all labels except sectors 7 and 16.

To rewrite all the disks in a CDS disk group

■ Type the following command:

```
# vxdg flush diskgroup
```

This rewrites all labels except sectors 7 and 16.

To forcibly rewrite the AIX coexistence label in sector 7 and the HP-UX coexistence label or VxVM ID block in sector 16

■ Type the following command:

```
# vxdisk -f flush disk access name
```

This command rewrites all labels if there exists a valid VxVM ID block that points to a valid private region. The -f option is required to rewrite sectors 7 and 16 when a disk is taken offline due to label corruption (possibly by a Windows system on the same fabric).

Disk group tasks

The following disk group tasks are supported:

- Changing the alignment of a disk group during disk encapsulation
- Changing the alignment of a non-CDS disk group

- Determining the setting of the CDS attribute on a disk group
- Splitting a CDS disk group
- Moving objects between CDS disk groups and non-CDS disk groups
- Moving objects between CDS disk groups
- Joining disk groups
- Changing the default CDS setting for disk group creation
- Creating non-CDS disk groups
- Upgrading an older version non-CDS disk group
- Replacing a disk in a CDS disk group
- Setting the maximum number of devices for CDS disk groups

Changing the alignment of a disk group during disk encapsulation

If you use the vxdiskadm command to encapsulate a disk into a disk group with an alignment of 8K, the disk group alignment must be reduced to 1.

If you use the vxencap command to perform the encapsulation, the alignment is carried out automatically without a confirmation prompt.

To change the alignment of a disk group during disk encapsulation

■ Run the vxdiskadm command, and select the "Add or initialize one or more disks" item from the main menu. As part of the encapsulation process, you are asked to confirm that a reduction of the disk group alignment from 8K to 1 is acceptable.

Changing the alignment of a non-CDS disk group

The alignment value can only be changed for disk groups with version 110 or greater.

For a CDS disk group, alignment can only take a value of 8k. Attempts to set the alignment of a CDS disk group to 1 fail unless you first change it to a non-CDS disk group.

Increasing the alignment may require vxcdsconvert to be run to change the layout of the objects in the disk group.

To display the current alignment value of a disk group, use the vxprint command.

See "Displaying the disk group alignment" on page 265.

To change the alignment value of a disk group

■ Type the vxdg set command:

```
# vxdg -g diskgroup set align={1|8k}
```

The operation to increase the alignment to 8K fails if objects exist in the disk group that do not conform to the new alignment restrictions. In that case, use the vxcdsconvert alignment command to change the layout of the objects:

```
# vxcdsconvert -g diskgroup [-A] [-d defaults file] \
  [-o novolstop] alignment [attribute=value] ...
```

This command increases the alignment value of a disk group and its objects to 8K, without converting the disks.

The sequence 8K to 1 to 8K is possible only using vxdq set as long as the configuration does not change after the 8K to 1 transition.

See "Converting a non-CDS disk group to a CDS disk group" on page 251.

Splitting a CDS disk group

You can use the vxdq split command to create a CDS disk group from an existing CDS disk group. The new (target) disk group preserves the setting of the CDS attribute and alignment in the original (source) disk group.

To split a CDS disk group

■ Use the vxdg split command to split CDS disk groups. See the Veritas Volume Manager Adminstrator's Guide.

Moving objects between CDS disk groups and non-CDS disk groups

The alignment of a source non-CDS disk group must be 8K to allow objects to be moved to a target CDS disk group. If objects are moved from a CDS disk group to a target non-CDS disk group with an alignment of 1, the alignment of the target disk group remains unchanged.

To move objects between a CDS disk group and a non-CDS disk group

■ Use the vxdq move command to move objects between a CDS disk group and a non-CDS disk groups.

See the Veritas Volume Manager Adminstrator's Guide.

Moving objects between CDS disk groups

The disk group alignment does not change as a result of moving objects between CDS disk groups.

To move objects between CDS disk groups

■ Use the vxdg move command to move objects between CDS disk groups. See the Veritas Volume Manager Adminstrator's Guide.

Joining disk groups

Joining two CDS disk groups or joining two non-CDS disk groups is permitted, but you cannot join a CDS disk group to a non-CDS disk group. If two non-CDS disk groups have different alignment values, the alignment of the resulting joined disk group is set to 1, and an informational message is displayed.

To join two disk groups

■ Use the vxdg join command to join two disk groups. See the Veritas Volume Manager Adminstrator's Guide.

Changing the default CDS setting for disk group creation

To change the default CDS setting for disk group creation

■ Edit the /etc/default/vxdg file, and change the setting for the cds attribute.

Creating non-CDS disk groups

A disk group with a version lower than 110 is given an alignment value equal to 1 when it is imported. This is because the dg align value is not stored in the configuration database for such disk groups.

To create a non-CDS disk group with a version lower than 110

- Type the following vxdg command:
 - # vxdq -T version init diskgroup disk name=disk access name

Upgrading an older version non-CDS disk group

You may want to upgrade a non-CDS disk group with a version lower than 110 in order to use new features other than CDS. After upgrading the disk group, the cds attribute is set to off, and the disk group has an alignment of 1.

Note: You must also perform a disk group conversion (using the vxcdsconvert utility) to use the CDS feature.

To upgrade the non-CDS pre-version 110 disk group

■ Type the following vxdg command:

vxdg upgrade diskgroup

Replacing a disk in a CDS disk group

Note: When replacing a disk in a CDS disk group, you cannot use a non-CDS disk as the replacement.

To replace a disk in a CDS disk group

■ Type the following commands:

```
# vxdg -g diskgroup -k rmdisk disk name
# vxdq -q diskqroup -k adddisk disk name=disk access name
```

The -k option retains and reuses the disk media record for the disk that is being replaced. The following example shows a disk device disk21 being reassigned to disk mydg01.

```
# vxdg -g diskgroup -k rmdisk mydg01
# vxdg -g diskgroup -k adddisk mydg01=disk21
```

For other operating systems, use the appropriate device name format.

Setting the maximum number of devices for CDS disk groups

To set the maximum number of devices that can be created in a CDS disk group

■ Type the following vxdg set command:

```
# vxdg -g diskgroup set maxdev=max-devices
```

The maxdev attribute can take any positive integer value that is greater than the number of devices that are currently in the disk group.

Changing the DRL map and log size

If DRL is enabled on a newly-created volume without specifying a log or map size, default values are used. You can use the command line attributes logmap len and loglen in conjunction with the vxassist, vxvol, and vxmake commands to set the DRL map and DRL log sizes. The attributes can be used independently, or they can be combined.

You can change the DRL map size and DRL log size only when the volume is disabled and the DRL maps are not in use. Changes can be made to the DRL map size only for volumes in a CDS disk group.

The logmap len attribute specifies the required size, in bytes, for the DRL log. It cannot be greater than the number of bytes available in the map on the disk.

To change the DRL map and log size

■ Use the following commands to remove and rebuild the logs:

```
# vxassist -g diskgroup remove log volume nlog=0
# vxassist -g diskgroup addlog volume nlog=nlogs \
 logtype=drl logmap len=len-bytes [loglen=len-blocks]
```

Note the following restrictions

If only logmap_len is specified	The DRL log size is set to the default value (33 * disk group alignment).
<pre>If logmap_len is greater than (DRL log size)/2</pre>	The command fails, and you need to either provide a sufficiently large loglen value or reduce logmap_len.
For CDS disk groups	The DRL map and log sizes are set to a minimum of 2 * (disk group alignment).

Creating a volume with a DRL log

To create a volume with a traditional DRL log by using the vxassist command

■ Type the following command:

```
# vxassist -g diskgroup make volume length mirror=2 \
  logtype=drl [loglen=len-blocks] [logmap len=len-bytes]
```

This command creates log subdisks that are each equal to the size of the DRL

Note the following restrictions

If neither logmap_len nor loglen is specified	 loglen is set to a default value that is based on disk group alignment. maplen is set to a reasonable value.
If only loglen is specified	■ For pre-version 110 disk groups, maplen is set to zero.

■ For version 110 and greater disk groups, maplen is set to use all the bytes available in the on-disk map.

If only logmap len is specified

- For pre-version 110 disk groups, logmap len is not applicable.
- For version 110 and greater disk groups, maplen must be less than the number of available bytes in the on-disk map for the default log length.

Setting the DRL map length

To set a DRL map length

- 1 Stop the volume to make the DRL inactive.
- 2 Type the following command:

```
# vxvol -g diskgroup set [loglen=len-blocks] \
  [logmap len=len-bytes] volume
```

This command does not change the existing DRL map size.

Note the following restrictions

If both logmap len and loglen are specified

- if logmap len is greater than loglen/2, vxvol fails with an error message. Either increase loglen to a sufficiently large value, or decrease logmap len to a sufficiently small value.
- The value of logmap len cannot exceed the number of bytes in the on-disk map.
- If logmap len is specified
- The value is constrained by size of the log, and cannot exceed the size of the on-disk map. The size of the on-disk map in blocks can be calculated from the following formula:

```
round(loglen/nmaps) - 24
where nmaps is 2 for a private disk
group, or 33 for a shared disk group.
```

■ The value of logmap len cannot exceed the number of bytes in the on-disk map.

If loglen is specified

- Specifying a value that is less than twice the disk group alignment value results in an error message.
- The value is constrained by size of the logging subdisk.

Displaying information

This section describes the following tasks:

- Determining the setting of the CDS attribute on a disk group
- Displaying the maximum number of devices in a CDS disk group
- Displaying map length and map alignment of traditional DRL logs
- Displaying the disk group alignment
- Displaying the log map length and alignment
- Displaying offset and length information in units of 512 bytes

Determining the setting of the CDS attribute on a disk group

To determine the setting of the CDS attribute on a disk group

■ Use the vxdq list command or the vxprint command to determine the setting of the CDS attribute, as shown in the following examples:

vxdg list

```
STATE
NAME
                            ΙD
dgTestSol2
            enabled,cds
                          1063238039.206.vmesc1
# vxdg list dgTestSol2
Group: dgTestSol2
dgid:
        1063238039.206.vmesc1
import-id: 1024.205
flags: cds
version: 110
alignment: 8192 (bytes)
```

```
# vxprint -F %cds -G -g dgTestSol2
on
```

The disk group, dgTestSol2, is shown as having the CDS flag set.

Displaying the maximum number of devices in a CDS disk group

To display the maximum number of devices in a CDS disk group

■ Type the following command:

```
# vxprint -g diskgroup -G -F %maxdev
```

Displaying map length and map alignment of traditional DRL logs

To display the map length and map alignment of traditional DRL logs

■ Type the following commands

```
# vxprint -q diskgroup -vl volume
# vxprint -g diskgroup -vF '%name %logmap_len %logmap_align' \
 volume
```

Displaying the disk group alignment

To display the disk group alignment

■ Type the following command:

```
# vxprint -q diskgroup -G -F %align
```

Utilities such as vxprint and vxdq list that print information about disk group records also output the disk group alignment.

Displaying the log map length and alignment

To display the log map length and alignment

■ Type the following command:

```
# vxprint -g diskgroup -lv volume
```

For example, to print information for the volume vol1 in disk group dq1:

```
# vxprint -g dg1 -lv vol1
```

The output is of the form:

```
logging: type=REGION loglen=0 serial=0/0 mapalign=0
maplen=0 (disabled)
```

This indicates a log map alignment (logmap align) value of 0, and a log map length (logmap len) value of 0.

If the log map is set and enabled, the command and results may be in the following form:

vxprint -lv drlvol

```
Disk group: dgTestSol
Volume: drlvol
info: len=20480
type:
        usetype=fsgen
state: state=ACTIVE kernel=ENABLED cdsrecovery=0/0 (clean)
assoc: plexes=drlvol-01, drlvol-02, drlvol-03
policies: read=SELECT (round-robin) exceptions=GEN DET SPARSE
flags: closed writecopy writeback
logging: type=REGION loglen=528 serial=0/0 mapalign=16
maplen=512 (enabled)
apprecov: segno=0/0
recovery: mode=default
recov id=0
device: minor=46000 bdev=212/46000 cdev=212/46000
path=/dev/vx/dsk/dgTestSol/drlvol
perms: user=root group=root mode=0600
quid: {d968de3e-1dd1-11b2-8fc1-080020d223e5}
```

Displaying offset and length information in units of 512 bytes

To display offset and length information in units of 512 bytes

■ Specify the -b option to the vxprint and vxdisk commands, as shown in these examples:

```
# vxprint -bm
# vxdisk -b list
```

Specifying the -b option enables consistent output to be obtained on different platforms. Without the -b option, the information is output in units of sectors. The number of bytes per sector differs between platforms.

When the vxprint -bm or vxdisk -b list command is used, the output also contains the b suffix, so that the output can be fed back to vxmake.

Default activation mode of shared disk groups

The default activation mode of shared disk groups involves a local in-kernel policy that differs between platforms. This means that, regardless of the platform on which the disk group was created, the importing platform will have platform-specific behavior with respect to activation of shared disk groups. Specifically, with the exception of HP-UX, importing a shared disk group results in the volumes being active and enabled for shared-write. In the case of HP-UX, the shared volumes will be inactive and require other actions to activate them for shared-write operations.

Additional considerations when importing CDS disk groups

Before you attempt to use CDS to move disk groups between different operating systems, and if the configuration of the disks has changed since the target system was last rebooted, you should consider the following points

Does the target system know about the disks? For example, the disks may not have been connected to the system either physically (not cabled) or logically (using FC zoning or LUN masking) when the system was booted up, but they have subsequently been connected without rebooting the system. This can happen when bringing new storage on-line, or when adding an additional DMP path to existing storage. On the target system, both the operating system and VxVM must be informed of the existence of the new storage. Issue the appropriate command to tell the operating system to look for the storage. (On Linux, depending on the supported capabilities of the host adapter, you may need to reboot the target system to achieve this.) Having done this, run either of the following commands on the target system to have VxVM recognize the storage:

- # vxdctl enable
- # vxdisk scandisks

Do the disks contain partitions or slices?

Both the Solaris and Linux operating systems maintain information about partitions or slices on disks. If you repartition a disk after the target system was booted, use the appropriate command to instruct the operating system to rescan the disk's TOC or partition table. For example, on a target Linux system, use the following command:

blockdev --rereadpt

Having done this, run either of the following commands on the target system to have VxVM recognize the storage:

- # vxdctl enable
- # vxdisk scandisks

any of the disks target system was last booted?

Has the format of For example, if you use the vxdisksetup -i command to format a disk for VxVM on one system, the vxdisk list command on the changed since the target system may still show the format as being auto:none. If so, use either of the following commands on the target system to instruct VxVM to rescan the format of the disks:

- # vxdctl enable
- # vxdisk scandisks

File system considerations

To set up or migrate volumes with VxFS file systems with CDS, you must consider the file system requirements. This section describes these requirements. It also describes additional tasks required for migrating or setting up in CDS.

Considerations about data in the file system

Data within a file system might not be in the appropriate format to be accessed if moved between different types of systems. For example, files stored in proprietary binary formats often require conversion for use on the target platform. Files containing databases might not be in a standard format that allows their access when moving a file system between various systems, even if those systems use the same byte order. Oracle 10g's Cross-Platform Transportable Tablespace is a notable exception; if used, this feature provides a consistent format across many platforms.

Some data is inherently portable, such as plain ASCII files. Other data is designed to be portable and the applications that access such data are able to access it irrespective of the system on which it was created, such as Adobe PDF files.

Note that the CDS facilities do not convert the end user data. The data is uninterpreted by the file system. Only individual applications have knowledge of the data formats, and thus those applications and end users must deal with this issue. This issue is not CDS-specific, but is true whenever data is moved between different types of systems.

Even though a user might have a file system with data that cannot be readily interpreted or manipulated on a different type of system, there still are reasons for moving such data by using CDS mechanisms. For example, if the desire is to bring a file system off line from its primary use location for purposes of backing it up without placing that load on the server or because the system on which it will be backed up is the one that has the tape devices directly attached to it, then using CDS to move the file system is appropriate.

An example is a principal file server that has various file systems being served by it over the network. If a second file server system with a different operating system was purchased to reduce the load on the original server, CDS can migrate the file system instead of having to move the data to different physical storage over the network, even if the data could not be interpreted or used by either the original or new file server. This is a scenario that often occurs when the data is only accessible or understood by software running on PCs and the file server is UNIX or Linux-based.

File system migration

File system migration refers to the system management operations related to stopping access to a file system, and then restarting these operations to access the file system from a different computer system. File system migration might be required to be done once, such as when permanently migrating a file system to another system without any future desire to move the file system back to its original system or to other systems. This type of file system migration is referred to as one-time file system migration. When ongoing file system migration between multiple systems is desired, this is known as ongoing file system migration. Different actions are required depending on the kind of migration, as described in the following sections.

Specifying the migration target

Most of the operations performed by the CDS commands require the target to which the file system is to be migrated to be specified by target specifiers in the following format:

```
os name=name[,os rel=release][,arch=arch name]
[, vxfs version=version][, bits=nbits]
```

The CDS commands require the following target specifiers:

os_name= <i>name</i>	Specifies the name of the target operating system to which the file system is planned to be migrated. Possible values are HP-UX, AIX, SunOS, or Linux. The os_name field must be specified if the target is specified.
os_rel= <i>release</i>	Specifies the operating system release version of the target. For example, 11.31.
arch=arch_name	Specifies the architecture of the target. For example, specify ia or ${\tt pa}$ for HP-UX.
vxfs_version=version	Specifies the VxFS release version that is in use at the target. For example, 5.1.
bits=nbits	Specifies the kernel bits of the target. <i>nbits</i> can have a value of 32 or 64 to indicate whether the target is running a 32-bit kernel or 64-bit kernel.

While os name must be specified for all fscdsadm invocations that permit the target to be specified, all other target specifiers are optional and are available for the user to fine tune the migration target specification.

The CDS commands use the limits information available in the default CDS limits file, /etc/vx/cdslimitstab. If the values for the optional target specifiers are not specified, fscdsadm will choose the defaults for the specified target based on the information available in the limits file that best fits the specified target, and proceed with the CDS operation. The chosen defaults are displayed to the user before proceeding with the migration.

Note: The default CDS limits information file, /etc/vx/cdslimitstab, is installed as part of the VxFS package. The contents of this file are used by the VxFS CDS commands and should not be altered.

Examples of target specifications

The following are examples of target specifications:

Specifies the target operating system and use defaults for os name=AIX the remainder.

os_name=HP-UX, os_rel=11.23, arch=ia, vxfs_version=5.0, bits=64	Specifies the operating system, operating system release version, architecture, VxFS version, and kernel bits of the target.
os_name=SunOS, arch=sparc	Specifies the operating system and architecture of the target.
os_name=Linux, bits=32	Specifies the operating system and kernel bits of the target.

Using the fscdsadm command

The fscdsadm command can be used to perform the following CDS tasks:

- Checking that the metadata limits are not exceeded
- Maintaining the list of target operating systems
- Enforcing the established CDS limits on a file system
- Ignoring the established CDS limits on a file system
- Validating the operating system targets for a file system
- Displaying the CDS status of a file system

Checking that the metadata limits are not exceeded

To check that the metadata limits are not exceeded

■ Type the following command to check whether there are any file system entities with metadata that exceed the limits for the specified target operating system:

```
# fscdsadm -v -t target mount point
```

Maintaining the list of target operating systems

When a file system will be migrated on an ongoing basis between multiple systems, the types of operating systems that are involved in these migrations are maintained in a target list file. Knowing what these targets are allows VxFS to determine file system limits that are appropriate to all of these targets. The file system limits that are enforced are file size, user ID, and group ID. The contents of the target list file are manipulated by using the fscdsadm command.

Adding an entry to the list of target operating systems

To add an entry to the list of target operating systems

■ Type the following command:

```
# fscdsadm -o add -t target mount_point
See "Specifying the migration target" on page 269.
```

Removing an entry from the list of target operating systems

To remove an entry from the list of target operating systems

■ Type the following command:

```
# fscdsadm -o remove -t target mount point
See "Specifying the migration target" on page 269.
```

Removing all entries from the list of target operating systems

To remove all entries from the list of target operating systems

■ Type the following command:

```
# fscdsadm -o none mount point
```

Displaying the list of target operating systems

To display a list of all target operating systems

■ Type the following command:

```
# fscdsadm -o list mount point
```

Enforcing the established CDS limits on a file system

By default, CDS ignores the limits that are implied by the operating system targets that are listed in the target list file.

To enforce the established CDS limits on a file system

■ Type the following command:

```
# fscdsadm -1 enforce mount point
```

Ignoring the established CDS limits on a file system

By default, CDS ignores the limits that are implied by the operating system targets that are listed in the target list file.

To ignore the established CDS limits on a file system

- Type the following command:
 - # fscdsadm -1 ignore mount point

Validating the operating system targets for a file system

To validate the operating system targets for a file system

- Type the following command:
 - # fscdsadm -v mount_point

Displaying the CDS status of a file system

The CDS status that is maintained for a file system includes the following information:

- the target list file
- the limits implied by the target list file
- whether the limits are being enforced or ignored
- whether all files are within the CDS limits for all operating system targets that are listed in the target list file

To display the CDS status of a file system

- Type the following command:
 - # fscdsadm -s mount point

Migrating a file system one time

This example describes a one-time migration of data between two operating systems. Some of the following steps require a backup of the file system to be created. To simplify the process, you can create one backup before performing any of the steps instead of creating multiple backups as you go.

To perform a one-time migration

If the underlying Volume Manager storage is not contained in a CDS disk group, it must first be upgraded to be a CDS disk group, and all other physical considerations related to migrating the storage physically between systems must first be addressed.

See "Converting a non-CDS disk group to a CDS disk group" on page 251.

If the file system is using a disk layout version prior to 7, upgrade the file system to Version 7.

See the Veritas Storage Foundation Installation Guide.

Use the following command to ensure that there are no files in the file system that will be inaccessible after migrating the data due to large file size or to differences in user or group ID between platforms:

```
# fscdsadm -v -t target mount point
```

If such files exist, move the files to another file system or reduce the size of the files.

Unmount the file system:

```
# umount mount point
```

- 5 Use the fscdsconv command to convert the file system to the opposite endian.
 - See "Converting the byte order of a file system" on page 276.
- Make the physical storage and Volume Manager logical storage accessible on the Linux system by exporting the disk group from the source system and importing the disk group on the target system after resolving any other physical storage attachment issues.

```
See "Disk tasks" on page 256.
```

Mount the file system on the target system.

Migrating a file system on an ongoing basis

This example describes how to migrate a file system between platforms on an ongoing basis. Some of the following steps require a backup of the file system to be created. To simplify the process, you can create one backup before performing any of the steps instead of creating multiple backups as you go.

To perform an ongoing migration

Use the following command to ensure that there are no files in the file system that will be inaccessible after migrating the data due to large file size or to differences in user or group ID between platforms:

```
# fscdsadm -v -t target mount point
```

If such files exist, move the files to another file system or reduce the size of the files.

- 2 Add the platform on the target list file:
 - If migrating a file system between the Solaris and Linux, add Sunos and Linux to the target list file:

```
# fscdsadm -o add -t os name=SunOS /mnt1
# fscdsadm -o add -t os name=Linux /mnt1
```

■ If migrating a file system between the HP-UX and Linux, add HP-UX and Linux to the target list file:

```
# fscdsadm -o add -t os name=HP-UX /mnt1
# fscdsadm -o add -t os name=Linux /mnt1
```

Enforce the limits:

```
# fscdsadm -1 enforce mount point
```

This is the last of the preparation steps. When the file system is to be migrated, it must be unmounted, and then the storage moved and mounted on the target system.

Unmount the file system:

```
# umount mount point
```

Make the file system suitable for use on the specified target.

```
See "Converting the byte order of a file system" on page 276.
```

Make the physical storage and Volume Manager logical storage accessible on the target system by exporting the disk group from the source system and importing the disk group on the target system after resolving any other physical storage attachment issues.

```
See "Disk tasks" on page 256.
```

Mount the file system on the target system.

Stopping ongoing migration

To stop performing ongoing migration

Type the following commands:

```
# fscdsadm -l ignore mount point
```

fscdsadm -o none mount point

The file system is left on the current system.

When to convert a file system

When moving a file system between two systems, it is essential to run the fscdsconv command to perform all of the file system migration tasks. The fscdsconv command validates the file system to ensure that it does not exceed any of the established CDS limits on the target, and converts the byte order of the file system if the byte order of the target is opposite to that of the current system.

Warning: Prior to VxFS 4.0 and disk layout Version 6, VxFS did not officially support moving file systems between different platforms, although in many cases a user may have successfully done so. Do not move file systems between platforms when using versions of VxFS prior to Version 4, or when using disk layouts earlier than Version 6. Instead, upgrade to VxFS 4.0 or higher, and disk layout Version 6 or later. Failure to upgrade before performing cross-platform movement can result in data loss or data corruption.

Note: If you replicate data from a little-endian to a big-endian system (or vice versa), you must convert the application after the replication completes.

Converting the byte order of a file system

Use the fscdsconv command to migrate a file system from one system to another.

To convert the byte order of a file system

Determine the disk layout version of the file system that you will migrate:

```
# fstyp -v /dev/vx/rdsk/diskgroup/volume | grep version
```

```
magic a501fcf5 version 9 ctime Thu Jun 1 16:16:53 2006
```

Only file systems with disk layout Version 7 or later can be converted. If the file system has an earlier disk layout version, convert the file system to disk layout Version 7 or later before proceeding.

See the vxfsconvert(1M) manual page.

See the vxupgrade(1M) manual page.

- Perform a full file system back up. Failure to do so could result in data loss or data corruption under some failure scenarios in which restoring from the backup is required.
- Designate a file system with free space where fscdsconv may create a file that will contain recovery information for usage in the event of a failed conversion.

Depending on the nature of the file system to be converted, for example if it is mirrored, you may wish to designate the recovery file to reside in a file system with the same level of failure tolerance. Having the same level of failure tolerance reduces the number of failure scenarios that would require trestoration from the backup.

Unmount the file system to be converted:

```
# umount mount point
```

Use the fscdsconv command to export the file system to the required target:

fscdsconv -f recovery file -t target OS -e special device

target OS specifies the operating system to which you are migrating the file system.

See "Specifying the migration target" on page 269.

recovery file is the name of the recovery file to be created by the fscdsconv command.

special device is the raw device or volume that contains the file system to be converted.

Include the file system that you chose in 3 when designating the recovery file.

For example, if the file system chosen to contain the recovery file is mounted on /data/fs3, the recovery file could be specified as

/data/fs3/jan04recovery. If there is not enough disk space on the chosen file system for the recovery file to be created, the conversion aborts and the file system to be converted is left intact.

The recovery file is not only used for recovery purposes after a failure, but is also used to perform the conversion. The directory that will contain the recovery file should not allow non-system administrator users to remove or replace the file, as this could lead to data loss or security breaches. The file should be located in a directory that is not subject to system or local scripts will remove the file after a system reboot, such as that which occurs with the /tmp and /var/tmp directories on the Solaris operating system.

The recovery file is almost always a sparse file. The disk utilization of this file can best be determined by using the following command:

du -sk filename

The recovery file is used only when the byte order of the file system must be converted to suit the specified migration target.

If you are converting multiple file systems at the same time, which requires the use of one recovery file per file system, record the names of the recovery files and their corresponding file systems being converted in the event that recovery from failures is required at a later time.

- Based on the information provided regarding the migration target, fscdsconv constructs and displays the complete migration target and prompts the use to verify all details of the target. If the migration target must be changed, enter n to exit fscdsconv without modifying the file system. At this point in the process, fscdsconv has not used the specified recovery file.
- If the byte order of the file system must be converted to migrate the file system to the specified target, fscdsconv prompts you to confirm the migration. Enter y to convert the byte order of the file system. If the byte order does not need to be converted, a message displays indicating this fact.
- The fscdsconv command indicates if any files are violating the maximum file size, maximum UID, or maximum GID limits on the specified target and prompts you if it should continue. If you must take corrective action to ensure that no files violate the limits on the migration target, enter n to exit fscdsconv. At this point in the process, fscdsconv has not used the specified recovery file.

If the migration converted the byte order of the file system, fscdsconv created a recovery file. The recovery file is not removed after the migration completes, and can be used to restore the file system to its original state if required at a later time.

- **10** If a failure occurs during the conversion, the failure could be one of the following cases:
 - System failure.
 - fscdsconv failure due to program defect or abnormal termination resulting from user actions.

In such cases, the file system being converted is no longer in a state in which it can be mounted or accessed by normal means through other VxFS utilities. To recover the file system, invoke the fscdsconv command with the recovery flag, -r:

fscdsconv -r -f recovery_file special_device

When the -r flag is specified, fscdsconv expects the recovery file to exist and that the file system being converted is the same file system specified in this second invocation of fscdsconv.

11 After invoking fscdsconv with the -r flag, the conversion process will restart and complete, given no subsequent failures.

In the event of another failure, repeat 10.

Under some circumstances, you will be required to restore the file system from the backup, such as if the disk fails that contains the recovery file. Failure to have created a backup would then result in total data loss in the file system. I/O errors on the device that holds the file system would also require a backup to be restored after the physical device problems are addressed. There may be other causes of failure that would require the use of the backup.

Importing and mounting a file system from another system

The fscdsconv command can be used to import and mount a file system that was previously used on another system.

To import and mount a file system from another system

Convert the file system:

```
# fscdsconv -f recovery file -i special device
```

If the byte order of the file system needs to be converted

Enter y to convert the byte order of the file system when prompted by fscdsconv. If the migration converted the byte order of the file system, fscdsconv creates a recovery file that persists after the migration completes. If required, you can use this file to restore the file system to its original state at a later time.

If the byte order of the file system does not need does not need to be converted. to be converted

A message displays that the byte order of the file system

Alignment value and block size

On the AIX, Linux and Solaris operating systems, an alignment value of 1 is equivalent to a block size of 512 bytes. On the HP-UX operating system, it is equivalent to a block size of 1024 bytes.

The block size on HP-UX is different from that on other supported platforms. Output from commands such as vxdisk and vxprint looks different on HP-UX for the same disk group if the -b option is not specified.

Disk group alignment and encapsulated disks

On the Solaris OS, all native file systems are cylinder aligned. Encapsulating such a disk results in subdisks that are also cylinder aligned. Such alignment will normally not be 8K aligned, but it will be 1K aligned. For the encapsulation process, there is no flexibility as to where on the disk the subdisks must be since the data location is predefined. If an alignment conflict occurs, user intervention is required. If the disk group alignment is 8K this operation will probably fail because this would require the cylinder to be an even number of 8K blocks in size.

Disk group import between Linux and non-Linux machines

A disk group created on a non-Linux system typically has device numbers greater than 1000. When that disk group is imported on a Linux machine with a pre-2.6 kernel, the devices are reassigned minor numbers less than 256.

If a disk group on a Linux system is imported to a non-Linux system, all device numbers will be less than 256. If those devices are available (that is, they do not conflict with devices in an imported boot disk group) they will be used. Otherwise new device numbers will be reassigned.

A single disk group could contain a number of devices exceeding the maximum number of devices for a given platform. In this case, the disk group cannot be imported on that platform because import would exhaust available minor devices for the VxVM driver. Although the case of minor number exhaustion is possible in a homogeneous environment, it will be more pronounced between platforms with different values for the maximum number of devices supported, such as Linux with a pre-2.6 kernel. This difference will render platforms with low maximum devices supported values less useful as heterogeneous disk group failover or recovery candidates.

Note: Using the disk group maxdev attribute may reduce the likelihood that a CDS disk group import on Linux with a per-2.6 kernel will exceed the maximum number of devices.

Migrating a snapshot volume

This example demonstrates how to migrate a snapshot volume containing a VxFS file system from a Solaris SPARC system (big endian) to a Linux system (little endian) or HP-UX system (big endian) to a Linux system (little endian).

To migrate a snapshot volume

- Create the instant snapshot volume, snapvol, from an existing plex in the volume, vol, in the CDS disk group, datadg:
 - # vxsnap -q datadq make source=vol/newvol=snapvol/nmirror=1
- 2 Quiesce any applications that are accessing the volume. For example, suspend updates to the volume that contains the database tables. The database may have a hot backup mode that allows you to do this by temporarily suspending writes to its tables.
- **3** Refresh the plexes of the snapshot volume using the following command:
 - # vxsnap -q datadg refresh snapvol source=yes syncing=yes
- The applications can now be unquiesced.
 - If you temporarily suspended updates to the volume by a database in 2, release all the tables from hot backup mode.
- Use the vxsnap syncwait command to wait for the synchronization to complete:
 - # vxsnap -q datadq syncwait snapvol
- Check the integrity of the file system, and then mount it on a suitable mount point:
 - # fsck -F vxfs /dev/vx/rdsk/datadg/snapvol # mount -F vxfs /dev/vx/dsk/datadg/snapvol /mnt
- 7 Confirm whether the file system can be converted to the target operating system:
 - # fscdstask validate Linux /mnt
- Unmount the snapshot:
 - # umount /mnt

9 Convert the file system to the opposite endian:

```
# fscdsconv -e -f recoveryfile -t target specifiers special
For example:
# fscdsconv -e -f /tmp/fs recov/recov.file -t Linux \
```

This step is only required if the source and target systems have the opposite endian configuration.

10 Split the snapshot volume into a new disk group, miqdq, and deport that disk group:

```
# vxdq split datadq miqdq snapvol
# vxdg deport migdg
```

/dev/vx/dsk/datadg/snapvol

11 Import the disk group, migdg, on the Linux system:

```
# vxdg import migdg
```

It may be necessary to reboot the Linux system so that it can detect the disks.

12 Use the following commands to recover and restart the snapshot volume:

```
# vxrecover -g migdg -m snapvol
```

13 Check the integrity of the file system, and then mount it on a suitable mount point:

```
# fsck -t vxfs /dev/vx/dsk/migdg/snapvol
# mount -t vxfs /dev/vx/dsk/migdg/snapvol /mnt
```

Index

absolute pathnames use with symbolic links 39 access type 241 accessing Quick I/O files with symbolic links 39 activation default 265 AIX coexistence label 241 alignment 243 changing 258 allocating file space 33 analyzing I/O statistics 62-63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 CDS disk groups alignment 258 B B backing up using NetBackup 133 backup of cluster file systems 120 of online databases 97 cache advisory checking setting for 68 cache hit ratio calculating 62-63 Cached Quick I/O customizing 65 determining files to use 61 disabling individual files 65 enabling individual files 65 enabling individual files 65 enabling individual files 65 enabling individual files 66 prerequisite for enabling 57 calculating cache hit ratio 62-63 CDS attribute 264 changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing disk format 256 changing disk format 256 changing file sizes 32 chgrp command 37	Symbols /etc/default/vxassist defaults file 253 /etc/default/vxcdsconvert defaults file 254 /etc/default/vxdg defaults file 254 /etc/default/vxdisk defaults file 254 /etc/default/vxencap defaults file 255 /etc/vx/darecs file 248	backups creating for volumes 87 benefits of Concurrent I/O 70 benefits of Quick I/O 28 block size 239 blockdevrereadpt 268
absolute pathnames use with symbolic links 39 access type 241 accessing Quick I/O files with symbolic links 39 activation default 265 AIX coexistence label 241 alignment 243 analyzing I/O statistics 62-63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 ndcomirror 100, 122 ndisk type 241 B B B B backing up using NetBackup 133 backup of cluster file systems 120 chacking setting for 68 cache hit ratio calculating 62-63 cached Quick I/O calculating 62-63 cache hit ratio calculating 62-63 determining files to use 61 disabling individual files 65 enabling individual files enabling individual files feature in individual files fea		-
use with symbolic links 39 access type 241 accessing Quick I/O files with symbolic links 39 activation default 265 AIX coexistence label 241 alignment 243 changing 258 allocating file space 33 analyzing I/O statistics 62–63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 use with symbolic links 39 cache hit ratio calculating 62–63 Cached Quick I/O customizing 65 determining files to use 61 disabling individual files 65 enabling individual files 66 making settings persistent 66 prerequisite for enabling 57 calculating cache hit ratio 62–63 CDS attribute 264 changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing disk format 256 changing file sizes 32 chepro command 37	A	
access type 241 accessing Quick I/O files with symbolic links 39 activation default 265 AIX coexistence label 241 alignment 243 changing 258 allocating file space 33 analyzing I/O statistics 62-63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 ndcomirror 100, 122 regionsize 103, 150 auto disk type 241 accessing Calculating 62-63 Cached Quick I/O customizing 65 determining files to use 61 disabling individual files 66 making settings persistent 66 prerequisite for enabling 57 calculating cache hit ratio 62-63 CDS attribute 264 changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing disk format 256 changing file sizes 32 chepro command 37	absolute pathnames	
accessing Quick I/O files with symbolic links 39 activation default 265 AIX coexistence label 241 alignment 243 changing 258 allocating file space 33 analyzing I/O statistics 62–63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 Beauto Alignment 246 changing CDS setting 260 changing 268 creating 248 creating disks 247 disk group alignment 240 disk group device quotas 243 alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing default CDS setting 260 changing default CDS setting 260 changing disk format 256 changing disk format 256 changing file sizes 32 chgrp command 37	use with symbolic links 39	
accessing Quick I/O files with symbolic links 39 activation default 265 AIX coexistence label 241 alignment 243 changing 258 allocating file space 33 analyzing I/O statistics 62–63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 B backing up using NetBackup 133 cached Quick I/O customizing 65 determining files to use 61 disabling individual files 65 enabling individual files 66 making settings persistent 66 prerequisite for enabling 57 calculating cache hit ratio 62–63 CDS attribute 264 changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 chgrp command 37	access type 241	_
activation default 265 AIX coexistence label 241 alignment 243 changing 258 allocating file space 33 analyzing I/O statistics 62-63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 B backing up using NetBackup 133 backup of cluster file systems 120 determining files to use 61 disabling individual files 65 enabling individual files 66 making settings persistent 66 prerequisite for enabling 57 calculating cache hit ratio 62-63 CDS attribute 264 changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups setting alignment 265 joining 260 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing disk format 256 changing disk format 256 changing disk format 256 changing file sizes 32 cherp command 37		
activation default 265 AIX coexistence label 241 alignment 243 changing 258 allocating file space 33 analyzing I/O statistics 62–63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 ndcomirror 100, 122 regionsize 103, 150 auto disk type 241 B backing up using NetBackup 133 backup of cluster file systems 120 determining files to use 61 disabling individual files 65 enabling individual files 66 enabling individual files 65 enabling individual files 66 enabling individual files 66 enabling individual files 65 enabling individual files 65 enabling individual files 66 enabling individual files 66 enabling individual files 66 enabling individual files 65 enabling individual files 66 enabling individual files 66 enabling individual files 65 enabling individual files 66 enabling individual files 65 enabling individual files 66 enabling individual files 65 enabling individual files 66 enabling individual files 65 enabling individual files 65 enabling individual files 65 enabling individual files 65 enabling individual files for albiling individual files for abluration for all individual files for abluration for all individual files for abluration for all individual files for all individual files	Quick I/O files with symbolic links 39	ĕ
AIX coexistence label 241 alignment 243 changing 258 allocating file space 33 calculating cache hit ratio 62-63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 ndicomirror 100, 122 regionsize 103, 150 auto disk type 241 B backing up using NetBackup 133 backup of cluster file systems 120 enabling individual files 66 making settings persistent 66 prerequisite for enabling 57 calculating cache hit ratio 62-63 CDS attribute 264 changing setting 260 creating DGs 248 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37		_
alignment 243	default 265	
changing 258 allocating file space 33 analyzing I/O statistics 62-63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 autto disk type 241 B CDS disk B changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks CDS	AIX coexistence label 241	
allocating file space 33 analyzing I/O statistics 62–63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 B B backing up using NetBackup 133 calculating cache hit ratio 62–63 CDS CDS attribute 264 changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing disk format 256 changing file sizes 32 chgrp command 37	alignment 243	
analyzing I/O statistics 62–63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 B B B backing up using NetBackup 133 B backup of cluster file systems 120 CDS attribute 264 changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing file sizes 32 cherp command 37	changing 258	
analyzing I/O statistics 62–63 ARCHIVELOG mode 130 archiving using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 B backing up using NetBackup 133 backup of cluster file systems 120 CDS attribute 264 changing setting 260 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	allocating file space 33	calculating cache hit ratio 62-63
archiving changing setting 260 using NetBackup 133 creating DGs 248 asynchronous I/O 28 creating disks 247 attribute disk group alignment 240 cDS 264 disk group device quotas 243 attributes disks 240 CDS disk groups alignment 265 poining 260 moving 259 setting alignment 258 B B B CDS disk groups alignment 265 poining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 chepp command 37		CDS
using NetBackup 133 asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 regionsize 103, 150 B B backing up using NetBackup 133 backup of cluster file systems 120 attributes cDS 264 creating DGs 248 creating disks 247 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	ARCHIVELOG mode 130	
asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 B B backing up using NetBackup 133 backup of cluster file systems 120 cDS 264 disk group alignment 240 disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	archiving	
asynchronous I/O 28 attribute CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 B backing up using NetBackup 133 backup of cluster file systems 120 cDS disk group device quotas 243 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	using NetBackup 133	•
CDS 264 attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 B B backing up using NetBackup 133 backup of cluster file systems 120 attributes disk group device quotas 243 disk proups alignment 265 poining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 chepro command 37		•
attributes init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 B backing up using NetBackup 133 backup of cluster file systems 120 disks 240 CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	attribute	disk group alignment 240
init 100, 122 ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 B CDS disk groups alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing default CDS setting 260 changing disk format 256 backup of cluster file systems 120 charp command 37	CDS 264	disk group device quotas 243
ndcomirror 100, 122 nmirror 100, 122 regionsize 103, 150 auto disk type 241 B acking up using NetBackup 133 backup of cluster file systems 120 alignment 265 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	attributes	
nmirror 100, 122 regionsize 103, 150 auto disk type 241 B acking up using NetBackup 133 backup of cluster file systems 120 joining 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	init 100, 122	
nmirror 100, 122 regionsize 103, 150 auto disk type 241 B backing up using NetBackup 133 backup of cluster file systems 120 pioning 260 moving 259 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	ndcomirror 100, 122	alignment 265
auto disk type 241 B CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 using NetBackup 133 backup of cluster file systems 120 setting alignment 258 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37		joining 260
CDS disks creating 246 changing CDS setting 260 backing up using NetBackup 133 backup of cluster file systems 120 CDS disks creating 246 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37	regionsize 103, 150	
B creating 246 changing CDS setting 260 backing up changing default CDS setting 260 using NetBackup 133 changing disk format 256 backup changing file sizes 32 of cluster file systems 120 charge command 37	auto disk type 241	
backing up using NetBackup 133 backup of cluster file systems 120 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 cherp command 37		CDS disks
backing up using NetBackup 133 backup of cluster file systems 120 changing CDS setting 260 changing default CDS setting 260 changing disk format 256 changing file sizes 32 charp command 37	R	creating 246
using NetBackup 133 changing derault CD3 setting 200 backup changing file sizes 32 of cluster file systems 120 chgrp command 37		
backup changing disk format 230 of cluster file systems 120 charging file sizes 32 chgrp command 37	U 1	
of cluster file systems 120 charp command 37		
Cite D Collination 37	•	
		chgrp command 37

chmod command	database performance
commands	using Quick I/O 28
chmod 57	databases
chown command 37	incomplete media recovery 131
commands	integrity of data in 88
chown 57	online backup of 97
cluster file systems	rolling back 131
off-host backup of 120	using Storage Checkpoints 129
co-existence label 241	dataserver buffer cache 55
collecting I/O statistics 61	DB2 BufferPool 54
commands	decision support
chgrp 37	using point-in-time copy solutions 144
chown 37	default activation 265
fsadm command 44	default CDS setting
grep 59	changing 260
ls 42	defaults files 249, 253
mount 31	determining
qioadmin 65	if Quick I/O installed and enabled 43
qiomkfile 44, 46	device quotas 243, 265
qiostat 61	displaying 265
setext 37	setting 261
vxtunefs 67	direct I/O 28
concepts 237	direct-write
Concurrent I/O	copy-behind 56
benefits 70	disabling Cached Quick I/O for a file 65
disabling 73-74	disabling Concurrent I/O 73-74
enabling 70, 73	disabling qio_cache_enable flag 58
converting non-CDS disks to CDS 249	disabling Quick I/O 50
converting non-CDS disks to CDS disks 249	disk
convertname	access type 241
displaying device name conversion 211	change format 256
CREADs 64	labels 256
creating	LVM 256
Quick I/O files 34-35	replacing 261
symbolic links to access Quick I/O files 32	disk access 239
creating a DRL log 262	disk format 240
creating CDS disk groups 248	disk group alignment 258
creating CDS disks 246–247	displaying 265
creating DRL logs 262	disk groups 242
creating non-CDS disk groups 260	alignment 243
creating pre-version 110 disk groups 260	creating 260
cross-platform data sharing	joining 260
recovery file 277	non-CDS 243
current-rev disk groups 243	upgrading 260
customizing Cached Quick I/O 65	disk quotas
- ,	setting 261
D	disk types 240
	disks
data on Secondary	effects of formatting or partitioning 267
using for off-host processing 166	· · · · · · · · · · · · · · · · · ·

displaying device quotas 265	fsadm command 44
displaying disk group alignment 265	fscdsadm 271
displaying DRL log size 265	fscdsconv 276
displaying DRL map size 265	
displaying log map values 265	G
displaying log size 265	grep command 59
displaying v_logmap values 265	0 1
displaying volume log map values 265	growing file systems 44
doconvert	Quick I/O files 44
beginning SDS to VxVM conversion 213	Quick I/O files 44
double buffering 28, 54-55	
DRL log size	I
displaying 265	I/O
setting 261	asynchronous 28
DRL logs	direct 28
creating 262	kernel asynchronous 28
DRL map length 263	I/O block size 239
DRL map size	ID block 242
displaying 265	improving
setting 261	database performance 28
DSS. See Decision Support	init attribute 100, 122
**	instant snapshots
E	reattaching 129, 166
-	intent logging 88
enabling	
Quick I/O 31	J
enabling Cached Quick I/O for a file 66	_
enabling Concurrent I/O 70, 73	joining CDS disk groups 260
enabling qio_cache_enable flag 58	joining disk groups 260
encapsulation 256	17
extending a file 32	K
extending Quick I/O files 44	kernel asynchronous I/O 28
	kernel write locks 28
F	
FastResync	L
Persistent 87	length listing 266
file	licensing 253
space allocation 33	listing disk groups 266
file system locking 28	listing disks 266
file systems	listing disks 200 listing offset and length information 260
growing to accommodate Quick I/O files 44	log size
mounting for shared access 122	=
FileSnaps	displaying 265
about 89	setting 261 ls command 42
data mining, reporting, and testing 172	
virtual desktops 171	LVM disks 256
write intensive applications 172	
best practices 171	M
FlashSnap 86	minor device numbers 243
	mount command 31

mounting	qiostat
shared-access file systems 122	output of 62-63
moving CDS disk groups 259	qiostat command 61
moving disk group objects 259	Quick I/O
	accessing regular VxFS files as 39
N	benefits 28
ndcomirror attribute 100, 122	determining status 43
NetBackup	disabling 50
overview 133	enabling 31
nmirror attribute 100, 122	extending files 44
	improving database performance with 28
0	performance improvements 56
	preallocating space for files 37
objects	showing resolution to a raw device 44
moving 259	using relative and absolute pathnames 39
off-host backup of cluster file systems	
using point-in-time copy solutions 120	R
offset	read-ahead algorithm
listing 266	for Cached Quick I/O 56
offset information 266 online database backup	recovery
•	using Storage Checkpoints 129
using point-in-time copy solutions 97 operating system data 239	recovery file, cross-platform data sharing 277
operating system data 239	regionsize attribute 103, 150
D	relative pathnames
P	use with symbolic links 39
persistence	replacing disks 261
for Cached Quick I/O settings 66	resetlogs option 132
Persistent FastResync 87	resizing a file 32
platform block 241	restoring
point-in-time copy solutions	using NetBackup 133
applications 85	restoring CDS disk labels 256
for decision support 144	restoring disk labels 256
for off-host cluster file system backup 120	
for online database backup 97	S
PREADS 64	SDS
preallocating space for Quick I/O files 37	conversion overview 204
preconvert	converting to VxVM 213
setting up SDS for conversion 210	mapping to VxVM objects 201
private region 241	planning for conversion 206
public region 241	post-conversion tasks 214
	preparing for conversion 209
Q	root disk conversion 215
qio_cache_enable flag	setting up for conversion 210
disabling 58	Secondary
enabling 58	using data 166
qioadmin command 65	setext command 37
qiomkfile command 44, 46	setting CDS disk group alignment 258
options for creating files	setting device quotas 261
symbolic links 32	

setting disk quotas 261 setting DRL log size 261 setting DRL map length 263 setting DRL map size 261 setting log size 261 settings making Cached Quick I/O persistent 58 shared access mounting file systems for 122 showconvert displaying SDS conversion plan 211 showing Quick I/O file resolved to raw device 44	vradmin utility ibc using off-host processing 166 vxcdsconvert 249 vxdctl enable 267 vxdg init 248 vxdg split 259 vxdisk scandisks 267 vxdiskadm 247, 249 vxdisksetup 246 vxsnap reattaching instant snapshots 129, 166 vxtunefs command 67
snapshots reattaching instant 129, 166 Solstice DiskSuite migrating from 200 sparse files 41 Storage Checkpoints 88 creating 130 database recovery 129 Storage Rollback implementing using Storage Checkpoints 129 using VxDBA 131 symbolic links advantages and disadvantages 39 to access Quick I/O files 39 system buffer cache 56	commands vxtunefs 59 VxVM devices 239 migrating from SDS 200 vxvol 263
T tunefstab file adding tuning parameters to 58 tuning parameters adding to tunefstab file 58 U upgrading disk groups 260	
upgrading pre-version 110 disk groups 260 utilities. See commands V v_logmap displaying 265 verifying caching using vxfstune parameters 59 verifying vxtunefs system parameters 59 volumes backing up 87	